Configuring outbound-only communication with HP OpenView Operations for UNIX 8

White paper



Abstract	2
Outbound-only communication in OVOPhased enhancement	3
Secure communication through a firewall	
RCP communication through one firewall	
RCP communication through two firewalls	
RCP chaining through multiple levels of firewalls	
Limitations of outbound-only communication	
Outbound-only configuration	
Configuration variables	
Client side (untrusted zone)	
Server side (trusted zone)	
Reverse Channel Proxy	
Command-line interfaces	
Getting started	
Deploying the agent software to the OVO management server	
Deploying software to OVO HTTPS agent systems	
Setting up outbound-only communication	
RCP performance considerations	
One RCP for one OVO HTTPS agent	
One RCP for more than one OVO HTTPS agent (RCP as concentrator)	. 20
Troubleshooting	
Verifying RCP communication from an agent to the server	
Verifying RCP-to-server communication through a firewall	
Verifying the connection to the RCP	
Verifying the OV Core IDs for agents	
Verifying the status of installed certificates on agents	
Verifying the certificate authorities for RCPs and agents	
Verifying the trusted certificates of the server	. 24
Sample customer setups	. 25
Glossary	. 27
Document updates	. 28



Abstract

HP OpenView Operations for UNIX (OVO/UNIX) has been enhanced to provide uni-directional secure communication between OVO management servers and OVO HTTPS agents through multiple firewalls and trust zones. This white paper describes the steps needed to configure OVO to work in this even more secure environment. Before reading this white paper, make sure you have read and understood the HP OpenView Operations for UNIX Firewall Concepts and Configuration Guide and the HP OpenView Operations HTTPS Agent Concepts and Configuration Guide.

Outbound-only communication in OVO

Customers use firewalls to protect their networked environments from intruders who try to penetrate their corporate intranets. Many customers need to manage systems located in sites that are less trusted than the OVO management server site. These systems must be managed through one or more firewalls. In the standard setup, OVO supports communication through firewalls if limited communication from the outside is restricted to certain ports. For details about using OVO in such an environment, refer to the HP OpenView Operations for UNIX Firewall Concepts and Configuration Guide.

For firewalls to offer maximum security, they must completely block traffic from the outside unless it is initiated from the secure (trusted) side of the firewall, as shown in Figure 1.

Figure 1. Initiating agent-server communication today




Figure 1 shows two different types of communication through a firewall:

1. Outbound communication

- Policy and instrumentation deployment
- Heartbeat monitoring
- Application launch
- Remote action launch from the server
- Operator-initiated action launch

2. Inbound communication

- OVO message
- Action response

Phased enhancement

HP OpenView Operations for UNIX (OVO/UNIX) has been enhanced to provide uni-directional secure communication between OVO management servers and OVO HTTPS agents through multiple firewalls and trust zones.

This enhancement includes two phases:

• Phase 1: Reverse Channel Proxy (2006)

Special Reverse Channel Proxy process that provides secure communication between OVO management servers and agents through up to two firewalls.

• Phase 2: Reverse Channel Proxy chaining (2007)

Mechanism that extends the Reverse Channel Proxy process to establish secure communication between OVO management servers and agents through multiple firewalls and trust zones.

Secure communication through a firewall

OVO has been enhanced to provide secure uni-directional communication between the OVO management server and OVO HTTPS agents through a firewall, as shown in Figure 2. A new special-purpose Reverse Channel Proxy (RCP) process (ovbbcrcp) provides the secure link between the server and the agents. The RCP enables secure data flow from an agent (untrusted side) through the firewall to the server (trusted side). All inbound communication from the agent to the server is conducted through an intermediary. The RCP is that intermediary.

Figure 2. Outbound-only communication: Summary (Phase I)




Figure 2 shows two different types of communication through a firewall:

- 1. Communication initiation
- 2. Data flow

Network security

Outbound-only communication includes an OVO management solution that is compliant with company-wide network security policies. All communication between multiple trust zones is initiated only from a trusted zone to an untrusted zone (outbound only). Communication from an OVO management server to an OVO HTTPS agent through a single firewall (outbound) goes through the firewall directly to the agent. All communication from an agent to a server (inbound), as well as all communication between a server and an agent through multiple firewalls, is conducted through an intermediary. Most agent systems can be used to host an RCP. The RCP is included in the agent software. To find out which platforms support RCP, see "Limitations of outbound-only communication" on page 9.

Use cases

Outbound-only communication enables you to do the following

- Run an OVO management server in a secure environment (as shown in Figure 3 in <u>"RCP communication through one firewall"</u> on page 5).
- Run an OVO HTTPS agent in a secure environment, with one RCP between the server and the agent, one firewall between the server and the RCP, and one firewall between the agent and the RCP (as shown in Figure 5 in <u>"RCP communication through two firewalls"</u> on page 7).
- Run RCP on a different system or on the same system as the agent.
- Re-establish outbound-only connections after any of the involved parties has been restarted.
- Run all types of communication required by OVO over the RCP.
- Lock the firewall completely from one side. Outbound-only communication still works.
- Set up an HTTP proxy between a server and an RCP, and between an RCP and an agent.

Firewall configuration

You can configure the firewall to allow communication from any source port on the OVO management server (trusted zone). If necessary, you can further restrict outbound-only communication from the server to specific client port ranges. For details, refer to the HP OpenView Operations for UNIX Firewall Concepts and Configuration Guide.

HP OpenView traffic only

RCP is not a generic proxy. A certificate is needed to set up an Admin Reverse Channel, a communication channel established by an OVO management server to a Reverse Channel Proxy (RCP). The RCP uses the Admin Reverse Channel to establish data channels from clients (OVO HTTPS agents) to a server on request.

Outbound-only communication is designed to cover all HP OpenView traffic using the HTTP Communication Component (BBC). Applications other than OVO/UNIX (for example, OVPM, OVR, and OVIS) are not supported by outbound-only communication. Applications like OVPM do not require outbound-only communication because they communicate from the more secure side to the less secure side (for example, from the same system as the OVO management server to an agent system where OVPA is running).

RCP communication through one firewall

Figure 3 shows how communication between OVO management servers and OVO HTTPS agents using a Reverse Channel Proxy (RCP) works. An RCP can be used for one or more agents. A server establishes a persistent Admin Reverse Channel to an RCP. As long as this Admin Reverse Channel is open, the RCP is able to establish a data channel from an agent to the server.

Figure 3. Outbound-only communication: Details (Phase I)




Figure 3 shows how RCP communication works:

- 1. Admin Reverse Channel
 - a. Server sends a request to the RCP for an Admin Reverse Channel.
 - b. RCP confirms that an Admin Reverse Channel can be opened.
 - c. Persistent Admin Reverse Channel is established between the server and the RCP.
 - d. Agent sends a request to the RCP for a data channel with the server.
- 2. Agent sends data through the new data channel established by the RCP to the server.

In this secure-server scenario, the RCP does the following:

- Runs on the agent system or on a dedicated system.
- Is configured using ovconfchg.
- Acts as a concentrator for multiple OVO HTTPS agents.

An RCP is different from an HTTP proxy:

Advantage of RCP

Unlike an HTTP proxy, RCP can route inbound traffic through a firewall that is completely blocked for inbound traffic.

Disadvantage of RCP


An RCP is able to route traffic for HP OpenView applications (for example, OVO) only. In contrast, an HTTP proxy can route all traffic, but not inbound through the blocked firewall.

NOTE:

You can use one RCP (concentrator) to enable outbound-only communication for multiple OVO HTTPS agents, including agents on HTTPS platforms that do not currently support RCP.

Secure uni-directional communication is also possible with optional HTTP proxies between the server and the RCP, as well as between the OVO HTTPS agents and the RCP, as shown in Figure 4.

Figure 4. Outbound-only communication: Optional HTTP proxies



Firewalls can be located between any of the following:

- 1. OVO management server and HTTP proxy 1
- 2. HTTP proxy 1 and the Reverse Channel Proxy
- 3. Reverse Channel Proxy and HTTP proxy 2
- 4. HTTP proxy 2 and the OVO HTTPS agents

RCP communication through two firewalls

A Reverse Channel Proxy (RCP) can also provide secure communication between OVO management servers and OVO HTTPS agents through two firewalls, as shown in Figure 5. Each connection through a firewall requires its own Admin Reverse Channel, which is the basis for a secure connection through a firewall. For this scenario to work, one Admin Reverse Channel must be established between the server and the RCP, and another Admin Reverse Channel must be established between the agent and the RCP.

Figure 5.Outbound-only communication: High-secure scenario (Phase 1)




Figure 5 shows two different types of communication through a firewall:

- 1. Communication initiation
- 2. Data flow

High secure scenario

A setup with an RCP located between two firewalls works for a high secure scenario with a server behind one firewall and agents located behind another firewall. The server and agents are in trust zones with higher trust than the RCP.

Service provider scenario

The scenario in Figure 5 is also valid for service provider setups, where the OVO management server is run in a service provider intranet, and the OVO HTTPS agents are located at the customer site. From the customer's perspective, the agents are located in a fully trusted site, but the server is not. From the service provider's perspective, the server is located in a fully trusted site, but the agents are not. The server as well as the agents use <code>ENABLE_REVERSE_ADMIN_CHANNELS</code>, <code>RC_CHANNELS</code> (or <code>RC_CHANNELS</code> CFG_FILES), and <code>PROXY</code>.

RCP chaining through multiple levels of firewalls

A mechanism, known as RCP chaining, can be used to establish secure uni-directional communication between OVO management servers and OVO HTTPS agents through multiple firewalls and multiple trust zones, as shown in Figure 6. Full support for this functionality will be added in 2007. At that time, it will also be possible to explicitly enable or disable encryption of the data being transmitted between systems, thus making it possible for the data to be inspected and filtered in real time.

Figure 6. Outbound-only communication: High-secure scenario (Phase 2)




Figure 6 shows RCP chaining using multiple trust zones:

- 1. Plain text between the server and the first RCP.
- 2. Encryption between the agents and the remaining RCPs.

Switching from encryption to plain text enables content filtering in more secure network domains.

NOTE:

Full SSL-based authentication is still active.

Each trust zone has an inspection point and an RCP backup in case the primary RCP is not available.

Limitations of outbound-only communication

Outbound-only communication has the following limitations:

Windows

Outbound-only communication is supported on Windows, but RCP running on Windows is not supported. To use a Windows system with outbound-only communication, set [bbc.http] PROXY on the Windows system to use an RCP running on a supported platform.

Tru64

Outbound-only communication is supported on Tru64, but RCP running on Tru64 is not supported. To use a Tru64 system with outbound-only communication, set [bbc.http] PROXY on the Tru64 system to use an RCP running on a supported platform.

Platforms

The initial release of outbound-only communication does not yet support all OVO HTTPS agent platforms. For the most detailed and up-to-date platform support information, check the "OVO UNIX Support Matrix" at one of the following locations:

http://support.openview.hp.com/sc/support matrices.jsp

http://partners.openview.hp.com/ovcw/pricing/config_matrix.jsp

To access the "Operations" product support matrix, a user identification (HP Passport) is required. To use an OVO HTTPS agent with outbound-only communication on a platform that does not support an RCP, you can use an RCP running on a supported platform and set [bbc.http] PROXY on the agent to use that RCP.

Make sure that the platform support matrix really does contain information that is more up-to-date than this white paper. The platform support information must be from December 2006 or later.

Backup proxies

Outbound-only communication does not yet support backup proxies (HTTP and RCP). Support for backup proxies is planned for Phase 2. In the interim, third-party mechanisms (for example, Cisco Local Director) will work for HTTP proxies but not for RCPs. If an RCP fails, you must restart it using over -restart ovbberge.

The OVO/UNIX 8.24 management server patch will provide outbound-only support for the following scenarios:

- OVO/UNIX 8 manager-to-manager HTTPS communication
- OVO/UNIX 8 Java GUI to OVO/UNIX 8 manager HTTPS communication

In most use cases of OVPM, OVPA, and OV Service Reporter integrated with OVO, communication is initiated from the trusted side (outbound from the OVO management server). In these use cases, no RCP is involved.

Outbound-only configuration

Configuring OVO to handle outbound-only communication needs to be done at the OVO management server (trusted zone), RCP, and the client (untrusted zone). The RCP can be located on a separate dedicated machine, or it can be co-located on client machines.

Configuration variables

You can change configuration variables while processes are running.

CAUTION:

You must not change the CHROOT_PATH while the CB is running.

Client side (untrusted zone)

The client side is usually an OVO HTTPS agent system in an untrusted zone. Clients must be configured to use an RCP for given targets (typically, OVO management servers).

The RCP entry must be configured as a list of RCPs in the [bbc.http] name space using ovconfchg. The syntax is identical to the syntax used for configuring communication using an HTTP proxy. For examples of how to apply this and other configuration settings, see "Getting started" on page 17.

```
[bbc.http]
PROXY=rcp1:port1+(a) - (b);rcp2:port2+(c) - (d);...
TARGET_FOR_RC=<OV Core ID>
TARGET_FOR_RC CMD=<script | command>
```

Syntax

PROXY

Defines which proxy and port to use for a certain hostname.

Format:

```
PROXY=rcp1:port1+(a)-(b);rcp2:port2+(c)-(d);...
```

- Denotes a comma- or semicolon-delimited list of hostnames, IP addresses, or both with wildcards that use the proxy rcp1.
- b Exclusions. Denotes a comma- or semicolon-delimited list of hostnames, IP addresses, or both that match a but do *not* use the proxy rcp1.
- Denotes a comma- or semicolon-delimited list of hostnames, IP addresses, or both with wildcards that use the proxy rcp2.
- d Exclusions. Denotes a comma- or semicolon-delimited list of hostnames, IP addresses, or both that match c but do *not* use the proxy rcp2.

```
TARGET FOR RC
```

OV Core ID. If this parameter is set, the RCP validates against the core id of the target CB (typically, the CB of the OVO management server). This setting is useful in cases where the OVO management server hostname is not resolvable on the RCP (for example, because of firewalls located between the RCP and the server). An OVO HTTPS agent uses <code>TARGET_FOR_RC</code> to uniquely identify the server that the agent is trying to reach using the RCP.

```
TARGET FOR RC CMD
```

Script or command name. If this parameter is set, the RCP validates against the core id of the target CB. For this setting to work, the output of the script or command must be a valid OV Core ID. If both TARGET_FOR_RC and TARGET_FOR_RC_CMD are specified, TARGET_FOR_RC takes precedence.

Example

```
PROXY=pnode.net.hp.com:1025+(*.*.hp.com)-(pnode.net.hp.com,pnode,*.noallow.hp.com)
```

In this example, the RCP on system <code>pnode.net.hp.com</code> is used with port 1025 while trying to reach any host that matches *.*.hp.com (for example, <code>host1.dmz.hp.com</code>, but not <code>server1.noallow.hp.com</code>). It is also possible to use IP addresses instead of hostnames. For example, <code>16.*.*.*</code> could be specified when identifying hosts.

IMPORTANT:

For correct operation, you must specify the RCP system name itself in the exclude list, so communication using the RCP does not loop at the RCP itself. For this reason, <code>pnode.net.hp.com</code> is already inside the exclude list of the above example.

Server side (trusted zone)

The server side is usually the OVO management server's communication broker (CB). To enable inbound communication from clients, the server must be configured to enable communication using an RCP.

During the CB startup, and whenever the CB configuration is changed using ovconfchg, the CB loads the configuration. The CB establishes the necessary Admin Reverse Channels internally.

Syntax

```
ENABLE REVERSE ADMIN CHANNELS
```

Permanent Admin Reverse Channel to the RCPs given in RC_CHANNELS is established only if this is set to true. This parameter is mandatory for outbound-only communication.

```
RC CHANNELS
```

List of RCPs to establish Admin Reverse Channels. This is a mandatory parameter for outbound-only unless RC CHANNELS CFG FILES is used instead.

Format:

```
<rcp1>:<rcp1 port>[,<rcp1 OvCoreID>][;<rcp2>....]
```

OV Core ID is optional, and is comma-separated. If this parameter is set, the CB validates against the core id of the RCP.

Set RC CHANNELS using the following command:

```
"ovconfchg -ns bbc.cb -set RC CHANNELS < rcp>:< rcp port>"
```

A semicolon-separated list of additional RCPs can be appended.

Note that the <code>-ovrg server</code> option is necessary in the <code>ovconfchg</code> call only when you are running on a high-availability (HA) cluster. For stand-alone OVO management servers, do not use this option when setting <code>RC CHANNELS</code>.

If the server runs as an HA resource group, use the following command:

```
"ovconfchg -ovrg server -ns bbc.cb -set RC CHANNELS < value>"
```

```
RC CHANNELS CFG FILES
```

Format: <filename>

The file with the specified name must be placed in the <DataDir>/conf/bbc directory. This file can contain a list of one or more RCPs. Each line can contain only one RCP name. For each RCP, a port number must be specified.

The OV Core ID is optional, separated from the port number by a comma:

```
<rcp>:<port>[,<rcp OvCoreID>]
```

Blank lines and comment lines (# is the first character) are permitted. The CB attempts to contact RCPs, as specified in RC_CHANNELS and RC_CHANNELS_CFG_FILES. If you change RCP hostnames inside the file specified by RC_CHANNELS_CFG_FILES, you will need to use ovconfchg to trigger the CB to reread the configuration.

One way to trigger the CB to reread the configuration is to use the following:

```
"ovconfchg -ns bbc.cb -set ENABLE REVERSE ADMIN CHANNELS true"
```

In general, if you are using many RCPs, where RCP hostnames are often changed, use RC_CHANNELS_CFG_FILES rather than the RC_CHANNELS setting.

```
RETRY INTERVAL
```

Time interval, in seconds, of each retry for establishing an Admin Reverse Channel to an RCP.

Set this interval using the following command:

```
"ovconfchg -ns bbc.cb -set RETRY INTERVAL 120"
```

The default value is 60 seconds.

```
MAX RECONNECT TRIES
```

Number of times that a CB attempts to establish an admin channel. When this number is reached, the CB stops attempting to establish the channels, and the failure is logged.

Example

```
[bbc.cb]
```

```
RC CHANNELS=pnode.net.hp.com:1025
```

In this example, the OVO management server CB attempts to contact the RCP on agent pnode.net.hp.com on port 1025 when starting up.

IMPORTANT:

On UNIX and Linux systems, the CB runs in chroot context with \(\narropt/Opt/OV / \) as its root directory. It will not be able to create connections to RCPs because it cannot locate \(/etc \), where the configuration files relevant to name services are located. These files are needed for opening TCP connections.

Workground A

Workaround A is more secure than Workaround B, but requires more maintenance (the hosts file must be updated regularly).

1. Create the following directory:

```
/var/opt/OV/etc
```

(The CB is chroot-ed to /var/opt/ov. When chroot-ed (the initial default setting), the CB is unable to access the file system root directory. The directory /var/opt/ov/etc is viewed as /etc by the CB.)

2. Copy the files relevant to the name service to the following directory:

```
/var/opt/OV/etc
```

Examples:

```
/etc/resolv.conf
/etc/hosts
/etc/nsswitch.conf
```

NOTE:

Using a symbolic link will not work. Also, it would defeat the purpose of using the chroot feature.

Workaround B

Workaround B is less secure than workaround A because, with the chroot feature disabled, the CB, the RCP, or both can access all files and directories on the host system.

Disable the ovbbccb chroot feature with the following:

```
ovconfchg -ns bbc.cb -set CHROOT PATH /
```

CAUTION:

Before adding, removing, or changing the CHROOT_PATH setting, you must stop the CB using ovc -kill.

Workaround C

Workaround C works only on the OVO management server side, and only if all RC_CHANNELS entries are IP addresses and not hostnames.

Use the IP address instead of the hostname. No name resolution is needed. The CB does not need to know the RCP hostname.

Reverse Channel Proxy

The Reverse Channel Proxy (RCP) provides the secure link between the OVO management servers and the OVO HTTPS agents.

```
[bbc.rcp]
SERVER PORT=0
                                  //Default='9090'
```

Syntax

SERVER PORT

RCP port number. This is a mandatory parameter for outbound-only.

Set this parameter using the following command:

"ovconfchg -ns bbc.rcp -set SERVER PORT < RCP port>"

By default, ovbbcrcp (RCP process) is not controlled by ovcd (OvCtrl, the OV Control Component).

You must explicitly register ovbbcrcp with ovctrl, as follows:

\$OvInstallDir/bin/ovcreg -add \

\$OvInstallDir/newconfig/DataDir/conf/bbc/ovbbcrcp.xml

For example, for Solaris, you would register ovbbcrcp as follows:

/opt/OV/bin/ovcreg -add \
/opt/OV/newconfig/DataDir/conf/bbc/ovbbcrcp.xml


For outbound-only, ovc -start should be used to start ovbbcrcp,

together with the other registered processes.

For details about the ovbbcrcp command-line interface, see "Command-<u>line interfaces</u>" on page 16.

The system on which the RCP is running requires a "Trusted" and a "Node" certificate from the OVO management server (like any OVO HTTPS agent).

Figure 7. Sample RCP configuration



1. **OVO management server** (myserver.serverdomain.com)

```
[bbc.cb]

RC_CHANNELS=myrcp.mydomain.com:1025

ENABLE REVERSE ADMIN CHANNELS=true
```

2. Reverse Channel Proxy (myrcp.mydomain.com)

```
[bbc.rcp]
SERVER PORT=1025
```

3. OVO HTTPS agent (myagent.mydomain.com)

```
[bbc.http]
```

PROXY=myrcp.mydomain.com:1025+(*)-(myrcp.mydomain.com,myrcp,myagent.mydomain.com,myagent)

Command-line interfaces

OVO provides a command-line interface (CLI) tool, called ovbbcrcp, with the following functionality: ovbbcrcp

Starts the RCP as a background process. Options include the following:

```
-h|-help
```

Displays and describes the available options for the ovbbcrcp command.

-v|version

Displays the version of the OVO RCP in use.

-kill

Stops the RCP.

-status

Displays the RCP status.

Getting started

This section includes step-by-step instructions that show you how to set up outbound-only communication between an OVO management server and OVO HTTPS agents using a Reverse Channel Proxy (RCP), as shown in Figure 3 in <u>"RCP communication through one firewall"</u> on page 5.

NOTE:

For outbound-only communication, the following minimum patch levels are required.

- OVO/UNIX Management Server: A.08.23 Server Patch and A.08.16 Core Agent Patch
- OVO HTTPS Agent RCP: A.08.16 (Core Agent) The A.08.16 Core Agent patch level includes HPOvBbc 06.00.052, HPOvConf 01.10.030, HPOvCtrl 01.50.240, HPOvSecCC 01.00.170, HPOvSecCo 02.20.070, and HPOvXpl 02.61.083.

If no RCP will be running on an agent system, no special patch level is required for that system. However, [bbc.http] PROXY must be set to route agent requests to a system with a running RCP that is able to connect to the server system.

Deploying the agent software to the OVO management server

To deploy the agent software to the server (or on a cluster, to all cluster nodes), follow these steps:

- 1. Open the Motif Administrator GUI Node Bank.
- Select Actions → Agents → Install / Update SW.

NOTE:

Most of the time it is not necessary to activate the Force Update checkbox. Doing so greatly increases the time required to install the software.

- 3. Click **OK** to start the installation process.
- 4. Shut down all server processes completely using ovstop and restart them using ovstart.

Deploying software to OVO HTTPS agent systems

Depending on the number of firewalls you have, or on your company procedures, it may not be possible to deploy agent software for new agents automatically. If you use manual agent installation, it is recommended that you use the bbc.inst.defaults mechanism to efficiently duplicate frequently used settings (for example, [bbc.http] PROXY and [bbc.rcp] SERVER_PORT) to multiple agents when installing them. For details, refer to the manual installation section of the HP OpenView Operations HTTPS Agent Concepts and Configuration Guide.

Setting up outbound-only communication

To set up outbound-only communication, follow these steps:

1. On the OVO management server system, use ovconfchg -set or ovconfchg -edit to set the ENABLE REVERSE ADMIN CHANNELS and RC CHANNELS configuration variables.

In the examples below, 1025 is used as the RCP port number.

Example 1:

```
ovconfchg -ns bbc.cb -set ENABLE_REVERSE_ADMIN_CHANNELS true ovconfchg -ns bbc.cb -set RC CHANNELS myrcp.mydomain.com:1025
```

Example 2: (if your server is a cluster system)

```
ovconfchg -ovrg server -ns bbc.cb -set ENABLE_REVERSE_ADMIN_CHANNELS \
true
ovconfchg -ovrg server -ns bbc.cb -set RC_CHANNELS \
myrcp.mydomain.com:1025
```

IMPORTANT

You must use the <code>-ovrg server</code> option for these two variables if your OVO management server is a cluster system.

2. Apply one of the workarounds described in "Server side (trusted zone)" on page 12.

If you apply Workaround B, remember to stop the OVO management server CB before making the change.

3. On the OVO HTTPS agent, set the PROXY configuration variable to use the RCP to communicate with the server.

Example:

```
ovconfchg -ns bbc.http -set PROXY \
"myrcp.mydomain.com:1025+(*)-(myrcp.mydomain.com,myrcp)"
```

In this example, the agent and RCP are on the same machine.

NOTE:

If the agent and RCP are running on separate systems, remember to add ",myagent.mydomain.com,myagent" to the exclude part of the PROXY setting.

- 4. On the agent system, restart the message agent process with ovc -restart opcmsga.
- 5. On the RCP system, use ovconfchg -set or ovconfchg -edit to set the SERVER_PORT configuration variable.

Example:

```
ovconfchg -ns bbc.rcp -set SERVER PORT 1025
```

In this example, the RCP and agent are on the same machine.

6. On the RCP system, register ovbbcrcp with ovc so that this process will be started, stopped, and monitored by ovc.

Examples:

- UNIX or Linux

```
/opt/OV/bin/ovcreg -add \
/opt/OV/newconfig/DataDir/conf/bbc/ovbbcrcp.xml
```

Windows

```
cd "c:\program files\hp openview\newconfig\datadir\conf\bbc"
"c:\program files\hp openview\bin\ovcreg" -add ovbbcrcp.xml
```

7. On the RCP system, start the ovbbcrcp process with ovc -start.

Use ovbbcrcp -status to check the status of the process. The output must include a line with bbc.rcp and the port number on which the RCP is listening.

Also, within one minute, ovbbcrcp -status should list the accepted Admin Reverse Channel Connection from the OVO management server.

On the server system, ovbbccb -status should list the successfully opened "HP OpenView HTTP Communication Reversal Channel Connection" to

```
myrcp.mydomain.com:myrcpportnumber.
```

If you run into problems, see <u>"Troubleshooting"</u> on page 21.

- 8. Test the connection on the agent using the following:
 - bbcutil -gettarget myserver.serverdomain.com
 The output should show that all agent communication will be routed using the proxy myrcp.mydomain.com:myrcpportnumber.
 - bbcutil -ping myserver.mydomain.com

The output should include status=eServiceOK and the OV Core ID of the OVO management server. It is good practice to carefully verify that this OV Core ID is the correct OV Core ID.

- Send a message (for example, using opensg). Verify that the message arrives in the message browser of the operator or administrator GUI.
- Verify that the agent is not buffering messages. One way to do this is to run
 /opt/OV/bin/opcagt on UNIX or Linux. The output should state that the agent is not
 buffering messages. If it is buffering, wait two minutes, and run the command again. If it is still
 buffering, verify that all OVO management server processes are running.
- 9. Test the connection on the OVO management server using the following:
 - bbcutil -gettarget myrcp.mydomain.com

The output should show that all communication will be routed directly to myrcp.mydomain.com:383. If the CB on myrcp has a different [bbc.cb] SERVER_PORT configured (for example, a non-root agent), the corresponding [bbc.cb.ports] PORTS must be set on the server. (To find out how to run agents under alternative users, refer to the HP OpenView Operations HTTPS Agent Concepts and Configuration Guide.) In this case, all communication will be routed to the SERVER PORT configured for that agent.

- bbcutil -ping myrcp.mydomain.com

The output should include status=eServiceOK and the OV Core ID of the agent. It is good practice to carefully verify that this OV Core ID is the correct OV Core ID.

-/opt/OV/bin/OpC/opcragt myrcp.mydomain.com

The output should list all agent processes as running and the message agent as not buffering.

RCP performance considerations

To ensure proper performance, make sure that the RCP system can service incoming requests fast enough.

One RCP for one OVO HTTPS agent

For a system hosting one RCP for one agent, meeting the minimum requirements for an agent system is sufficient. If you are planning to use one RCP for each agent (located on the same system), system performance will not be significantly impacted by this single additional process.

One RCP for more than one OVO HTTPS agent (RCP as concentrator)

For a system hosting one RCP for more than one agent, meeting the minimum requirements for an agent system may not be sufficient. If you are planning to use one RCP for more than one agent system, you must ensure that the RCP system will be able to service all incoming requests fast enough.

Incoming requests are serviced on a first-come, first-served basis (FIFO queue). No additional disk space is required for the RCP system. Usage of CPU capacity by the RCP is roughly comparable to that of the OVO management server BBC message receiver process (opensgrb).

If an RCP has open Admin Reverse Channel Connections to more than one server, and if communication with one of the servers is interrupted, this interruption will not adversely affect communication with the other servers. If the RCP gets overloaded, message throughput will drop. However, sufficient safeguards are in place to ensure that no messages will be lost in transit (as long as the hard disks and file systems are functioning correctly).

HTTPS outbound-only communication between the agent and the server uses an end-to-end SSL handshake/authentication. No SSL stops occur between the server and the agent. As a result, no data is buffered by the RCP.

Troubleshooting

For additional troubleshooting information, refer to the following documents:

- HP OpenView Operations HTTPS Agent Concepts and Configuration Guide
- HP OpenView Operations for UNIX Firewall Concepts and Configuration Guide

Verifying RCP communication from an agent to the server

To verify that the agent system configuration correctly routes agent requests to the OVO management server using Reverse Channel Proxy (RCP), use the following command:

```
/opt/OV/bin/bbcutil -gettarget <management server hostname>
```

The output should look something like this:

```
HTTP Proxy: myrcp.mydomain.com:1025 (126.157.135.32)
```

NOTE:

The bbcutil command cannot differentiate between a regular HTTP proxy and an RCP. In this example, the RCP must be running on myrcp.mydomain.com using port 1025 for RCP communication to work correctly.

Verifying RCP-to-server communication through a firewall

To verify that an Admin Reverse Channel was correctly set up to the Reverse Channel Proxy (RCP), use the following command on the OVO management server:

```
/opt/OV/bin/ovbbccb -status
```

Check the last section of the output from this command, which is entitled "HP OpenView HTTP Communication Reverse Channel Connections."

The command output should look something like this:

```
HP OpenView HTTP Communication Reverse Channel Connections
Opened:

tcpc50.mydomain.com:1025 BBC 06.00.041; ovbbcrcp 06.00.041

tcvm1119.mydomain.com:1025 BBC 06.00.041; ovbbcrcp 06.00.041

ichthys.mydomain.com:1025 BBC 06.00.041; ovbbcrcp 06.00.041

blauber.mydomain.com:1025 BBC 06.00.041; ovbbcrcp 06.00.041

Pending:

myrcp.mydomain.com:1025 Connection To Host Failed

sagar.mydomain.com:1025 Connection To Host Failed

tcdhcp1118.mydomain.com:1025 Connection To Host Failed
```

The Opened connections were established successfully. Some connections are pending because communication between the server and the RCP is not working. Such a communication problem can occur if a port is blocked by the firewall for this destination port (outbound, see Figure 1 in "Outbound-only communication in OVO" on page 2), another application is listening on the same port, an agent system has no route to the server, and so on.

Verifying the connection to the RCP

If you run ovbbccb -status, and receive the error message Connection to Host Failed with a status of Error Unknown, you need to verify the connection to the host. (For more about ovbbccb -status, see "Verifying RCP-to-server communication through a firewall" on page 21).

To verify the connection to the RCP, check the following:

RCP port number

Check the port number to which the CB on the OVO management server tries to connect. It is configured in RC_CHANNELS (or RC_CHANNELS_CFG_FILES) on the server.

Is :port number attached after the hostname?

- Correct: myrcp.mydomain.com:1025
- Incorrect: myrcp.mydomain.com

If the port number is configured correctly, check for the correct spelling of the RCP hostname, the fully qualified name, or the IP address (in case you specified an IP address instead of a hostname) configured in [bbc.cb] RC_CHANNELS. (If you used RC_CHANNELS_CFG_FILES, check the RCP name or IP address in the files).

Firewall

Is the firewall open for this destination port (outbound, see Figure 1 in <u>"Outbound-only communication in OVO"</u> on page 2)?

RCP port

On the RCP, check the RCP port using ovbbcrcp -status. Does this display the RCP as running on the same port number as configured for the RC CHANNELS on the server?

DNS setup

Depending on your DNS, it is possible that some agents may not be able to establish communication to the server. In this case, you can set <code>TARGET_FOR_RC</code> to the OV Core ID of the server. If the server is a cluster system, use the OV Core ID of the virtual node. For details, see "Client side (untrusted zone)" on page 10.

Verifying the OV Core IDs for agents

Another problem that causes communication between OVO management server and agent to fail is a null OV Core ID for the agent system in the OVO management server database. This null OV Core ID can occur when the agent software is installed manually or a node is added to the OVO Node Bank although it is already configured.

To check for an OV Core ID mismatch, follow these steps:

- 1. Open the OVO Motif Administrator GUI.
- 2. Right-click the node in question.
- 3. From the shortcut menu, select **Modify**.
- 4. In the Modify Node window, click **Communication Options**.

The OV Core ID must match the OV Core ID as output by the <code>/opt/OV/bin/ovcoreid</code> command on the agent.

If the OV Core ID is all zeroes (000...), you must update the OV Core ID in the OVO management server database using this command:

/opt/OV/bin/OpC/utils/opcnode -chg id node name=myrcp.mydomain.com id="mycoreid"

Verifying the status of installed certificates on agents

A system running on the untrusted side of a firewall must have a valid OVO certificate for HTTPS communication to work between the agent and the OVO management server.

To check the status of installed certificates on the agent, use the following:

```
/opt/OV/bin/ovcert -list
```

The output should look something like this:

The Certificates section must contain a line with the OV Core ID of the agent system.

To see the OV Core ID, use the following:

```
/opt/OV/bin/ovcoreid
```

The Trusted Certificates section must contain a line with the OV Core ID of the OVO management server. If the server is a cluster, the OV Core ID of the virtual node must appear in this list.

In a MoM environment, you will see a certificate authority (CA) certificate for each of the MoM servers, as shown in the example.

For details on how to correctly issue and install certificates on agents, refer to the HP OpenView Operations HTTPS Agent Concepts and Configuration Guide.

Verifying the certificate authorities for RCPs and agents

When the agent is on a different system than the RCP, and the RCP was installed from another OVO management server (MoM environment), it is possible for communication to fail with SSL-related errors reported in the System.txt error log file. Verify that both certificate authorities (CAs) are among the trusted certificates of the agent and the RCP.

To get the Issuer CA of a certificate, use following command:

```
ovcert -certinfo `ovcoreid`| grep "Issuer CN"
```

Verify that the Issuer CA is listed in the Trusted Certificates section of ovcert -list on the other node:

```
ovcert -list
```

If the trusted certificate is not known on one of the two systems, exchange the trusted certificates from the agent to the RCP system, and from the RCP system to the agent.

To export the trusted certificates from the agent to the RCP system, follow these steps:

1. Export the trusted certificates from the agent:

```
ovcert -exporttrusted -file /tmp/trusted
```

2. Copy the file /tmp/trusted to the RCP system and import the certificates:

```
ovcert -importtrusted -file /tmp/trusted
```

To export the trusted certificates from the RCP system to the agent, follow these steps:

1. Export the trusted certificates from the RCP system:

```
ovcert -exporttrusted -file /tmp/trusted
```

2. Copy the file /tmp/trusted to the agent and import the certificates:

```
ovcert -importtrusted -file /tmp/trusted
```

For more information about security in MoM environments, refer to the HP OpenView Operations HTTPS Agent Concepts and Configuration Guide.

Verifying the trusted certificates of the server

Verify that the server can communicate with the agent:

```
/opt/OV/bin/OpC/opcragt myrcp.mydomain.com
```

If you get SSL errors, run this command:

```
ovcert -list
```

Verify that all of the trusted certificates from the keystore OVRG server are also available in the agent keystore (first section).

If they are not, update the trusted certificates:


ovcert -updatetrusted

For a server in a cluster environment, repeat this step on all of the physical nodes of the cluster.

Sample customer setups

This section shows how some customers have set up OVO/UNIX with outbound-only communication. Figure 8 shows a sample customer setup with an OVO/UNIX management server cluster.

Figure 8. OVO/UNIX management server cluster



OVO/UNIX
management server

OVO/UNIX
management server

OVO/UNIX
management server
backup

100 outbound
OVO HTTPS agents with NAT between the server and agents

1 RCP per outbound agent, running on the same system

CB = communication broker
RCP = Reverse Channel Proxy
NAT = Network Address Translation

Figure 9. OVO/UNIX management server, backup server, and outbound OVO HTTPS agents

Glossary

Admin Reverse Channel Connection

HTTPS connection initiated by a CB in a high trust zone through a firewall to a RCP in a low or medium trust zone. The connection remains open until it is closed by the CB or the RCP. The connection is used by the RCP to "tunnel" connections from systems in the low or medium trust zone to the CB in the high trust zone.

CB

communication broker. HP OpenView process that enables other processes to communicate with nodes through a single TCP port.

HTTP Tunneled Connection

HTTPS connection from a system in a medium or low trust zone to a CB in a high trust zone, through a firewall. An RCP in the medium or low trust zone "tunnels" this connection through the firewall. An HTTP Tunneled Connection can be established only if the CB in the high trust zone has an open Admin Reverse Channel Connection to the RCP.

outbound-only communication

TCP/IP communication through a firewall. For this type of communication, the firewall is configured such that a trusted system is able to send data out through the firewall, typically using any TCP port. After this specific port is opened by the trusted system, the untrusted system on the other side of the firewall can send data back to the trusted system on the open port. The trusted system controls when and for how long ports are opened. If no ports are open, no untrusted system can send data through the firewall to the trusted system.

ovbbcrcp

Command-line utility that starts and stops the RCP as a background process on an OVO HTTPS agent system.

OVPA

OpenView Performance Agent

OVPM

OpenView Performance Manager

RCP

Reverse Channel Proxy. HP OpenView process (ovbbcrcp) that can provide a secure link between two systems, using the HTTPS protocol. Used to allow outbound-only communication through firewalls.

trust zone

Network separated from other networks by at least one firewall. Network traffic originating from a low trust zone is normally blocked by the firewall, and is thus normally unable to reach systems in a high trust zone on the other side of the firewall.

trusted site

Site that is trusted by another communications party. It can contain multiple trust zones.

Document updates

The first page of this document contains the version number, which indicates the software version.

The last page of this document contains the publish date, which changes each time the document is updated.

To check for recent updates, or to verify that you are using the most recent edition, visit the following URL:

http://ovweb.external.hp.com/lpe/doc_serv/

- 1. In the Product list, click the product name.
- 2. In the Version list, click the version number.
- 3. In the OS list, click the OS type.
- 4. In the document list, click the document title.
- 5. To retrieve the document, click **Open** or **Download**.

NOTE:

To view files in PDF format (*.pdf), Adobe Acrobat Reader must be installed on your system. To download Adobe Acrobat Reader, go to the following URL:

http://www.adobe.com

© 2007 Hewlett-Packard Development Company, L.P. The information contained herein is subject to change without notice. The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

Microsoft® and Microsoft Windows® are U.S. registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of The Open Group.

All other product names are the property of their respective trademark or service mark holders and are hereby acknowledged.

