

IBM® DB2 Universal Database™



# Data Movement Utilities Guide and Reference

*Version 8.2*



IBM<sup>®</sup> DB2 Universal Database<sup>™</sup>



# Data Movement Utilities Guide and Reference

*Version 8.2*

Before using this information and the product it supports, be sure to read the general information under *Notices*.

This document contains proprietary information of IBM. It is provided under a license agreement and is protected by copyright law. The information contained in this publication does not include any product warranties, and any statements provided in this manual should not be interpreted as such.

You can order IBM publications online or through your local IBM representative.

- To order publications online, go to the IBM Publications Center at [www.ibm.com/shop/publications/order](http://www.ibm.com/shop/publications/order)
- To find your local IBM representative, go to the IBM Directory of Worldwide Contacts at [www.ibm.com/planetwide](http://www.ibm.com/planetwide)

To order DB2 publications from DB2 Marketing and Sales in the United States or Canada, call 1-800-IBM-4YOU (426-4968).

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1999 - 2004. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

# Contents

<b>About This Book</b> . . . . .	<b>v</b>	Multidimensional clustering considerations. . . . .	96
Who Should Use this Book . . . . .	v	Restarting an interrupted load operation. . . . .	97
How this Book is Structured . . . . .	v	Restarting or Terminating an Allow Read Access Load Operation . . . . .	97
<b>Chapter 1. Export.</b> . . . . .	<b>1</b>	Recovering data with the load copy location file . . . . .	98
Export Overview . . . . .	1	LOAD. . . . .	100
Privileges, authorities and authorization required to use export . . . . .	2	LOAD QUERY . . . . .	121
Using Export . . . . .	3	db2Load - Load . . . . .	123
Using export with identity columns . . . . .	4	db2LoadQuery - Load Query . . . . .	145
Recreating an exported table . . . . .	4	File type modifiers for load. . . . .	149
Exporting large objects (LOBS) . . . . .	4	Load exception table . . . . .	160
Exporting data in parallel . . . . .	5	Load dump file. . . . .	160
EXPORT . . . . .	8	Load temporary files . . . . .	161
db2Export - Export . . . . .	12	Load utility log records . . . . .	162
File type modifiers for export . . . . .	19	Table locking, table states and table space states	162
Export Sessions - CLP Examples . . . . .	23	Character set and national language support . . . . .	165
<b>Chapter 2. Import</b> . . . . .	<b>25</b>	Pending states after a load operation . . . . .	165
Import Overview . . . . .	25	Optimizing load performance . . . . .	166
Privileges, authorities, and authorization required to use import. . . . .	26	Load - CLP Examples . . . . .	171
Using import . . . . .	27	<b>Chapter 4. Loading data in a partitioned database environment . . . . .</b>	<b>177</b>
Using import in a client/server environment . . . . .	28	Partitioned database load - overview . . . . .	177
Using import with buffered inserts . . . . .	29	Using load in a partitioned database environment	179
Using import with identity columns . . . . .	29	Monitoring a partitioned database load using the LOAD QUERY command . . . . .	184
Using import with generated columns . . . . .	31	Restarting or terminating a load operation in a partitioned database environment . . . . .	186
Using import to recreate an exported table . . . . .	32	Partitioned database load configuration options	187
Importing large objects (LOBS) . . . . .	33	Example partitioned database load sessions . . . . .	192
Importing user-defined distinct types (UDTs) . . . . .	34	Migration and back-level compatibility . . . . .	195
Table locking during import . . . . .	34	Loading data in a partitioned database environment - hints and tips . . . . .	197
IMPORT . . . . .	35	<b>Chapter 5. Moving DB2 Data Links Manager Data . . . . .</b>	<b>199</b>
db2Import - Import. . . . .	48	Moving DB2 Data Links Manager Data Using Export - Concepts . . . . .	199
File type modifiers for import . . . . .	59	Using export to move DB2 Data Links Manager data . . . . .	201
Character Set and NLS Considerations . . . . .	68	Using import to move DB2 Data Links Manager data . . . . .	202
Import Sessions - CLP Examples . . . . .	68	Using load to move DB2 Data Links Manager data	203
<b>Chapter 3. Load</b> . . . . .	<b>73</b>	<b>Chapter 6. Moving Data Between Systems . . . . .</b>	<b>205</b>
Load Overview . . . . .	74	Moving data across platforms - file format considerations . . . . .	205
Changes to Previous Load Behavior Introduced in Version 6 and Version 7 . . . . .	77	PC/IXF File Format . . . . .	205
Changes to Previous Load Behavior Introduced in Version 8 . . . . .	78	Delimited ASCII (DEL) File Format . . . . .	206
Parallelism and loading . . . . .	80	WSF File Format . . . . .	206
Privileges, authorities, and authorizations required to use Load . . . . .	81	Moving Data With DB2 Connect . . . . .	206
Using Load . . . . .	81	db2move - Database Movement Tool . . . . .	209
Read access load operations . . . . .	83	db2relocatedb - Relocate Database . . . . .	213
Building indexes. . . . .	86		
Using load with identity columns . . . . .	87		
Using load with generated columns . . . . .	89		
Checking for integrity violations . . . . .	91		
Refreshing dependent immediate materialized query tables . . . . .	94		
Propagating dependent immediate staging tables. . . . .	95		

Delimiter restrictions for moving data . . . . .	217
Moving data between typed tables . . . . .	218
Moving Data Between Typed Tables - Details . . . . .	219
Traverse Order . . . . .	219
Selection During Data Movement. . . . .	220
Examples of Moving Data Between Typed Tables . . . . .	221
Using replication to move data . . . . .	222
IBM Replication Tools . . . . .	224
The IBM Replication Tools by Component. . . . .	224
Using the Data Warehouse Center to Move Data . . . . .	224
Moving data using the cursor file type . . . . .	226

**Appendix A. How to read the syntax diagrams . . . . . 227**

**Appendix B. Differences Between the Import and Load Utility . . . . . 231**

**Appendix C. Export/Import/Load Sessions - API Sample Program . . . 233**

**Appendix D. File Formats . . . . . 243**

Export/Import/Load Utility File Formats . . . . .	243
Delimited ASCII (DEL) File Format . . . . .	244
Example and Data Type Descriptions . . . . .	245
Example DEL File . . . . .	245
DEL Data Type Descriptions . . . . .	246
Non-delimited ASCII (ASC) File Format . . . . .	249
Example and Data Type Descriptions . . . . .	249
Example ASC File . . . . .	249
ASC Data Type Descriptions . . . . .	250
PC Version of IXF File Format . . . . .	252
PC Version of IXF File Format - Details. . . . .	254
PC/IXF Record Types . . . . .	254
PC/IXF Data Types . . . . .	270
PC/IXF Data Type Descriptions . . . . .	275
General Rules Governing PC/IXF File Import into Databases . . . . .	279
Data Type-Specific Rules Governing PC/IXF File Import into Databases . . . . .	281
FORCEIN Option . . . . .	283
Differences Between PC/IXF and Version 0 System/370 IXF . . . . .	290
Worksheet File Format (WSF) . . . . .	290

**Appendix E. Export/Import/Load Utility Unicode Considerations. . . . . 293**

Restrictions for Code Pages 1394, 1392 and 5488 . . . . .	294
Incompatibilities . . . . .	294

**Appendix F. Bind Files Used by the Export, Import and Load Utilities . . . 297**

**Appendix G. Warning, error and completion messages. . . . . 299**

**Appendix H. DB2 Universal Database technical information . . . . . 301**

DB2 documentation and help . . . . .	301
DB2 documentation updates . . . . .	301
DB2 Information Center . . . . .	302
DB2 Information Center installation scenarios . . . . .	303
Installing the DB2 Information Center using the DB2 Setup wizard (UNIX) . . . . .	305
Installing the DB2 Information Center using the DB2 Setup wizard (Windows) . . . . .	308
Invoking the DB2 Information Center . . . . .	310
Updating the DB2 Information Center installed on your computer or intranet server . . . . .	311
Displaying topics in your preferred language in the DB2 Information Center . . . . .	311
DB2 PDF and printed documentation . . . . .	312
Core DB2 information . . . . .	312
Administration information . . . . .	313
Application development information . . . . .	314
Business intelligence information . . . . .	314
DB2 Connect information . . . . .	315
Getting started information. . . . .	315
Tutorial information . . . . .	315
Optional component information . . . . .	316
Release notes . . . . .	316
Printing DB2 books from PDF files . . . . .	317
Ordering printed DB2 books . . . . .	318
Invoking contextual help from a DB2 tool . . . . .	318
Invoking message help from the command line processor . . . . .	319
Invoking command help from the command line processor . . . . .	320
Invoking SQL state help from the command line processor . . . . .	320
DB2 tutorials . . . . .	321
DB2 troubleshooting information . . . . .	321
Accessibility . . . . .	322
Keyboard input and navigation . . . . .	322
Accessible display . . . . .	323
Compatibility with assistive technologies . . . . .	323
Accessible documentation . . . . .	323
Dotted decimal syntax diagrams . . . . .	323
Common Criteria certification of DB2 Universal Database products. . . . .	325

**Appendix I. Notices . . . . . 327**

Trademarks . . . . .	329
----------------------	-----

**Index . . . . . 331**

**Contacting IBM . . . . . 335**

Product information . . . . .	335
-------------------------------	-----

---

## About This Book

This book provides information about, and shows you how to use, the following IBM DB2 Universal Database (UDB) data movement utilities:

- The Import and Export utilities move data between a table or view and another database or spreadsheet program; between DB2 databases; and between DB2 databases and host databases using DB2 Connect. The export utility moves data from a database into operating system files; you can then use those files to import or load that data into another database.
- The Load utility moves data into tables, extends existing indexes, and generates statistics. Load moves data much faster than the import utility when large amounts of data are involved. Data unloaded using the export utility can be loaded with the load utility.
- When the Load utility is used in a partitioned database environment, large amounts of data can be partitioned and loaded into different database partitions.
- DataPropagator (DPROP) is a component of DB2 Universal Database that allows automatic copying of table updates to other tables in other DB2 relational databases.
- The Data Warehouse Center (DWC) can be used to move data from operational databases to a warehouse database.

Other vendor's products that move data in and out of databases are also available, but are not discussed in this book.

---

## Who Should Use this Book

This manual is for database administrators, application programmers, and other DB2 UDB users who perform the following tasks:

- Load data into DB2 tables from operating system files
- Move data between DB2 databases, and between DB2 and other applications (for example, spreadsheets)
- Archive data.

It is assumed that you are familiar with DB2 Universal Database, Structured Query Language (SQL), and with the operating system environment in which DB2 UDB is running.

---

## How this Book is Structured

The following topics are covered:

### Chapter 1

Describes the DB2 export utility, used to move data from DB2 tables into files.

### Chapter 2

Describes the DB2 import utility, used to move data from files into DB2 tables or views.

### Chapter 3

Describes the DB2 load utility, used to move large volumes of data into DB2 tables.

**Chapter 4**

Describes loading data in a partitioned database environment.

**Chapter 5**

Describes how to use the DB2 export, import, and load utilities to move DB2 Data Links Manager data.

**Chapter 6**

Describes how to use the DB2 export, import, and load utilities to transfer data across platforms, and to and from DRDA host databases. DataPropagator (DPROP), another method for moving data between databases in an enterprise, is also described. Also introduces the Data Warehouse Center (DWC), which can be used to move data from operational databases to a warehouse database.

**Appendix A**

Explains the conventions used in syntax diagrams.

**Appendix B**

Summarizes the important differences between the DB2 load and import utilities.

**Appendix C**

Includes an API sample program that illustrates how to export data to a file, import data to a table, load data into a table, and check the status of a load operation.

**Appendix D**

Describes external file formats supported by the database manager export, import, and load utilities.

**Appendix E**

Discusses unicode consideration when using the export, import and load utilities.

**Appendix F**

Lists bind files with their default isolation levels, as well as which utilities use them and for what purpose.

**Appendix G**

Provides information about interpreting messages generated by the database manager when a warning or error condition has been detected.

---

## Chapter 1. Export

This chapter describes the DB2 UDB export utility, which is used to write data from a DB2 database to one or more files stored outside of the database. The exported data can then be imported or loaded into another DB2 database, using the DB2 import or the DB2 load utility, respectively, or it can be imported into another application (for example, a spreadsheet).

The following topics are covered:

- “Export Overview”
- “Privileges, authorities and authorization required to use export” on page 2
- “Using Export” on page 3
- “Using export with identity columns” on page 4
- “Recreating an exported table” on page 4
- “Exporting large objects (LOBs)” on page 4
- “Exporting data in parallel” on page 5
- “EXPORT” on page 8
- “db2Export - Export” on page 12
- “Export Sessions - CLP Examples” on page 23

For information about exporting DB2 Data Links Manager data, see “Using export to move DB2 Data Links Manager data” on page 201. For information about exporting data out of typed tables, see “Moving data between typed tables” on page 218. For information about exporting data from a DRDA server database to a file on the DB2 Connect workstation, and the reverse, see “Moving Data With DB2 Connect” on page 206.

---

### Export Overview

The export utility exports data from a database to an operating system file, which can be in one of several external file formats. This operating system file can then be used to move the table data to a different server such as DB2<sup>®</sup> UDB for iSeries<sup>™</sup>.

The following information is required when exporting data:

- An SQL SELECT statement specifying the data to be exported.
- The path and name of the operating system file that will store the exported data.
- The format of the data in the input file. This format can be IXF, WSF, or DEL.
- When exporting typed tables, you might need to provide the subtable traverse order within the hierarchy. If the IXF format is to be used, the default order is recommended. When specifying the order, recall that the subtables must be traversed in the PRE-ORDER fashion. When exporting typed tables, you cannot provide a SELECT statement directly. Instead, you must specify the target subtable name, and optionally a WHERE clause. The export utility uses this information, along with the traverse order, to generate and execute the required SELECT statement.

You can also specify:

- New column names when exporting to IXF or WSF files. If you do not want to specify new column names, the column names in the existing table or view are used in the exported file.
- Additional options to customize the export operation.
- A message file name. During DB2 operations such as exporting, importing, loading, binding, or restoring data, you can specify that message files be created to contain the error, warning, and informational messages associated with those operations. Specify the name of these files with the MESSAGES parameter. These message files are standard ASCII text files. Each message in a message file begins on a new line and contains information provided by the DB2 message retrieval facility. To print them, use the printing procedure for your operating system; to view them, use any ASCII editor.

If you want to use the export utility in a multiple database partition environment, you can use **db2batch** to complete the task at each database partition. The SELECT statement must be able to return only the data found locally. The selection condition is as follows:

```
SELECT * FROM tablename WHERE NODENUMBER(column-name) = CURRENT NODE
```

**Related concepts:**

- “Privileges, authorities and authorization required to use export” on page 2
- “Using export with identity columns” on page 4
- “Recreating an exported table” on page 4
- “Exporting large objects (LOBS)” on page 4
- “Exporting data in parallel” on page 5
- “Moving data between typed tables” on page 218
- “Examples of db2batch tests” in the *Administration Guide: Performance*

**Related tasks:**

- “Using Export” on page 3

**Related reference:**

- “db2Export - Export” on page 12
- “db2batch - Benchmark Tool Command” in the *Command Reference*
- “Export Sessions - CLP Examples” on page 23
- “Export/Import/Load Utility File Formats” on page 243
- “EXPORT” on page 8

---

## Privileges, authorities and authorization required to use export

Privileges enable users to create or access database resources. Authority levels provide a method of grouping privileges and higher-level database manager maintenance and utility operations. Together, these act to control access to the database manager and its database objects. Users can access only those objects for which they have the appropriate authorization; that is, the required privilege or authority.

You must have SYSADM or DBADM authority, or CONTROL or SELECT privilege for each table participating in the export operation.

**Related reference:**

- “db2Export - Export” on page 12
- “EXPORT” on page 8

---

## Using Export

### Prerequisites:

Before invoking the export utility, you must be connected to (or be able to implicitly connect to) the database from which the data will be exported. Since the utility will issue a COMMIT statement, you should complete all transactions and release all locks by performing either a COMMIT or a ROLLBACK before invoking export. Other user applications accessing the table using separate connections need not disconnect.

### Restrictions:

The following restrictions apply to the export utility:

- This utility does not support the use of nicknames.
- This utility does not support tables with structured type columns.

### Procedure:

*The export utility can be invoked through the command line processor (CLP), the Export notebook in the Control Centre, or an application programming interface (API),*

#### **db2Export.**

Following is an example of the EXPORT command issued through the CLP:

```
db2 export to staff.ixf of ixf select * from userid.staff
```

To open the Export notebook:

1. From the Control Center, expand the object tree until you find the Tables or Views folder.
2. Click on the folder you want to work with. Any existing tables or views are displayed in the pane on the right side of the window (the contents pane).
3. Click the right mouse button on the table or view you want in the contents pane, and select Export from the pop-up menu. The Export notebook opens.

Detailed information about the Control Center is provided through its online help facility.

### Related reference:

- “db2Export - Export” on page 12

### Related samples:

- “tbmove.out -- HOW TO MOVE TABLE DATA (C)”
- “tbmove.sqc -- How to move table data (C)”
- “tbmove.out -- HOW TO MOVE TABLE DATA (C++)”
- “tbmove.sqC -- How to move table data (C++)”

---

## Using export with identity columns

The export utility can be used to export data from a table containing an identity column. If the SELECT statement specified for the export operation is of the form "select \* from tablename", and the METHOD option is not used, exporting identity column properties to IXF files is supported. The REPLACE\_CREATE and the CREATE options of the IMPORT command can then be used to recreate the table, including its identity column properties. If such an IXF file is created from a table containing an identity column of type GENERATED ALWAYS, the only way that the data file can be successfully imported is to specify the identityignore modifier. Otherwise, all rows will be rejected (SQL3550W).

**Related concepts:**

- "Identity columns" in the *Administration Guide: Planning*

---

## Recreating an exported table

A table can be saved by using the export utility and specifying the IXF file format. The saved table (including its indexes) can then be recreated using the import utility.

The export operation will fail if the data you want to export exceeds the space available on the file system on which the exported file will be created. In this case, you should limit the amount of data selected by specifying conditions on the WHERE clause, so that the export file will fit on the target file system. You can invoke the export utility multiple times to export all of the data.

The DEL and ASC file formats do not contain descriptions of the target table, but they do contain the record data. To recreate a table with data stored in these file formats, create the target table, and then use the load, or import utility to populate the table from these files. **db2look** (DB2 Statistics and DDL Extraction Tool) can be used to capture the original table definitions, and to generate the corresponding data definition language (DDL).

**Related concepts:**

- "Using import to recreate an exported table" on page 32

**Related reference:**

- "db2look - DB2 Statistics and DDL Extraction Tool Command" in the *Command Reference*

---

## Exporting large objects (LOBs)

When exporting data from large object (LOB) columns, the default action is to select the first 32KB of data, and to place this data in the same file as the rest of the column data.

**Note:** The IXF file format does not store the LOB options of the column, such as whether or not the LOB column is logged. This means that the import utility cannot recreate a table containing a LOB column that is defined to be 1GB or larger.

A LOB Location Specifier (LLS) is used to store multiple LOBs in a single file when exporting LOB information. When exporting data using the `lobsinfile` modifier, the export utility selects the entire LOB file and places it in one of the LOB files. There might be multiple LOBs per LOB file and multiple LOB files in each LOB path. The data file will contain the LLS records.

An LLS is a string indicating where LOB data can be found within a file. The format of the LLS is `filename.ext.nnn.mmm/`, where `filename.ext` is the name of the file that contains the LOB, `nnn` is the offset of the LOB within the file (measured in bytes), and `mmm` is the length of the LOB (in bytes). For example, an LLS of `db2exp.001.123.456/` indicates that the LOB is located in the file `db2exp.001`, begins at an offset of 123 bytes into the file, and is 456 bytes long. If the indicated size in the LLS is 0, the LOB is considered to have a length of 0. If the length is -1, the LOB is considered to be NULL and the offset and file name are ignored.

**Related reference:**

- “db2Export - Export” on page 12
- “EXPORT” on page 8
- “Large objects (LOBs)” in the *SQL Reference, Volume 1*

---

## Exporting data in parallel

Exporting data in parallel reduces data transfer, and distributes the writing of the result set, as well as the generation of the formatted output, across nodes in a more effective manner than would otherwise be the case. When data is exported in parallel (by invoking multiple export operations, one for each partition of a table), it is extracted, converted on the local nodes, and then written to the local file system. In contrast, when exporting data serially (exporting through a single export operation), it is extracted in parallel and then shipped to the client, where a single process performs conversion and writes the result set to a local file system.

The **db2batch** command is used to monitor the performance characteristics and execution duration of SQL statements. This utility also has a parallel export function in partitioned database environments that:

- Runs queries to define the data to be exported
- On each partition, creates a file containing the exported data that resides on that partition.

**Note:** If the target file path is shared between database partitions, a single file will contain the output from all partitions sharing the path.

A query is run in parallel on each partition to retrieve the data on that partition. When running the **db2batch** command with the `-p s` option, the original SELECT query is run in parallel. When running the **db2batch** command with either the `-p t` option or the `-p d` option, a staging table is loaded with the export data, using the specified query, and a `SELECT *` query is run on the staging table in parallel on each partition to export the data. To export only the data that resides on a given partition, **db2batch** adds the predicate `NODENUMBER(colname) = CURRENT NODE` to the WHERE clause of the query that is run on that partition. The `colname` parameter must be set to the qualified or the unqualified name of a table column. The first column name in the original query is used to set this parameter.

It is important to understand that **db2batch** command runs an SQL query and sends the output to the target file; it does not use the export utility. The export utility options are not applicable to parallel export using the **db2batch** command. You cannot export LOB columns using the **db2batch** command.

Run **db2batch** command with the **-h** option from the command window to see a complete description of command options.

The **db2batch** command executes a parallel SQL query and sends the output to a specified file. Note that the command is executing a select statement, not the export utility. LOB columns, regardless of data length, cannot be exported using this method.

To export contents of the staff table in parallel, use:

```
db2batch -p s -d sample -f staff.batch -r /home/userid/staff.asc -q on
```

In this example:

- The query is ran in parallel on a single table (the **-p s** option)
- Connection is made to the sample database (the **-d sample** option)
- The control file **staff.batch** contains the (semicolon terminated) SQL select statement **select \* from staff;**
- Output is stored to **/home/userid/staff.asc** files accessible on each database partition, default output format is positional ASCII (remember that **db2batch** is not using the export utility)
- Only the output of the query will be sent to the file (the **-q** option)

To export into a delimited ASCII file:

```
db2batch -p s -d sample -f emp_resume.batch -r /home/userid/emp_resume.del,  
/home/mmilek/userid/emp_resume.out -q del
```

In this example:

- Only non-LOB columns from **emp\_resume** table are selected (control file **emp\_resume.batch** contains **select empno,resume\_format from emp\_resume;**)
- The **emp\_resume.del** file contains the query output in delimited ASCII format (the **-q del** option), comma is the default column delimiter and **|** is the default char delimiter
- The **emp\_resume.out** file contains the query statistics

There are two types of parallel export, depending on what tables are queried, and where those tables exist in the partitioned database environment:

- Parallel export from a partitioned table, or a join or subquery on multiple tables that are collocated (specify **-p s** on the **db2batch** command).

There are two ways in which tables can be considered collocated:

- The tables are in a single database partition group defined on the same partition.
- The tables are in the same database partition group, and have partitioning keys with the same number and type of columns. The corresponding columns of the partitioning key are partition compatible, and the tables are equi-joined on the entire partition key, or a superset of the partition key.

In each case, the query can be run on each partition to generate that partition's export data file using the **NODENUMBER** function as described below. (Note that if a table exists in a single partition only, export parallelism is negated,

because the data is retrieved from only one partition. To enable export parallelism in this case, refer to the next bullet.)

- A SELECT from multiple non-collocated tables (specify `-p t tablename` or `-p d` on the **db2batch** command; the former allows you to specify the name of an existing table to use as a staging table, while the latter causes the export utility to create a staging table).

The export utility uses a staging table that is populated through the export query. This staging table is used to locate the rows of the "export" result set by running an INSERT of the fullselect query into the staging table. Once the staging table is created, the export utility generates an export data file at each partition by running:

```
"select * WHERE NODENUMBER(colname) = CURRENT NODE"
```

on the staging table.

A staging table can also be used to export a single partition table in parallel. In most cases, transferring the data from a single partition into a multi-partition staging table, and then exporting the staging table in parallel on all partitions, is faster than exporting the single partition table serially.

The export utility runs a query in parallel on each partition to retrieve the data on that partition. In the case of `db2batch -p s`, the original SELECT query is run in parallel. In the case of `db2batch -p t` and `db2batch -p d`, a staging table is loaded with the export data, using the specified query, and a SELECT \* query is run on the staging table in parallel on each partition to export the data. To export only the data that resides on a given partition, **db2batch** adds the predicate `NODENUMBER(colname) = CURRENT NODE` to the WHERE clause of the query that is run on that partition. The *colname* parameter must be set to the qualified or the unqualified name of a table column. The export utility uses the first column name in the original query to set this parameter.

Following are the limitations on queries used by the export utility:

- When specifying `db2batch -p s`, the query must not contain only column functions, because a column name is needed for the `NODENUMBER colname` predicate.
- When specifying `db2batch -p s`, aggregates (such as min, max, and avg) must be based on a grouping that includes the partitioning key.
- When specifying `db2batch -p t` or `db2batch -p d`, the query cannot contain ORDER BY, because ORDER BY on a fullselect within an INSERT statement is not supported by DB2<sup>®</sup> UDB.

If, when specifying `-p s` on the **db2batch** command, you also use the `-r` option to create result output files, the files on each partition will be in sorted order if you have an ORDER BY clause. If a single sorted file is your objective, merge the sorted file on each partition into one sorted file. For example, on UNIX<sup>®</sup> based systems, use the command `sort -m` to merge the files into a single sorted file. If you are sending your output to an NFS mounted file system, the output will not be sorted, even if you specify the ORDER BY clause.

#### Related concepts:

- "Export Overview" on page 1

#### Related reference:

- "db2batch - Benchmark Tool Command" in the *Command Reference*

# EXPORT

Exports data from a database to one of several external file formats. The user specifies the data to be exported by supplying an SQL SELECT statement, or by providing hierarchical information for typed tables.

**Authorization:**

One of the following:


- *sysadm*
- *dbadm*

or CONTROL or SELECT privilege on each participating table or view.

**Required connection:**

Database. If implicit connect is enabled, a connection to the default database is established.

**Command syntax:**



**traversal-order-list:**



**Command parameters:**

**HIERARCHY traversal-order-list**

Export a sub-hierarchy using the specified traverse order. All sub-tables must be listed in PRE-ORDER fashion. The first sub-table name is used as the target table name for the SELECT statement.

**HIERARCHY STARTING sub-table-name**

Using the default traverse order (OUTER order for ASC, DEL, or WSF files, or the order stored in PC/IXF data files), export a sub-hierarchy starting from *sub-table-name*.

**LOBFILE filename**

Specifies one or more base file names for the LOB files. When name space is exhausted for the first name, the second name is used, and so on.

When creating LOB files during an export operation, file names are constructed by appending the current base name from this list to the current path (from *lob-path*), and then appending a 3-digit sequence number. For example, if the current LOB path is the directory */u/foo/lob/path/*, and the current LOB file name is *bar*, the LOB files created will be */u/foo/lob/path/bar.001*, */u/foo/lob/path/bar.002*, and so on.

**LOBS TO lob-path**

Specifies one or more paths to directories in which the LOB files are to be stored. There will be at least one file per LOB path, and each file will contain at least one LOB.

**MESSAGES message-file**

Specifies the destination for warning and error messages that occur during an export operation. If the file already exists, the export utility appends the information. If *message-file* is omitted, the messages are written to standard output.

**METHOD N column-name**

Specifies one or more column names to be used in the output file. If this parameter is not specified, the column names in the table are used. This parameter is valid only for WSF and IXF files, but is not valid when exporting hierarchical data.

**MODIFIED BY filetype-mod**

Specifies file type modifier options. See File type modifiers for export.

**OF filetype**

Specifies the format of the data in the output file:

- DEL (delimited ASCII format), which is used by a variety of database manager and file manager programs.
- WSF (work sheet format), which is used by programs such as:
  - Lotus 1-2-3
  - Lotus Symphony

**Note:** When exporting BIGINT or DECIMAL data, only values that fall within the range of type DOUBLE can be exported accurately. Although values that do not fall within this range are also exported, importing or loading these values back may result in incorrect data, depending on the operating system.

- IXF (integrated exchange format, PC version), in which most of the table attributes, as well as any existing indexes, are saved in the IXF file, except when columns are specified in the SELECT statement. With this format, the table can be recreated, while with the other file formats, the table must already exist before data can be imported into it.

**select-statement**

Specifies the SELECT statement that will return the data to be exported. If the SELECT statement causes an error, a message is written to the message

## EXPORT

file (or to standard output). If the error code is one of SQL0012W, SQL0347W, SQL0360W, SQL0437W, or SQL1824W, the export operation continues; otherwise, it stops.

### TO filename

Specifies the name of the file to which data is to be exported. If the complete path to the file is not specified, the export utility uses the current directory and the default drive as the destination.

If the name of a file that already exists is specified, the export utility overwrites the contents of the file; it does not append the information.

### Examples:

The following example shows how to export information from the STAFF table in the SAMPLE database to the file myfile.ixf. The output will be in IXF format. Note that you must be connected to the SAMPLE database before issuing the command. The index definitions (if any) will be stored in the output file except when the database connection is made through DB2 Connect.

```
db2 export to myfile.ixf of ixf messages msgs.txt select * from staff
```

The following example shows how to export the information about employees in Department 20 from the STAFF table in the SAMPLE database. The output will be in IXF format and will go into the awards.ixf file. Note that you must first connect to the SAMPLE database before issuing the command. Also note that the actual column name in the table is 'dept' instead of 'department'.

```
db2 export to awards.ixf of ixf messages msgs.txt select * from staff
where dept = 20
```

The following example shows how to export LOBs to a DEL file:

```
| db2 export to myfile.del of del lobs to mylobs/
| lobfile lobs1, lobs2 modified by lobsinfile
| select * from emp_photo
```

The following example shows how to export LOBs to a DEL file, specifying a second directory for files that may not fit into the first directory:

```
| db2 export to myfile.del of del
| lobs to /db2exp1/, /db2exp2/ modified by lobsinfile
| select * from emp_photo
```

The following example shows how to export data to a DEL file, using a single quotation mark as the string delimiter, a semicolon as the column delimiter, and a comma as the decimal point. The same convention should be used when importing data back into the database:

```
db2 export to myfile.del of del
modified by chardel'' coldel; decpt,
select * from staff
```

### Usage notes:

Be sure to complete all table operations and release all locks before starting an export operation. This can be done by issuing a COMMIT after closing all cursors opened WITH HOLD, or by issuing a ROLLBACK.

Table aliases can be used in the SELECT statement.

The messages placed in the message file include the information returned from the message retrieval service. Each message begins on a new line.

The export utility produces a warning message whenever a character column with a length greater than 254 is selected for export to DEL format files.

PC/IXF import should be used to move data between databases. If character data containing row separators is exported to a delimited ASCII (DEL) file and processed by a text transfer program, fields containing the row separators will shrink or expand.

The file copying step is not necessary if the source and the target databases are both accessible from the same client.

DB2 Connect can be used to export tables from DRDA servers such as DB2 for OS/390, DB2 for VM and VSE, and DB2 for OS/400. Only PC/IXF export is supported.

The export utility will not create multiple-part PC/IXF files when invoked from an AIX system.

The export utility will store the NOT NULL WITH DEFAULT attribute of the table in an IXF file if the SELECT statement provided is in the form `SELECT * FROM tablename`.

When exporting typed tables, subselect statements can only be expressed by specifying the target table name and the WHERE clause. Fullselect and *select-statement* cannot be specified when exporting a hierarchy.

For file formats other than IXF, it is recommended that the traversal order list be specified, because it tells DB2 how to traverse the hierarchy, and what sub-tables to export. If this list is not specified, all tables in the hierarchy are exported, and the default order is the OUTER order. The alternative is to use the default order, which is the order given by the OUTER function.

**Note:** Use the same traverse order during an import operation. The load utility does not support loading hierarchies or sub-hierarchies.

#### **DB2 Data Links Manager considerations:**

To ensure that a consistent copy of the table and the corresponding files referenced by the DATALINK columns are copied for export, do the following:

1. Issue the command: `QUIESCE TABLESPACES FOR TABLE tablename SHARE`.  
This ensures that no update transactions are in progress when EXPORT is run.
2. Issue the EXPORT command.
3. Run the **dlfm\_export** utility at each Data Links server. Input to the **dlfm\_export** utility is the control file name, which is generated by the export utility. This produces a tar (or equivalent) archive of the files listed within the control file.
4. Issue the command: `QUIESCE TABLESPACES FOR TABLE tablename RESET`.  
This makes the table available for updates.

EXPORT is executed as an SQL application. The rows and columns satisfying the SELECT statement conditions are extracted from the database. For the DATALINK columns, the SELECT statement should not specify any scalar function.

## EXPORT

Successful execution of EXPORT results in generation of the following files:

- An export data file as specified in the EXPORT command. A DATALINK column value in this file has the same format as that used by the IMPORT and LOAD utilities. When the DATALINK column value is the SQL NULL value, handling is the same as that for other data types.
- Control files *server\_name*, which are generated for each Data Links server. On Windows operating systems, a single control file, *ctrlfile.lst*, is used by all Data Links servers. These control files are placed in the directory <data-file path>/dlfm/YYYYMMDD/HHMMSS (on the Windows NT operating system, *ctrlfile.lst* is placed in the directory <data-file path>\dlfm\YYYYMMDD\HHMMSS). YYYYMMDD represents the date (year month day), and HHMMSS represents the time (hour minute second).

The *dlfm\_export* utility is provided to export files from a Data Links server. This utility generates an archive file, which can be used to restore files in the target Data Links server.

### Related concepts:

- “Export Overview” on page 1
- “Privileges, authorities and authorization required to use export” on page 2

### Related tasks:

- “Using Export” on page 3

### Related reference:

- “db2Export - Export” on page 12
- “Export Sessions - CLP Examples” on page 23
- “File type modifiers for export” on page 19
- “Delimiter restrictions for moving data” on page 217

---

## db2Export - Export

Exports data from a database to one of several external file formats. The user specifies the data to be exported by supplying an SQL SELECT statement, or by providing hierarchical information for typed tables.

### Authorization:

One of the following:

- *sysadm*
- *dbadm*

or CONTROL or SELECT privilege on each participating table or view.

### Required connection:

Database. If implicit connect is enabled, a connection to the default database is established.

### API include file:

*db2ApiDf.h*

**C API syntax:**

```

/* File: db2ApiDf.h */
/* API: db2Export */
/* ... */

SQL_API_RC SQL_API_FN
db2Export (
    db2UInt32 versionNumber,
    void * pParmStruct,
    struct sqlca * pSqlca);

typedef SQL_STRUCTURE db2ExportStruct
{
    char                                *piDataFileName;
    struct sqlu_media_list              *piLobPathList;
    struct sqlu_media_list              *piLobFileList;
    struct sqldcol                      *piDataDescriptor;
    struct sqllob                       *piActionString;
    char                                *piFileType;
    struct sqlchar                      *piFileTypeMod;
    char                                *piMsgFileName;
    db2int16                            iCallerAction;
    struct db2ExportOut                 *poExportInfoOut;
} db2ExportStruct;

typedef SQL_STRUCTURE db2ExportOut
{
    db2UInt64                            oRowsExported;
} db2ExportOut;
/* ... */

```

**Generic API syntax:**

```

/* File: db2ApiDf.h */
/* API: db2gExport */
/* ... */

SQL_API_RC SQL_API_FN
db2gExport (
    db2UInt32 versionNumber,
    void * pParmStruct,
    struct sqlca * pSqlca);

typedef SQL_STRUCTURE db2gExportStruct
{
    char                                *piDataFileName;
    struct sqlu_media_list              *piLobPathList;
    struct sqlu_media_list              *piLobFileList;
    struct sqldcol                      *piDataDescriptor;
    struct sqllob                       *piActionString;
    char                                *piFileType;
    struct sqlchar                      *piFileTypeMod;
    char                                *piMsgFileName;
    db2int16                            iCallerAction;
    struct db2ExportOut                 *poExportInfoOut;
    db2UInt16                           iDataFileNameLen;
    db2UInt16                           iFileTypeLen;
    db2UInt16                           iMsgFileNameLen;
} db2gExportStruct;
/* ... */

```

**API parameters:****versionNumber**

Input. Specifies the version and release level of the structure passed as the second parameter *pParmStruct*.

## db2Export - Export

### **pParmStruct**

Input. A pointer to the *db2ExportStruct* structure.

### **pSqlca**

Output. A pointer to the *sqlca* structure.

### **iDataFileNameLen**

Input. A 2-byte unsigned integer representing the length in bytes of the data file name.

### **iFileTypeLen**

Input. A 2-byte unsigned integer representing the length in bytes of the file type.

### **iMsgFileNameLen**

Input. A 2-byte unsigned integer representing the length in bytes of the message file name.

### **piDataFileName**

Input. A string containing the path and the name of the external file into which the data is to be exported.

### **piLobPathList**

Input. An *sqlu\_media\_list* using *media\_type* `SQLU_LOCAL_MEDIA`, and the *sqlu\_media\_entry* structure listing paths on the client where the LOB files are to be stored.

When file space is exhausted on the first path in this list, the API will use the second path, and so on.

### **piLobFileList**

Input. An *sqlu\_media\_list* using *media\_type* `SQLU_CLIENT_LOCATION`, and the *sqlu\_location\_entry* structure containing base file names.

When the name space is exhausted using the first name in this list, the API will use the second name, and so on.

When creating LOB files during an export operation, file names are constructed by appending the current base name from this list to the current path (from *pLobFilePath*), and then appending a 3-digit sequence number. For example, if the current LOB path is the directory `/u/foo/lob/path`, and the current LOB file name is `bar`, the created LOB files will be `/u/foo/lob/path/bar.001`, `/u/foo/lob/pah/bar.002`, and so on.

### **piDataDescriptor**

Input. Pointer to an *sqldcol* structure specifying the column names for the output file. The value of the *dcolmeth* field determines how the remainder of the information provided in this parameter is interpreted by the export utility. Valid values for this parameter (defined in `sqlutil`) are:

#### **SQL\_METH\_N**

Names. Specify column names to be used in the output file.

#### **SQL\_METH\_D**

Default. Existing column names from the table are to be used in the output file. In this case, the number of columns and the column specification array are both ignored. The column names are derived from the output of the SELECT statement specified in *pActionString*.

### **piActionString**

Input. Pointer to an *sqllob* structure containing a valid dynamic SQL SELECT statement. The structure contains a 4-byte long field, followed by

the characters that make up the SELECT statement. The SELECT statement specifies the data to be extracted from the database and written to the external file.

The columns for the external file (from *piDataDescriptor*), and the database columns from the SELECT statement, are matched according to their respective list/structure positions. The first column of data selected from the database is placed in the first column of the external file, and its column name is taken from the first element of the external column array.

#### **piFileType**

Input. A string that indicates the format of the data within the external file. Supported external file formats (defined in `sqlutil`) are:

##### **SQL\_DEL**

Delimited ASCII, for exchange with dBase, BASIC, and the IBM Personal Decision Series programs, and many other database managers and file managers.

##### **SQL\_WSF**

Worksheet formats for exchange with Lotus Symphony and 1-2-3 programs.

##### **SQL\_IXF**

PC version of the Integrated Exchange Format, the preferred method for exporting data from a table. Data exported to this file format can later be imported or loaded into the same table or into another database manager table.

#### **piFileTypeMod**

Input. A pointer to an *sqlcol* structure containing a 2-byte long field, followed by an array of characters that specify one or more processing options. If this pointer is NULL, or the structure pointed to has zero characters, this action is interpreted as selection of a default specification.

Not all options can be used with all of the supported file types. See File type modifiers for export.

#### **piMsgFileName**

Input. A string containing the destination for error, warning, and informational messages returned by the utility. It can be the path and the name of an operating system file or a standard device. If the file already exists, it is overwritten. If it does not exist, a file is created.

#### **iCallerAction**

Input. An action requested by the caller. Valid values (defined in `sqlutil`) are:

##### **SQLU\_INITIAL**

Initial call. This value must be used on the first call to the API.

If the initial call or any subsequent call returns and requires the calling application to perform some action prior to completing the requested export operation, the caller action must be set to one of the following:

##### **SQLU\_CONTINUE**

Continue processing. This value can only be used on subsequent calls to the API, after the initial call has returned with the utility requesting user input (for example, to respond to an end of tape condition). It specifies that the user action requested by the utility has completed, and the utility can continue processing the initial request.

## db2Export - Export

### SQLU\_TERMINATE

Terminate processing. This value can only be used on subsequent calls to the API, after the initial call has returned with the utility requesting user input (for example, to respond to an end of tape condition). It specifies that the user action requested by the utility was not performed, and the utility is to terminate processing the initial request.

### poExportInfoOut

A pointer to the *db2ExportOut* structure.

### oRowsExported

Output. Returns the number of records exported to the target file.

### REXX API syntax:

```
EXPORT :stmt TO datafile OF filetype  
[MODIFIED BY :filetmod] [USING :dcoldata]  
MESSAGES msgfile [ROWS EXPORTED :number]
```

```
CONTINUE EXPORT
```

```
STOP EXPORT
```

### REXX API parameters:

**stmt** A REXX host variable containing a valid dynamic SQL SELECT statement. The statement specifies the data to be extracted from the database.

### datafile

Name of the file into which the data is to be exported.

### filetype

The format of the data in the export file. The supported file formats are:

**DEL** Delimited ASCII

**WSF** Worksheet format

**IXF** PC version of Integrated Exchange Format.

### filetmod

A host variable containing additional processing options.

### dcoldata

A compound REXX host variable containing the column names to be used in the export file. In the following, XXX represents the name of the host variable:

**XXX.0** Number of columns (number of elements in the remainder of the variable).

**XXX.1** First column name.

**XXX.2** Second column name.

**XXX.3** and so on.

If this parameter is NULL, or a value for *dcoldata* has not been specified, the utility uses the column names from the database table.

### msgfile

File, path, or device name where error and warning messages are to be sent.

**number**

A host variable that will contain the number of exported rows.

**Usage notes:**

Be sure to complete all table operations and release all locks before starting an export operation. This can be done by issuing a COMMIT after closing all cursors opened WITH HOLD, or by issuing a ROLLBACK.

Table aliases can be used in the SELECT statement.

The messages placed in the message file include the information returned from the message retrieval service. Each message begins on a new line.

The export utility produces a warning message whenever a character column with a length greater than 254 is selected for export to DEL format files.

A warning message is issued if the number of columns (*dcolnum*) in the external column name array, *piDataDescriptor*, is not equal to the number of columns generated by the SELECT statement. In this case, the number of columns written to the external file is the lesser of the two numbers. Excess database columns or external column names are not used to generate the output file.

If the db2uexpm.bnd module or any other shipped .bnd files are bound manually, the **format** option on the binder must not be used.

PC/IXF import should be used to move data between databases. If character data containing row separators is exported to a delimited ASCII (DEL) file and processed by a text transfer program, fields containing the row separators will shrink or expand.

DB2 Connect can be used to export tables from DRDA servers such as DB2 for z/OS and OS/390, DB2 for VM and VSE, and DB2 for iSeries. Only PC/IXF export is supported.

The export utility will not create multiple-part PC/IXF files when invoked from an AIX system.

Index definitions for a table are included in the PC/IXF file when the contents of a single database table are exported to a PC/IXF file with a *pActionString* beginning with SELECT \* FROM tablename, and the *piDataDescriptor* parameter specifying default names. Indexes are not saved for views, or if the SELECT clause of the *piActionString* includes a join. A WHERE clause, a GROUP BY clause, or a HAVING clause in the *piActionString* will not prevent the saving of indexes. In all of these cases, when exporting from typed tables, the entire hierarchy must be exported.

The export utility will store the NOT NULL WITH DEFAULT attribute of the table in an IXF file if the SELECT statement provided is in the form SELECT \* FROM tablename.

When exporting typed tables, subselect statements can only be expressed by specifying the target table name and the WHERE clause. Fullselect and *select-statement* cannot be specified when exporting a hierarchy.

## db2Export - Export

For file formats other than IXF, it is recommended that the traversal order list be specified, because it tells DB2 how to traverse the hierarchy, and what sub-tables to export. If this list is not specified, all tables in the hierarchy are exported, and the default order is the OUTER order. The alternative is to use the default order, which is the order given by the OUTER function.

**Note:** Use the same traverse order during an import operation. The load utility does not support loading hierarchies or sub-hierarchies.

### DB2 Data Links Manager considerations:

To ensure that a consistent copy of the table and the corresponding files referenced by the DATALINK columns are copied for export, do the following:

1. Issue the command: QUIESCE TABLESPACES FOR TABLE tablename SHARE.  
This ensures that no update transactions are in progress when EXPORT is run.
2. Issue the EXPORT command.
3. Run the **dlfm\_export** utility at each Data Links server. Input to the **dlfm\_export** utility is the control file name, which is generated by the export utility. This produces a tar (or equivalent) archive of the files listed within the control file. **dlfm\_export** does not capture the ACLs information of the files that are archived.
4. Issue the command: QUIESCE TABLESPACES FOR TABLE tablename RESET.  
This makes the table available for updates.

EXPORT is executed as an SQL application. The rows and columns satisfying the SELECT statement conditions are extracted from the database. For the DATALINK columns, the SELECT statement should not specify any scalar function.

Successful execution of EXPORT results in generation of the following files:

- An export data file as specified in the EXPORT command. A DATALINK column value in this file has the same format as that used by the IMPORT and LOAD utilities. When the DATALINK column value is the SQL NULL value, handling is the same as that for other data types.
- Control files *server\_name*, which are generated for each Data Links server. On the Windows NT operating system, a single control file, *ctrlfile.lst*, is used by all Data Links servers. These control files are placed in the directory <data-file path>/dlfm/YYYYMMDD/HHMMSS (on the Windows NT operating system, *ctrlfile.lst* is placed in the directory <data-file path>\dlfm\YYYYMMDD\HHMMSS). YYYYMMDD represents the date (year month day), and HHMMSS represents the time (hour minute second).

The **dlfm\_export** utility is provided to export files from a Data Links server. This utility generates an archive file, which can be used to restore files in the target Data Links server.

### Related concepts:

- “Moving DB2 Data Links Manager Data Using Export - Concepts” on page 199

### Related reference:

- “SQLCA” in the *Administrative API Reference*
- “SQLCHAR” in the *Administrative API Reference*
- “SQLDCOL” in the *Administrative API Reference*
- “SQLU-MEDIA-LIST” in the *Administrative API Reference*

- “File type modifiers for export” on page 19
- “Delimiter restrictions for moving data” on page 217

#### Related samples:

- “exp samp.sqb -- Export and import tables with table data to a DRDA database (IBM COBOL)”
- “impexp.sqb -- Export and import tables with table data (IBM COBOL)”
- “tload.sqb -- How to export and load table data (IBM COBOL)”
- “tbmove.sqc -- How to move table data (C)”
- “tbmove.sqC -- How to move table data (C++)”

## File type modifiers for export

Table 1. Valid file type modifiers for export: All file formats

Modifier	Description
lobsinfile	<p><i>lob-path</i> specifies the path to the files containing LOB data.</p> <p>Each path contains at least one file that contains at least one LOB pointed to by a Lob Location Specifier (LLS) in the data file. The LLS is a string representation of the location of a LOB in a file stored in the LOB file path. The format of an LLS is <i>filename.ext.nnn.mmm/</i>, where <i>filename.ext</i> is the name of the file that contains the LOB, <i>nnn</i> is the offset in bytes of the LOB within the file, and <i>mmm</i> is the length of the LOB in bytes. For example, if the string <i>db2exp.001.123.456/</i> is stored in the data file, the LOB is located at offset 123 in the file <i>db2exp.001</i>, and is 456 bytes long.</p> <p>If you specify the “lobsinfile” modifier when using EXPORT, the LOB data is placed in the locations specified by the LOBS TO clause. Otherwise the LOB data is sent to the current working directory. The LOBS TO clause specifies one or more paths to directories in which the LOB files are to be stored. There will be at least one file per LOB path, and each file will contain at least one LOB.</p> <p>To indicate a null LOB, enter the size as -1. If the size is specified as 0, it is treated as a 0 length LOB. For null LOBS with length of -1, the offset and the file name are ignored. For example, the LLS of a null LOB might be <i>db2exp.001.7.-1/</i>.</p>

Table 2. Valid file type modifiers for export: DEL (delimited ASCII) file format

Modifier	Description
chardelx	<p><i>x</i> is a single character string delimiter. The default value is a double quotation mark ("). The specified character is used in place of double quotation marks to enclose a character string.<sup>2</sup> If you want to explicitly specify the double quotation mark as the character string delimiter, it should be specified as follows:</p> <pre>modified by charde1""</pre> <p>The single quotation mark (') can also be specified as a character string delimiter as follows:</p> <pre>modified by charde1''</pre>
codepage= <i>x</i>	<p><i>x</i> is an ASCII character string. The value is interpreted as the code page of the data in the output data set. Converts character data to this code page from the application code page during the export operation.</p> <p>For pure DBCS (graphic), mixed DBCS, and EUC, delimiters are restricted to the range of x00 to x3F, inclusive.</p> <p><b>Note:</b> The codepage modifier cannot be used with the <i>lobsinfile</i> modifier.</p>



Table 2. Valid file type modifiers for export: DEL (delimited ASCII) file format (continued)

Modifier	Description
timestampformat="x"	<p data-bbox="558 254 1458 306">x is the format of the time stamp in the source file.<sup>4</sup> Valid time stamp elements are:</p> <p data-bbox="558 317 1458 348">YYYY - Year (four digits ranging from 0000 - 9999)</p> <p data-bbox="558 348 1458 380">M - Month (one or two digits ranging from 1 - 12)</p> <p data-bbox="558 380 1458 432">MM - Month (two digits ranging from 01 - 12; mutually exclusive with M and MMM)</p> <p data-bbox="558 432 1458 485">MMM - Month (three-letter case-insensitive abbreviation for the month name; mutually exclusive with M and MM)</p> <p data-bbox="558 485 1458 516">D - Day (one or two digits ranging from 1 - 31)</p> <p data-bbox="558 516 1458 548">DD - Day (two digits ranging from 1 - 31; mutually exclusive with D)</p> <p data-bbox="558 548 1458 600">DDD - Day of the year (three digits ranging from 001 - 366; mutually exclusive with other day or month elements)</p> <p data-bbox="558 600 1458 653">H - Hour (one or two digits ranging from 0 - 12 for a 12 hour system, and 0 - 24 for a 24 hour system)</p> <p data-bbox="558 653 1458 726">HH - Hour (two digits ranging from 0 - 12 for a 12 hour system, and 0 - 24 for a 24 hour system; mutually exclusive with H)</p> <p data-bbox="558 726 1458 758">M - Minute (one or two digits ranging from 0 - 59)</p> <p data-bbox="558 758 1458 810">MM - Minute (two digits ranging from 0 - 59; mutually exclusive with M, minute)</p> <p data-bbox="558 810 1458 842">S - Second (one or two digits ranging from 0 - 59)</p> <p data-bbox="558 842 1458 894">SS - Second (two digits ranging from 0 - 59; mutually exclusive with S)</p> <p data-bbox="558 894 1458 968">SSSSS - Second of the day after midnight (5 digits ranging from 00000 - 86399; mutually exclusive with other time elements)</p> <p data-bbox="558 968 1458 1041">UUUUUU - Microsecond (6 digits ranging from 000000 - 999999; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1041 1458 1115">UUUUU - Microsecond (5 digits ranging from 00000 - 99999, maps to range from 000000 - 999990; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1115 1458 1188">UUUU - Microsecond (4 digits ranging from 0000 - 9999, maps to range from 000000 - 999900; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1188 1458 1262">UUU - Microsecond (3 digits ranging from 000 - 999, maps to range from 000000 - 999000; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1262 1458 1335">UU - Microsecond (2 digits ranging from 00 - 99, maps to range from 000000 - 990000; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1335 1458 1409">U - Microsecond (1 digit ranging from 0 - 9, maps to range from 000000 - 900000; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1409 1458 1440">TT - Meridian indicator (AM or PM)</p> <p data-bbox="558 1461 1458 1514">Following is an example of a time stamp format: "YYYY/MM/DD HH:MM:SS.UUUUUU"</p> <p data-bbox="558 1545 1458 1640">The MMM element will produce the following values: 'Jan', 'Feb', 'Mar', 'Apr', 'May', 'Jun', 'Jul', 'Aug', 'Sep', 'Oct', 'Nov', and 'Dec'. 'Jan' is equal to month 1, and 'Dec' is equal to month 12.</p> <p data-bbox="558 1661 1458 1713">The following example illustrates how to export data containing user-defined time stamp formats from a table called 'schedule':</p> <pre data-bbox="558 1724 1458 1808">db2 export to delfile2 of del modified by timestampformat="yyyy.mm.dd hh:mm tt" select * from schedule</pre>

## db2Export - Export

Table 3. Valid file type modifiers for export: WSF file format

Modifier	Description
1	Creates a WSF file that is compatible with Lotus 1-2-3 Release 1, or Lotus 1-2-3 Release 1a. <sup>5</sup> This is the default.
2	Creates a WSF file that is compatible with Lotus Symphony Release 1.0. <sup>5</sup>
3	Creates a WSF file that is compatible with Lotus 1-2-3 Version 2, or Lotus Symphony Release 1.1. <sup>5</sup>
4	Creates a WSF file containing DBCS characters.

### Notes:

1. The export utility does not issue a warning if an attempt is made to use unsupported file types with the MODIFIED BY option. If this is attempted, the export operation fails, and an error code is returned.
2. Delimiter restrictions for moving data lists restrictions that apply to the characters that can be used as delimiter overrides.
3. The export utility normally writes
  - date data in YYYYMMDD format
  - char(date) data in "YYYY-MM-DD" format
  - time data in "HH.MM.SS" format
  - time stamp data in "YYYY-MM-DD-HH. MM.SS. uuuuuu" format

Data contained in any datetime columns specified in the SELECT statement for the export operation will also be in these formats.

4. For time stamp formats, care must be taken to avoid ambiguity between the month and the minute descriptors, since they both use the letter M. A month field must be adjacent to other date fields. A minute field must be adjacent to other time fields. Following are some ambiguous time stamp formats:

"M" (could be a month, or a minute)  
"M:M" (Which is which?)  
"M:YYYY:M" (Both are interpreted as month.)  
"S:M:YYYY" (adjacent to both a time value and a date value)

In ambiguous cases, the utility will report an error message, and the operation will fail.

Following are some unambiguous time stamp formats:

"M:YYYY" (Month)  
"S:M" (Minute)  
"M:YYYY:S:M" (Month...Minute)  
"M:H:YYYY:M:D" (Minute...Month)

5. These files can also be directed to a specific product by specifying an L for Lotus 1-2-3, or an S for Symphony in the *filetype-mod* parameter string. Only one value or product designator may be specified.

### Related reference:

- "db2Export - Export" on page 12
- "EXPORT" on page 8
- "Delimiter restrictions for moving data" on page 217

---

## Export Sessions - CLP Examples

The following example shows how to export information from the STAFF table in the SAMPLE database (to which the user must be connected) to myfile.ixf, with the output in IXF format. If the database connection is not through DB2 Connect, the index definitions (if any) will be stored in the output file; otherwise, only the data will be stored:

```
db2 export to myfile.ixf of ixf messages msgs.txt select * from staff
```

The following example shows how to export the information about employees in Department 20 from the STAFF table in the SAMPLE database (to which the user must be connected) to awards.ixf, with the output in IXF format:

```
db2 export to awards.ixf of ixf messages msgs.txt select * from staff
where dept = 20
```

The following example shows how to export LOBs to a DEL file:

```
db2 export to myfile.del of del lobs to mylobs/
lobfile lobs1, lobs2 modified by lobsinfile
select * from emp_photo
```

The following example shows how to export LOBs to a DEL file, specifying a second directory for files that might not fit into the first directory:

```
db2 export to myfile.del of del
lobs to /db2exp1/, /db2exp2/ modified by lobsinfile
select * from emp_photo
```

The following example shows how to export data to a DEL file, using a single quotation mark as the string delimiter, a semicolon as the column delimiter, and a comma as the decimal point. The same convention should be used when importing data back into the database:

```
db2 export to myfile.del of del
modified by chardel'' coldel; decpt,
select * from staff
```

### Related reference:

- “EXPORT” on page 8



---

## Chapter 2. Import

This chapter describes the DB2 UDB import utility, which uses the SQL INSERT statement to write data from an input file into a table or view. If the target table or view already contains data, you can either replace or append to the existing data.

The following topics are covered:

- “Import Overview”
- “Privileges, authorities, and authorization required to use import” on page 26
- “Using import” on page 27
- “Using import in a client/server environment” on page 28
- “Using import with buffered inserts” on page 29
- “Using import with identity columns” on page 29
- “Using import with generated columns” on page 31
- “Using import to recreate an exported table” on page 32
- “Importing large objects (LOBs)” on page 33
- “Importing user-defined distinct types (UDTs)” on page 34
- “Table locking during import” on page 34
- “IMPORT” on page 35
- “db2Import - Import” on page 48
- “Character Set and NLS Considerations” on page 68
- “Import Sessions - CLP Examples” on page 68

For information about importing DB2 Data Links Manager data, see “Using import to move DB2 Data Links Manager data” on page 202. For information about importing data from typed tables, see “Moving data between typed tables” on page 218. For information about importing data from a file on the DB2 Connect workstation to a DRDA server database, and the reverse, see “Moving Data With DB2 Connect” on page 206.

---

### Import Overview

The import utility inserts data from an input file into a table or updatable view. If the table or view receiving the imported data already contains data, you can either replace or append to the existing data.

The following information is required when importing data:

- The path and the name of the input file.
- The name or alias of the target table or view.
- The format of the data in the input file. This format can be IXF, WSF, DEL, or ASC.
- Whether the input data is to be inserted into the table or view, or whether existing data in the table or view is to be updated or replaced by the input data.
- A message file name, if the utility is invoked through the application programming interface (API), **sqluimpr**.
- When working with typed tables, you might need to provide the method or order by which to progress through all of the structured types. The order of

proceeding top-to-bottom, left-to-right through all of the supertables and subtables in the hierarchy is called the *traverse* order. This order is important when moving data between table hierarchies, because it determines where the data is moved in relation to other data.

When working with typed tables, you might also need to provide the subtable list. This list shows into which subtables and attributes to import data.

You can also specify:

- The method to use for importing the data: column location, column name, or relative column position.
- The number of rows to INSERT before committing the changes to the table. Requesting periodic COMMITs reduces the number of rows that are lost if a failure and a ROLLBACK occur during the import operation. It also prevents the DB2® logs from getting full when processing a large input file.
- The number of file records to skip before beginning the import operation. If an error occurs, you can restart the import operation immediately following the last row that was successfully imported and committed.
- The names of the columns within the table or view into which the data is to be inserted.
- A message file name. During DB2 operations such as exporting, importing, loading, binding, or restoring data, you can specify that message files be created to contain the error, warning, and informational messages associated with those operations. Specify the name of these files with the MESSAGES parameter. These message files are standard ASCII text files. Each message in a message file begins on a new line and contains information provided by the DB2 message retrieval facility. To print them, use the printing procedure for your operating system; to view them, use any ASCII editor.

**Note:** Specifying target table column names or a specific importing method makes importing to a remote database slower.

**Related concepts:**

- “Moving data between typed tables” on page 218

**Related reference:**

- “db2Import - Import” on page 48
- “Import Sessions - CLP Examples” on page 68
- “Export/Import/Load Utility File Formats” on page 243
- “IMPORT” on page 35

---

## Privileges, authorities, and authorization required to use import

Privileges enable users to create or access database resources. Authority levels provide a method of grouping privileges and higher-level database manager maintenance and utility operations. Together, these act to control access to the database manager and its database objects. Users can access only those objects for which they have the appropriate authorization; that is, the required privilege or authority.

To use the import utility to create a new table, you must have SYSADM authority, DBADM authority, or CREATETAB privilege for the database. To replace data in an existing table or view, you must have SYSADM authority, DBADM authority, or CONTROL privilege for the table or view, or INSERT, SELECT, UPDATE and

DELETE privileges for the table or view. To append data to an existing table or view, you must have SELECT and INSERT privileges for the table or view.

**Related reference:**

- “db2Import - Import” on page 48
- “IMPORT” on page 35

---

## Using import

**Prerequisites:**

Before invoking the import utility, you must be connected to (or be able to implicitly connect to) the database into which the data will be imported. Since the utility will issue a COMMIT or a ROLLBACK statement, you should complete all transactions and release all locks by performing either a COMMIT or a ROLLBACK before invoking import.

**Restrictions:**

The following restrictions apply to the import utility:

- This utility does not support the use of nicknames.
- If the existing table is a parent table containing a primary key that is referenced by a foreign key in a dependent table, its data cannot be replaced, only appended to.
- You cannot perform an import replace operation into an underlying table of a materialized query table defined in refresh immediate mode.
- You cannot import data into a system table, a summary table, or a table with a structured type column.
- You cannot import data into declared temporary tables.
- Views cannot be created through the import utility.
- Referential constraints and foreign key definitions are not preserved when creating tables from PC/IXF files. (Primary key definitions *are* preserved if the data was previously exported using SELECT \*.)
- Because the import utility generates its own SQL statements, the maximum statement size of 64KB may, in some cases, be exceeded.

The following limitation applies to the import utility:

If the volume of output messages generated by an import operation against a remote database exceeds 60KB, the utility will keep the first 30KB and the last 30KB.

**Procedure:**

*The import utility can be invoked through the command line processor (CLP), the Import notebook in the Control Centre, or an application programming interface (API), **sqluimpr**.*

Following is an example of the IMPORT command issued through the CLP:

```
db2 import from stafftab.ixf of ixf insert into userid.staff
```

To open the Import notebook:

1. From the Control Center, expand the object tree until you find the Tables folder.

2. Click on the Tables folder. Any existing tables are displayed in the pane on the right side of the window (the contents pane).
3. Click the right mouse button on the table you want in the contents pane, and select Import from the pop-up menu. The Import notebook opens.

Detailed information about the Control Center is provided through its online help facility.

**Related reference:**

- “db2Import - Import” on page 48

**Related samples:**

- “tbmove.out -- HOW TO MOVE TABLE DATA (C)”
- “tbmove.sqc -- How to move table data (C)”
- “tbmove.out -- HOW TO MOVE TABLE DATA (C++)”
- “tbmove.sqC -- How to move table data (C++)”

---

## Using import in a client/server environment

When you import a file to a remote database, a stored procedure can be called to perform the import on the server. A stored procedure will not be called when:

- The application and database code pages are different.
- The file being imported is a multiple-part PC/IXF file.
- The method used for importing the data is either column name or relative column position.
- The target column list provided is longer than 4KB.
- The LOBS FROM clause or the `lobsinfile` modifier is specified.
- The NULL INDICATORS clause is specified for ASC files.

When import uses a stored procedure, messages are created in the message file using the default language installed on the server. The messages are in the language of the application if the language at the client and the server are the same.

The import utility creates two temporary files in the `tmp` subdirectory of the `sql1ib` directory (or the directory indicated by the **DB2INSTPROF** registry variable, if specified). One file is for data, and the other file is for messages generated by the import utility.

If you receive an error about writing or opening data on the server, ensure that:

- The directory exists.
- There is sufficient disk space for the files.
- The instance owner has write permission in the directory.

**Related concepts:**

- “Import Overview” on page 25

---

## Using import with buffered inserts

In a partitioned database environment, the import utility can be enabled to use buffered inserts. This reduces the messaging that occurs when data is imported, resulting in better performance; however, since details about a failed buffered insert are not returned, this option should only be enabled if you are not concerned about error reporting.

| When buffered inserts are used, import sets a default WARNINGCOUNT value to  
| 1. As a result, the utility will fail if any rows are rejected. If a record is rejected, the  
| utility will roll back the current transaction. The number of committed records can  
| be used to determine which records were successfully inserted into the database.  
| The number of committed records can be non zero only if the COMMITCOUNT  
| option was specified.

| If a different WARNINGCOUNT value is explicitly specified on the import  
| command, and some rows were rejected, the row summary output by the utility  
| can be incorrect. This is due to a combination of the asynchronous error reporting  
| used with buffered inserts and the fact that an error detected during the insertion  
| of a group of rows causes all the rows of that group to be backed out. Since the  
| utility would not reliably report which input records were rejected, it would be  
| difficult to determine which records were committed and which records need to be  
| re-inserted into the database.

Use the DB2® bind utility to request buffered inserts. The import package, db2uimpb.bnd, must be rebound against the database using the INSERT BUF option. For example:

```
db2 connect to your_database
db2 bind db2uimpb.bnd insert buf
```

| Buffered inserts feature cannot be used in conjunction with import operations in  
| which the INSERT\_UPDATE parameter is specified. A new bind file  
| (db2uimpb2.bnd) is introduced to enforce this restriction. The new file should  
| never be bound with INSERT BUF option, as doing so will cause the import  
| operations in which the INSERT\_UPDATE parameter is specified to fail. Import  
| operations in which INSERT, REPLACE or REPLACE\_CREATE parameter is  
| specified are not affected by the binding of the new file.

### Related concepts:

- “Import Overview” on page 25

---

## Using import with identity columns

The import utility can be used to import data into a table containing an identity column. If no identity-related file type modifiers are used, the utility works according to the following rules:

- If the identity column is GENERATED ALWAYS, an identity value is generated for a table row whenever the corresponding row in the input file is missing a value for the identity column, or a NULL value is explicitly given. If a non-NULL value is specified for the identity column, the row is rejected (SQL3550W).
- If the identity column is GENERATED BY DEFAULT, the import utility makes use of user-supplied values, if they are provided; if the data is missing or explicitly NULL, a value is generated.

The import utility does not perform any extra validation of user-supplied identity values beyond what is normally done for values of the identity column's data type (that is, SMALLINT, INT, BIGINT, or DECIMAL). Duplicate values will not be reported. In addition, the `compound=x` modifier cannot be used when importing data into a table with an identity column.

Two file type modifiers are supported by the import utility to simplify its use with tables that contain an identity column:

- The `identitymissing` modifier makes importing a table with an identity column more convenient if the input data file does not contain any values (not even NULLS) for the identity column. For example, consider a table defined with the following SQL statement:

```
create table table1 (c1 char(30),
                   c2 int generated by default as identity,
                   c3 real,
                   c4 char(1))
```

A user might want to import data from a file (`import.del`) into TABLE1, and this data might have been exported from a table that does not have an identity column. The following is an example of such a file:

```
Robert, 45.2, J
Mike, 76.9, K
Leo, 23.4, I
```

One way to import this file would be to explicitly list the columns to be imported through the IMPORT command as follows:

```
db2 import from import.del of del replace into table1 (c1, c3, c4)
```

For a table with many columns, however, this syntax might be cumbersome and prone to error. An alternate method of importing the file is to use the `identitymissing` file type modifier as follows:

```
db2 import from import.del of del modified by identitymissing
replace into table1
```

- The `identityignore` modifier is in some ways the opposite of the `identitymissing` modifier: it indicates to the import utility that even though the input data file contains data for the identity column, the data should be ignored, and an identity value should be generated for each row. For example, a user might want to import the following data from a file (`import.del`) into TABLE1, as defined above:

```
Robert, 1, 45.2, J
Mike, 2, 76.9, K
Leo, 3, 23.4, I
```

If the user-supplied values of 1, 2, and 3 are not to be used for the identity column, the user could issue the following IMPORT command:

```
db2 import from import.del of del method P(1, 3, 4)
replace into table1 (c1, c3, c4)
```

Again, this approach might be cumbersome and prone to error if the table has many columns. The `identityignore` modifier simplifies the syntax as follows:

```
db2 import from import.del of del modified by identityignore
replace into table1
```

When a table with an identity column is exported to an IXF file, the `REPLACE_CREATE` and the `CREATE` options of the IMPORT command can be used to recreate the table, including its identity column properties. If such an IXF file is created from a table containing an identity column of type `GENERATED ALWAYS`, the only way that the data file can be successfully imported is to specify the `identityignore` modifier. Otherwise, all rows will be rejected (SQL3550W).

**Related concepts:**

- “Identity columns” in the *Administration Guide: Planning*

---

## Using import with generated columns

The import utility can be used to import data into a table containing (non-identity) generated columns.

If no generated column-related file type modifiers are used, the import utility works according to the following rules:

- A value will be generated for a generated column whenever the corresponding row in the input file is missing a value for the column, or a NULL value is explicitly given. If a non-NULL value is supplied for a generated column, the row is rejected (SQL3550W).
- If the server generates a NULL value for a generated column that is not nullable, the row of data to which this field belongs is rejected (SQL0407N). This could happen, for example, if a non-nullable generated column were defined as the sum of two table columns that have NULL values supplied to them in the input file.

Two file type modifiers are supported by the import utility to simplify its use with tables that contain generated columns:

- The `generatedmissing` modifier makes importing data into a table with generated columns more convenient if the input data file does not contain any values (not even NULLS) for all generated columns present in the table. For example, consider a table defined with the following SQL statement:

```
create table table1 (c1 int,
                    c2 int,
                    g1 int generated always as (c1 + c2),
                    g2 int generated always as (2 * c1),
                    c3 char(1))
```

A user might want to import data from a file (`load.del`) into `TABLE1`, and this data might have been exported from a table that does not have any generated columns. The following is an example of such a file:

```
1, 5, J
2, 6, K
3, 7, I
```

One way to import this file would be to explicitly list the columns to be imported through the `IMPORT` command as follows:

```
db2 import from import.del of del replace into table1 (c1, c2, c3)
```

For a table with many columns, however, this syntax might be cumbersome and prone to error. An alternate method of importing the file is to use the `generatedmissing` file type modifier as follows:

```
db2 import from import.del of del modified by generatedmissing
replace into table1
```

- The `generatedignore` modifier is in some ways the opposite of the `generatedmissing` modifier: it indicates to the import utility that even though the input data file contains data for all generated columns, the data should be ignored, and values should be generated for each row. For example, a user might want to import the following data from a file (`import.del`) into `TABLE1`, as defined above:

```
1, 5, 10, 15, J
2, 6, 11, 16, K
3, 7, 12, 17, I
```

The user-supplied, non-NULL values of 10, 11, and 12 (for g1), and 15, 16, and 17 (for g2) result in the row being rejected (SQL3550W). To avoid this, the user could issue the following IMPORT command:

```
db2 import from import.del of del method P(1, 2, 5)
replace into table1 (c1, c2, c3)
```

Again, this approach might be cumbersome and prone to error if the table has many columns. The generatedignore modifier simplifies the syntax as follows:

```
db2 import from import.del of del modified by generatedignore
replace into table1
```

**Related concepts:**

- “Generated Columns” in the *Application Development Guide: Programming Client Applications*

---

## Using import to recreate an exported table

You can use the import utility to recreate a table that was saved through the export utility. The table must have been exported to an IXF file, and the SELECT statement used during the export operation must have met certain conditions (for example, no column names can be used in the SELECT clause; only select \* is permitted). When creating a table from an IXF file, not all attributes of the original table are preserved. For example, referential constraints, foreign key definitions, and user-defined data types are not retained. The following attributes of the original table are retained:

- Primary key name, and definition
- Unique constraints names, and definitions, but not other types of constraints or triggers
- Column information:
  - Column name
  - Column data type, including user-defined distinct types, which are preserved as their base type
  - Identity properties
  - Lengths (except for lob\_file types)
  - Code page (if applicable)
  - DATALINK options
  - Identity options
  - Whether the column is defined as nullable or not nullable
  - Default values for constants, if any, but not other types of default values
- Index information:
  - Index name
  - Index creator name
  - Column names, and whether each column is sorted in ascending, or in descending order
  - Whether the index is defined as unique
  - Whether the index is clustered
  - Whether the index allows reverse scans
  - *pctfree* values
  - *minpctused* values

The following attributes of the original table are *not* retained:

- Whether the source was a normal table, a materialized query table, a view, or a set of columns from any or all of these sources
- Table information:
  - Materialized query table definition (if applicable)
  - Materialized query table options (if applicable)
  - Table space options; however, this information can be specified through the IMPORT command
- Column information:
  - Any default value except constant values
  - LOB options (if any)
  - References clause of the create table statement (if any)
  - Referential constraints (if any)
  - Check constraints (if any)
  - Generated column options (if any)
- Index information:
  - Include columns (if any)

**Related concepts:**

- “Recreating an exported table” on page 4

## Importing large objects (LOBS)

When importing into large object (LOB) columns, the data can come either from the same file as the rest of the column data, or from separate files. If the data is coming from separate files the LOBSINFILE file type modifier must be specified.

The column in the main input data file contains either the import data (default), or the name of a file where the import data is stored.

**Notes:**

1. When LOB data is stored in the main input data file, no more than 32KB of data is allowed. Truncation warnings are ignored.
2. All of the LOB data must be stored in the main file, or each LOB is stored in separate files. The main file cannot have a mixture of LOB data and file names. LOB values are imported from separate files by using the `lobsinfile` modifier, and the LOBS FROM clause.

A LOB Location Specifier (LLS) can be used to store multiple LOBs in a single file when importing, exporting and loading LOB information.

An LLS is a string indicating where LOB data can be found within a file. The format of the LLS is `filename.ext.nnn.mmm/`, where `filename.ext` is the name of the file that contains the LOB, `nnn` is the offset of the LOB within the file (measured in bytes), and `mmm` is the length of the LOB (in bytes). For example, an LLS of `db2exp.001.123.456/` indicates that the LOB is located in the file `db2exp.001`, begins at an offset of 123 bytes into the file, and is 256 bytes long. If the indicated size in the LLS is 0, the LOB is considered to have a length of 0. If the length is -1, the LOB is considered to be NULL and the offset and file name are ignored.

When importing or loading data with the modified by `lobsinfile` option specified, An LLS will be expected for each of the corresponding LOB columns. If

something other than an LLS is encountered for a LOB column, the database will treat it as a LOB file, and will load the entire file as the LOB.

**Related reference:**

- “General Rules Governing PC/IXF File Import into Databases” on page 279
- “Data Type-Specific Rules Governing PC/IXF File Import into Databases” on page 281
- “IMPORT” on page 35
- “Large objects (LOBs)” in the *SQL Reference, Volume 1*

---

## Importing user-defined distinct types (UDTs)

The import utility casts user-defined distinct types (UDTs) to similar base data types automatically. This saves you from having to explicitly cast UDTs to the base data types. Casting allows for comparisons between UDTs and the base data types in SQL.

**Related concepts:**

- “User-defined distinct types” in the *Application Development Guide: Programming Server Applications*

---

## Table locking during import

4 The import utility supports two table locking modes. The offline mode (ALLOW  
4 NO ACCESS) prevents concurrent applications from accessing table data. This is  
4 the default mode. The online mode (ALLOW WRITE ACCESS) allows concurrent  
4 applications both read and write access to the import target table.

4 By default, the import utility is bound to the database with isolation level RS (read  
4 stability).

4 **Online Import (ALLOW WRITE ACCESS):**

4 The Import utility acquires a nonexclusive (IX) lock on the target table. Holding  
4 this lock on the table has the following implications:

- 4 • If there are other applications holding an incompatible table lock, the import  
4 utility will not start inserting data until all of these applications commit or roll  
4 back their changes.
- 4 • While import is running, any other application requesting an incompatible table  
4 lock will wait until the import commits or rolls back the current transaction.  
4 Note that import’s table lock does not persist across a transaction boundary. As a  
4 result, online import has to request and potentially wait for a table lock after  
4 every commit.
- 4 • If there are other applications holding an incompatible row lock, the import  
4 utility will stop inserting data until all of these applications commit or roll back  
4 their changes.
- 4 • While import is running, any other application requesting an incompatible row  
4 lock will wait until the import operation commits or rolls back the current  
4 transaction.

4 To preserve the online properties, and to reduce the chance of a deadlock, online  
4 import will periodically commit the current transaction and release all row locks

4 before escalating to an exclusive (X) table lock. Consequently, during an online  
4 import, commits might be performed even if the commitcount option was not  
4 used. A commit frequency can either be explicitly specified, or the AUTOMATIC  
4 commit mode can be used. No commits will be performed if a commitcount value  
4 of zero is explicitly specified. Note that a deadlock will occur if the concurrent  
4 application holding a conflicting row lock attempts to escalate to a table lock.

4 Import runs in the online mode if 'ALLOW WRITE ACCESS' is specified. The  
4 online mode is not compatible with the following:

- 4 • REPLACE, CREATE and REPLACE\_CREATE import modes
- 4 • Buffered inserts
- 4 • Imports into a target view
- 4 • Imports into a hierarchy table
- 4 • Imports into a target table using table lock size

#### 4 **Offline Import (ALLOW NO ACCESS):**

4 If a large number of rows is being imported into a table, the existing lock might  
4 escalate to an exclusive lock. If another application working on the same table is  
4 holding some row locks, a deadlock will occur if the lock escalates to an exclusive  
4 lock. To avoid this, the import utility requests an exclusive lock on the table at the  
4 beginning of its operation. This is the default import behavior.

4 Holding a lock on the table has two implications. First, if there are other  
4 applications holding a table lock, or row locks on the import target table, the  
4 import utility will wait until all of those applications commit or roll back their  
4 changes. Second, while import is running, any other application requesting locks  
4 will wait until the import operation has completed. Import runs in the offline  
4 mode if 'ALLOW WRITE ACCESS' is not specified.

#### **Related concepts:**

- "Table locking, table states and table space states" on page 162

---

## IMPORT

Inserts data from an external file with a supported file format into a table, hierarchy, or view. LOAD is a faster alternative, but the load utility does not support loading data at the hierarchy level.

#### **Authorization:**

- IMPORT using the INSERT option requires one of the following:
  - *sysadm*
  - *dbadm*
  - CONTROL privilege on each participating table or view
  - INSERT and SELECT privilege on each participating table or view
- IMPORT to an existing table using the INSERT\_UPDATE option, requires one of the following:
  - *sysadm*
  - *dbadm*
  - CONTROL privilege on the table or view


# IMPORT

- INSERT, SELECT, UPDATE and DELETE privilege on each participating table or view
- IMPORT to an existing table using the REPLACE or REPLACE\_CREATE option, requires one of the following:
  - *sysadm*
  - *dbadm*
  - CONTROL privilege on the table or view
  - INSERT, SELECT, and DELETE privilege on the table or view
- IMPORT to a new table using the CREATE or REPLACE\_CREATE option, requires one of the following:
  - *sysadm*
  - *dbadm*
  - CREATETAB authority on the database and USE privilege on the table space, as well as one of:
    - IMPLICIT\_SCHEMA authority on the database, if the implicit or explicit schema name of the table does not exist
    - CREATIN privilege on the schema, if the schema name of the table refers to an existing schema
- IMPORT to an existing hierarchy using the REPLACE option requires one of the following:
  - *sysadm*
  - *dbadm*
  - CONTROL privilege on every sub-table in the hierarchy

## Required connection:


Database. If implicit connect is enabled, a connection to the default database is established.

## Command syntax:



4


4



**hierarchy description:**




**sub-table-list:**




**traversal-order-list:**



**tblspace-specs:**



**datalink-spec:**



**Command parameters:**

**ALL TABLES**

An implicit keyword for hierarchy only. When importing a hierarchy, the default is to import all tables specified in the traversal order.

**ALLOW NO ACCESS**

Runs import in the offline mode. An exclusive (X) lock on the target table is acquired before any rows are inserted. This prevents concurrent applications from accessing table data. This is the default import behavior.

4  
4  
4  
4

## IMPORT

### ALLOW WRITE ACCESS

Runs import in the online mode. An intent exclusive (IX) lock on the target table is acquired when the first row is inserted. This allows concurrent readers and writers to access table data. Online mode is not compatible with the REPLACE, CREATE, or REPLACE\_CREATE import options. Online mode is not supported in conjunction with buffered inserts. The import operation will periodically commit inserted data to prevent lock escalation to a table lock and to avoid running out of active log space. These commits will be performed even if the COMMITCOUNT option was not used. During each commit, import will lose its IX table lock, and will attempt to reacquire it after the commit.

### AS ROOT TABLE

Creates one or more sub-tables as a stand-alone table hierarchy.

### COMMITCOUNT *n*/AUTOMATIC

Performs a COMMIT after every *n* records are imported. When a number *n* is specified, import performs a COMMIT after every *n* records are imported. When compound inserts are used, a user-specified commit frequency of *n* is rounded up to the first integer multiple of the compound count value. When AUTOMATIC is specified, import internally determines when a commit needs to be performed. The utility will commit for either one of two reasons:

- to avoid running out of active log space
- to avoid lock escalation from row level to table level

If the ALLOW WRITE ACCESS option is specified, and the COMMITCOUNT option is not specified, the import utility will perform commits as if COMMITCOUNT AUTOMATIC had been specified.

### CREATE

Creates the table definition and row contents in the code page of the database. If the data was exported from a DB2 table, sub-table, or hierarchy, indexes are created. If this option operates on a hierarchy, and data was exported from DB2, a type hierarchy will also be created. This option can only be used with IXF files.

**Note:** If the data was exported from an MVS host database, and it contains LONGVAR fields whose lengths, calculated on the page size, are less than 254, CREATE may fail because the rows are too long. See Using import to recreate an exported table for a list of restrictions. In this case, the table should be created manually, and IMPORT with INSERT should be invoked, or, alternatively, the LOAD command should be used.

### DATALINK SPECIFICATION

For each DATALINK column, there can be one column specification enclosed by parentheses. Each column specification consists of one or more DL\_LINKTYPE, prefix, and a DL\_URL\_SUFFIX specification. The prefix specification can be either DL\_URL\_REPLACE\_PREFIX or DL\_URL\_DEFAULT\_PREFIX.

There can be as many DATALINK column specifications as the number of DATALINK columns defined in the table. The order of specifications follows the order of DATALINK columns found within the *insert-column* list, or within the table definition (if an *insert-column* list is not specified).

**DL\_LINKTYPE**

If specified, it should match the LINKTYPE of the column definition. Thus, DL\_LINKTYPE URL is acceptable if the column definition specifies LINKTYPE URL.

**DL\_URL\_DEFAULT\_PREFIX "prefix"**

If specified, it should act as the default prefix for all DATALINK values within the same column. In this context, prefix refers to the "scheme host port" part of the URL specification.

Examples of prefix are:

```
"http://server"
"file://server"
"file:"
"http://server:80"
```

If no prefix is found in a column's data, and a default prefix is specified with DL\_URL\_DEFAULT\_PREFIX, the default prefix is prefixed to the column value (if not NULL).

For example, if DL\_URL\_DEFAULT\_PREFIX specifies the default prefix "http://toronto":

- The column input value "/x/y/z" is stored as "http://toronto/x/y/z".
- The column input value "http://coyote/a/b/c" is stored as "http://coyote/a/b/c".
- The column input value NULL is stored as NULL.

**DL\_URL\_REPLACE\_PREFIX "prefix"**

This clause is useful for loading or importing data previously generated by the export utility, when the user wants to globally replace the host name in the data with another host name. If specified, it becomes the prefix for *all* non-NULL column values. If a column value has a prefix, this will replace it. If a column value has no prefix, the prefix specified by DL\_URL\_REPLACE\_PREFIX is prefixed to the column value.

For example, if DL\_URL\_REPLACE\_PREFIX specifies the prefix "http://toronto":

- The column input value "/x/y/z" is stored as "http://toronto/x/y/z".
- The column input value "http://coyote/a/b/c" is stored as "http://toronto/a/b/c". Note that "toronto" replaces "coyote".
- The column input value NULL is stored as NULL.

**DL\_URL\_SUFFIX "suffix"**

If specified, it is appended to every non-NULL column value for the column. It is, in fact, appended to the "path" component of the URL part of the DATALINK value.

**FROM filename**

Specifies the file that contains the data to be imported. If the path is omitted, the current working directory is used.

**HIERARCHY**

Specifies that hierarchical data is to be imported.

**IN tablespace-name**

Identifies the table space in which the table will be created. The table space must exist, and must be a REGULAR table space. If no other table space is specified, all table parts are stored in this table space. If this clause is not specified, the table is created in a table space created by the authorization

## IMPORT

ID. If none is found, the table is placed into the default table space USERSPACE1. If USERSPACE1 has been dropped, table creation fails.

### **INDEX IN tablespace-name**

Identifies the table space in which any indexes on the table will be created. This option is allowed only when the primary table space specified in the IN clause is a DMS table space. The specified table space must exist, and must be a REGULAR or LARGE DMS table space.

**Note:** Specifying which table space will contain an index can only be done when the table is created.

### **insert-column**

Specifies the name of a column in the table or the view into which data is to be inserted.

### **INSERT**

Adds the imported data to the table without changing the existing table data.

### **INSERT\_UPDATE**

Adds rows of imported data to the target table, or updates existing rows (of the target table) with matching primary keys.

### **INTO table-name**

Specifies the database table into which the data is to be imported. This table cannot be a system table, a declared temporary table or a summary table.

One can use an alias for INSERT, INSERT\_UPDATE, or REPLACE, except in the case of a down-level server, when the fully qualified or the unqualified table name should be used. A qualified table name is in the form: *schema.tablename*. The *schema* is the user name under which the table was created.

### **LOBS FROM lob-path**

Specifies one or more paths that store LOB files. The names of the LOB data files are stored in the main data file (ASC, DEL, or IXF), in the column that will be loaded into the LOB column. This option is ignored if the lobsinfile modifier is not specified.

### **LONG IN tablespace-name**

Identifies the table space in which the values of any long columns (LONG VARCHAR, LONG VARGRAPHIC, LOB data types, or distinct types with any of these as source types) will be stored. This option is allowed only if the primary table space specified in the IN clause is a DMS table space. The table space must exist, and must be a LARGE DMS table space.

### **MESSAGES message-file**

Specifies the destination for warning and error messages that occur during an import operation. If the file already exists, the import utility appends the information. If the complete path to the file is not specified, the utility uses the current directory and the default drive as the destination. If *message-file* is omitted, the messages are written to standard output.

### **METHOD**

**L** Specifies the start and end column numbers from which to import data. A column number is a byte offset from the beginning of a row of data. It is numbered starting from 1.

**Note:** This method can only be used with ASC files, and is the only valid option for that file type.

**N** Specifies the names of the columns to be imported.

**Note:** This method can only be used with IXF files.

**P** Specifies the field numbers of the input data fields to be imported.

**Note:** This method can only be used with IXF or DEL files, and is the only valid option for the DEL file type.

#### **MODIFIED BY filetype-mod**

Specifies file type modifier options. See File type modifiers for import.

#### **NOTIMEOUT**

Specifies that the import utility will not time out while waiting for locks. This option supersedes the *locktimeout* database configuration parameter. Other applications are not affected.

#### **NULL INDICATORS null-indicator-list**

This option can only be used when the METHOD L parameter is specified. That is, the input file is an ASC file. The null indicator list is a comma-separated list of positive integers specifying the column number of each null indicator field. The column number is the byte offset of the null indicator field from the beginning of a row of data. There must be one entry in the null indicator list for each data field defined in the METHOD L parameter. A column number of zero indicates that the corresponding data field always contains data.

A value of Y in the NULL indicator column specifies that the column data is NULL. Any character *other than* Y in the NULL indicator column specifies that the column data is not NULL, and that column data specified by the METHOD L option will be imported.

The NULL indicator character can be changed using the MODIFIED BY option, with the nullindchar file type modifier.

#### **OF filetype**

Specifies the format of the data in the input file:

- ASC (non-delimited ASCII format)
- DEL (delimited ASCII format), which is used by a variety of database manager and file manager programs
- WSF (work sheet format), which is used by programs such as:
  - Lotus 1-2-3
  - Lotus Symphony
- IXF (integrated exchange format, PC version), which means it was exported from the same or another DB2 table. An IXF file also contains the table definition and definitions of any existing indexes, except when columns are specified in the SELECT statement.

#### **REPLACE**

Deletes all existing data from the table by truncating the data object, and inserts the imported data. The table definition and the index definitions are not changed. This option can only be used if the table exists. It is not valid for tables with DATALINK columns. If this option is used when moving data between hierarchies, only the data for an entire hierarchy, not individual subtables, can be replaced.

4  
4  
4  
4

## IMPORT

### REPLACE\_CREATE

If the table exists, deletes all existing data from the table by truncating the data object, and inserts the imported data without changing the table definition or the index definitions.

3 If the table does not exist, creates the table and index definitions, as well as  
3 the row contents, in the code page of the database. See Using import to  
3 recreate an exported table for a list of restrictions.

This option can only be used with IXF files. It is not valid for tables with DATALINK columns. If this option is used when moving data between hierarchies, only the data for an entire hierarchy, not individual subtables, can be replaced.

### RESTARTCOUNT *n*

Specifies that an import operation is to be started at record  $n + 1$ . The first  $n$  records are skipped. This option is functionally equivalent to SKIPCOUNT. RESTARTCOUNT and SKIPCOUNT are mutually exclusive.

### ROWCOUNT *n*

4 Specifies the number  $n$  of physical records in the file to be imported  
4 (inserted or updated). Allows a user to import only  $n$  rows from a file,  
4 starting from the record determined by the SKIPCOUNT or  
4 RESTARTCOUNT options. If the SKIPCOUNT or RESTARTCOUNT  
4 options are not specified, the first  $n$  rows are imported. If SKIPCOUNT  $m$   
4 or RESTARTCOUNT  $m$  is specified, rows  $m+1$  to  $m+n$  are imported. When  
4 compound inserts are used, user specified rowcount  $n$  is rounded up to the  
4 first integer multiple of the compound count value.

### SKIPCOUNT *n*

4 Specifies that an import operation is to be started at record  $n + 1$ . The first  
4  $n$  records are skipped. This option is functionally equivalent to  
4 RESTARTCOUNT. SKIPCOUNT and RESTARTCOUNT are mutually  
4 exclusive.

### STARTING *sub-table-name*

A keyword for hierarchy only, requesting the default order, starting from *sub-table-name*. For PC/IXF files, the default order is the order stored in the input file. The default order is the only valid order for the PC/IXF file format.

### *sub-table-list*

For typed tables with the INSERT or the INSERT\_UPDATE option, a list of sub-table names is used to indicate the sub-tables into which data is to be imported.

### *traversal-order-list*

For typed tables with the INSERT, INSERT\_UPDATE, or the REPLACE option, a list of sub-table names is used to indicate the traversal order of the importing sub-tables in the hierarchy.

### UNDER *sub-table-name*

Specifies a parent table for creating one or more sub-tables.

### WARNINGCOUNT *n*

4 Stops the import operation after  $n$  warnings. Set this parameter if no  
4 warnings are expected, but verification that the correct file and table are  
4 being used is desired. If the import file or the target table is specified  
4 incorrectly, the import utility will generate a warning for each row that it

4 attempts to import, which will cause the import to fail. If *n* is zero, or this  
 4 option is not specified, the import operation will continue regardless of the  
 4 number of warnings issued.

### Examples:

#### Example 1

The following example shows how to import information from myfile.ixf to the STAFF table:

```
db2 import from myfile.ixf of ixf messages msg.txt insert into staff

SQL3150N The H record in the PC/IXF file has product "DB2 01.00", date
"19970220", and time "140848".

SQL3153N The T record in the PC/IXF file has name "myfile",
qualifier " ", and source " ".

SQL3109N The utility is beginning to load data from file "myfile".

SQL3110N The utility has completed processing. "58" rows were read
from the input file.

SQL3221W ...Begin COMMIT WORK. Input Record Count = "58".

SQL3222W ...COMMIT of any database changes was successful.

SQL3149N "58" rows were processed from the input file. "58" rows were
successfully inserted into the table. "0" rows were rejected.
```

#### Example 2

The following example shows how to import the table MOVIE TABLE from the input file delfile1, which has data in the DEL format:

```
db2 import from delfile1 of del
modified by dldel|
insert into movietable (actorname, description, url_making_of,
url_movie) datalink specification (dl_url_default_prefix
"http://narang"), (dl_url_replace_prefix "http://bomdel"
dl_url_suffix ".mpeg")
```

### Notes:

1. The table has four columns:

actorname	VARCHAR(n)
description	VARCHAR(m)
url_making_of	DATALINK (with LINKTYPE URL)
url_movie	DATALINK (with LINKTYPE URL)

2. The DATALINK data in the input file has the vertical bar (|) character as the sub-field delimiter.
3. If any column value for url\_making\_of does not have the prefix character sequence, "http://narang" is used.
4. Each non-NULL column value for url\_movie will get "http://bomdel" as its prefix. Existing values are replaced.
5. Each non-NULL column value for url\_movie will get ".mpeg" appended to the path. For example, if a column value of url\_movie is "http://server1/x/y/z", it will be stored as "http://bomdel/x/y/z.mpeg"; if the value is "/x/y/z", it will be stored as "http://bomdel/x/y/z.mpeg".

#### Example 3 (Importing into a Table with an Identity Column)

## IMPORT

TABLE1 has 4 columns:

- C1 VARCHAR(30)
- C2 INT GENERATED BY DEFAULT AS IDENTITY
- C3 DECIMAL(7,2)
- C4 CHAR(1)

TABLE2 is the same as TABLE1, except that C2 is a GENERATED ALWAYS identity column.

Data records in DATAFILE1 (DEL format):

```
"Liszt"  
"Hummel",,187.43, H  
"Grieg",100, 66.34, G  
"Satie",101, 818.23, I
```

Data records in DATAFILE2 (DEL format):

```
"Liszt", 74.49, A  
"Hummel", 0.01, H  
"Grieg", 66.34, G  
"Satie", 818.23, I
```

The following command generates identity values for rows 1 and 2, since no identity values are supplied in DATAFILE1 for those rows. Rows 3 and 4, however, are assigned the user-supplied identity values of 100 and 101, respectively.

```
db2 import from datafile1.del of del replace into table1
```

To import DATAFILE1 into TABLE1 so that identity values are generated for all rows, issue one of the following commands:

```
db2 import from datafile1.del of del method P(1, 3, 4)  
replace into table1 (c1, c3, c4)  
db2 import from datafile1.del of del modified by identityignore  
replace into table1
```

To import DATAFILE2 into TABLE1 so that identity values are generated for each row, issue one of the following commands:

```
db2 import from datafile2.del of del replace into table1 (c1, c3, c4)  
db2 import from datafile2.del of del modified by identitymissing  
replace into table1
```

If DATAFILE1 is imported into TABLE2 without using any of the identity-related file type modifiers, rows 1 and 2 will be inserted, but rows 3 and 4 will be rejected, because they supply their own non-NULL values, and the identity column is GENERATED ALWAYS.

### Usage notes:

Be sure to complete all table operations and release all locks before starting an import operation. This can be done by issuing a COMMIT after closing all cursors opened WITH HOLD, or by issuing a ROLLBACK.

The import utility adds rows to the target table using the SQL INSERT statement. The utility issues one INSERT statement for each row of data in the input file. If an INSERT statement fails, one of two actions result:

- If it is likely that subsequent INSERT statements can be successful, a warning message is written to the message file, and processing continues.

- If it is likely that subsequent INSERT statements will fail, and there is potential for database damage, an error message is written to the message file, and processing halts.

The utility performs an automatic COMMIT after the old rows are deleted during a REPLACE or a REPLACE\_CREATE operation. Therefore, if the system fails, or the application interrupts the database manager after the table object is truncated, all of the old data is lost. Ensure that the old data is no longer needed before using these options.

If the log becomes full during a CREATE, REPLACE, or REPLACE\_CREATE operation, the utility performs an automatic COMMIT on inserted records. If the system fails, or the application interrupts the database manager after an automatic COMMIT, a table with partial data remains in the database. Use the REPLACE or the REPLACE\_CREATE option to rerun the whole import operation, or use INSERT with the RESTARTCOUNT parameter set to the number of rows successfully imported.

4 By default, automatic COMMITs are not performed for the INSERT or the  
4 INSERT\_UPDATE option. They are, however, performed if the COMMITCOUNT  
4 parameter is not zero. If automatic COMMITs are not performed, a full log results  
4 in a ROLLBACK.

4 Offline import does not perform automatic COMMITs if any of the following  
4 conditions is true:

- 4 • the target is a view, not a table
- 4 • compound inserts are used
- 4 • buffered inserts are used

4 By default, online import performs automatic COMMITs to free both the active log  
4 space and the lock list. Automatic COMMITs are not performed only if a  
4 COMMITCOUNT value of zero is specified.

Whenever the import utility performs a COMMIT, two messages are written to the message file: one indicates the number of records to be committed, and the other is written after a successful COMMIT. When restarting the import operation after a failure, specify the number of records to skip, as determined from the last successful COMMIT.

The import utility accepts input data with minor incompatibility problems (for example, character data can be imported using padding or truncation, and numeric data can be imported with a different numeric data type), but data with major incompatibility problems is not accepted.

One cannot REPLACE or REPLACE\_CREATE an object table if it has any dependents other than itself, or an object view if its base table has any dependents (including itself). To replace such a table or a view, do the following:

1. Drop all foreign keys in which the table is a parent.
2. Run the import utility.
3. Alter the table to recreate the foreign keys.

If an error occurs while recreating the foreign keys, modify the data to maintain referential integrity.

## IMPORT

Referential constraints and foreign key definitions are not preserved when creating tables from PC/IXF files. (Primary key definitions *are* preserved if the data was previously exported using SELECT \*.)

Importing to a remote database requires enough disk space on the server for a copy of the input data file, the output message file, and potential growth in the size of the database.

If an import operation is run against a remote database, and the output message file is very long (more than 60KB), the message file returned to the user on the client may be missing messages from the middle of the import operation. The first 30KB of message information and the last 30KB of message information are always retained.

Importing PC/IXF files to a remote database is much faster if the PC/IXF file is on a hard drive rather than on diskettes.

The database table or hierarchy must exist before data in the ASC, DEL, or WSF file formats can be imported; however, if the table does not already exist, IMPORT CREATE or IMPORT REPLACE\_CREATE creates the table when it imports data from a PC/IXF file. For typed tables, IMPORT CREATE can create the type hierarchy and the table hierarchy as well.

PC/IXF import should be used to move data (including hierarchical data) between databases. If character data containing row separators is exported to a delimited ASCII (DEL) file and processed by a text transfer program, fields containing the row separators will shrink or expand. The file copying step is not necessary if the source and the target databases are both accessible from the same client.

The data in ASC and DEL files is assumed to be in the code page of the client application performing the import. PC/IXF files, which allow for different code pages, are recommended when importing data in different code pages. If the PC/IXF file and the import utility are in the same code page, processing occurs as for a regular application. If the two differ, and the FORCEIN option is specified, the import utility assumes that data in the PC/IXF file has the same code page as the application performing the import. This occurs even if there is a conversion table for the two code pages. If the two differ, the FORCEIN option is not specified, and there is a conversion table, all data in the PC/IXF file will be converted from the file code page to the application code page. If the two differ, the FORCEIN option is not specified, and there is no conversion table, the import operation will fail. This applies only to PC/IXF files on DB2 UDB clients on the AIX operating system.

For table objects on an 8 KB page that are close to the limit of 1012 columns, import of PC/IXF data files may cause DB2 to return an error, because the maximum size of an SQL statement was exceeded. This situation can occur only if the columns are of type CHAR, VARCHAR, or CLOB. The restriction does not apply to import of DEL or ASC files. If PC/IXF files are being used to create a new table, an alternative is use **db2look** to dump the DDL statement that created the table, and then to issue that statement through the CLP.

DB2 Connect can be used to import data to DRDA servers such as DB2 for OS/390, DB2 for VM and VSE, and DB2 for OS/400. Only PC/IXF import (INSERT option) is supported. The RESTARTCOUNT parameter, but not the COMMITCOUNT parameter, is also supported.

When using the CREATE option with typed tables, create every sub-table defined in the PC/IXF file; sub-table definitions cannot be altered. When using options other than CREATE with typed tables, the traversal order list enables one to specify the traverse order; therefore, the traversal order list must match the one used during the export operation. For the PC/IXF file format, one need only specify the target sub-table name, and use the traverse order stored in the file.

The import utility can be used to recover a table previously exported to a PC/IXF file. The table returns to the state it was in when exported.

Data cannot be imported to a system table, a declared temporary table, or a summary table.

Views cannot be created through the import utility.

On the Windows operating system:

- Importing logically split PC/IXF files is not supported.
- Importing bad format PC/IXF or WSF files is not supported.

#### **DB2 Data Links Manager considerations:**

Before running the DB2 import utility, do the following:

1. Copy the files that will be referenced to the appropriate Data Links servers. The **dlfm\_import** utility can be used to extract files from an archive that is generated by the **dlfm\_export** utility.
2. Register the required prefix names to the DB2 Data Links Managers. There may be other administrative tasks, such as registering the database, if required.
3. Update the Data Links server information in the URLs (of the DATALINK columns) from the exported data for the SQL table, if required. (If the original configuration's Data Links servers are the same at the target location, the Data Links server names need not be updated.)
4. Define the Data Links servers at the target configuration in the DB2 Data Links Manager configuration file.

When the import utility runs against the target database, files referred to by DATALINK column data are linked on the appropriate Data Links servers.

During the insert operation, DATALINK column processing links the files in the appropriate Data Links servers according to the column specifications at the target database.

#### **Related concepts:**

- "Import Overview" on page 25
- "Privileges, authorities, and authorization required to use import" on page 26

#### **Related tasks:**

- "Using import" on page 27

#### **Related reference:**

- "db2Import - Import" on page 48
- "db2look - DB2 Statistics and DDL Extraction Tool Command" in the *Command Reference*
- "Import Sessions - CLP Examples" on page 68

## IMPORT

- “LOAD” on page 100
- “File type modifiers for import” on page 59
- “Delimiter restrictions for moving data” on page 217

---

### db2Import - Import

Inserts data from an external file with a supported file format into a table, hierarchy, or view. A faster alternative is Load however, the load utility does not support loading data at the hierarchy level.

#### Authorization:

- IMPORT using the INSERT option requires one of the following:
  - *sysadm*
  - *dbadm*
  - CONTROL privilege on each participating table or view
  - INSERT and SELECT privilege on each participating table or view
- IMPORT to an existing table using the INSERT\_UPDATE option, requires one of the following:
  - *sysadm*
  - *dbadm*
  - CONTROL privilege on the table or view
  - INSERT, SELECT, UPDATE and DELETE privilege on each participating table or view
- IMPORT to an existing table using the REPLACE or REPLACE\_CREATE option, requires one of the following:
  - *sysadm*
  - *dbadm*
  - CONTROL privilege on the table or view
  - INSERT, SELECT, and DELETE privilege on the table or view
- IMPORT to a new table using the CREATE or REPLACE\_CREATE option, requires one of the following:
  - *sysadm*
  - *dbadm*
  - CREATETAB authority on the database and USE privilege on the table space, as well as one of:
    - IMPLICIT\_SCHEMA authority on the database, if the implicit or explicit schema name of the table does not exist
    - CREATIN privilege on the schema, if the schema name of the table refers to an existing schema
- IMPORT to a table or a hierarchy that does not exist using the CREATE, or the REPLACE\_CREATE option, requires one of the following:
  - *sysadm*
  - *dbadm*
  - CREATETAB authority on the database, and one of:
    - IMPLICIT\_SCHEMA authority on the database, if the schema name of the table does not exist
    - CREATEIN privilege on the schema, if the schema of the table exists

- CONTROL privilege on every sub-table in the hierarchy, if the REPLACE\_CREATE option on the entire hierarchy is used
- IMPORT to an existing hierarchy using the REPLACE option requires one of the following:
  - *sysadm*
  - *dbadm*
  - CONTROL privilege on every sub-table in the hierarchy

**Required connection:**

Database. If implicit connect is enabled, a connection to the default database is established.

**API include file:**

*db2ApiDf.h*

**C API syntax:**

```

4      /* db2Import - API */
4      SQL_API_RC SQL_API_FN
4      db2Import (
4          db2Uint32 versionNumber,
4          void * pParmStruct,
4          struct sqlca * pSqlca);
4
4      /* db2Import parameter structure */
4      typedef SQL_STRUCTURE db2ImportStruct
4      {
4          char                               *piDataFileName;
4          struct sqlu_media_list             *piLobPathList;
4          struct sqlcol                      *piDataDescriptor;
4          struct sqlchar                    *piActionString;
4          char                               *piFileType;
4          struct sqlchar                    *piFileTypeMod;
4          char                               *piMsgFileName;
4          db2int16                          iCallerAction;
4          struct db2ImportIn                *piImportInfoIn;
4          struct db2ImportOut              *poImportInfoOut;
4          db2int32                          *piNullIndicators;
4      } db2ImportStruct;
4
4      /* Import input structure */
4      typedef SQL_STRUCTURE db2ImportIn
4      {
4          db2Uint64                          iRowcount;
4          db2Uint64                          iRestartcount;
4          db2Uint64                          iSkipcount;
4          db2int32                          *piCommitcount;
4          db2Uint32                          iWarningcount;
4          db2Uint16                          iNoTimeout;
4          db2Uint16                          iAccessLevel;
4      } db2ImportIn;
4
4      /* Import output structure */
4      typedef SQL_STRUCTURE db2ImportOut
4      {
4          db2Uint64                          oRowsRead;
4          db2Uint64                          oRowsSkipped;
4          db2Uint64                          oRowsInserted;

```

## db2Import - Import

```
4         db2UInt64           oRowsUpdated;
4         db2UInt64           oRowsRejected;
4         db2UInt64           oRowsCommitted;
4     } db2ImportOut;

Generic API syntax:

4     /* db2gImport - Generic API */
4     SQL_API_RC SQL_API_FN
4     db2gImport (
4         db2UInt32 versionNumber,
4         void * pParmStruct,
4         struct sqlca * pSqlca);
4
4     /* db2gImport parameter structure */
4     typedef SQL_STRUCTURE db2gImportStruct
4     {
4         char                 *piDataFileName;
4         struct sqlu_media_list *piLobPathList;
4         struct sqlcol         *piDataDescriptor;
4         struct sqlchar        *piActionString;
4         char                 *piFileType;
4         struct sqlchar        *piFileTypeMod;
4         char                 *piMsgFileName;
4         db2int16              iCallerAction;
4         struct db2gImportIn   *piImportInfoIn;
4         struct db2gImportOut  *poImportInfoOut;
4         db2int32              *piNullIndicators;
4         db2UInt16             iDataFileNameLen;
4         db2UInt16             iFileTypeLen;
4         db2UInt16             iMsgFileNameLen;
4     } db2gImportStruct;
4
4     /* Generic Import input structure */
4     typedef SQL_STRUCTURE db2gImportIn
4     {
4         db2UInt64             iRowCount;
4         db2UInt64             iRestartcount;
4         db2UInt64             iSkipcount;
4         db2int32              *piCommitcount;
4         db2UInt32             iWarningcount;
4         db2UInt16             iNoTimeout;
4         db2UInt16             iAccessLevel;
4     } db2gImportIn;
4
4     /* Generic Import output structure */
4     typedef SQL_STRUCTURE db2gImportOut
4     {
4         db2UInt64             oRowsRead;
4         db2UInt64             oRowsSkipped;
4         db2UInt64             oRowsInserted;
4         db2UInt64             oRowsUpdated;
4         db2UInt64             oRowsRejected;
4         db2UInt64             oRowsCommitted;
4     } db2gImportOut;
```

### API parameters:

#### versionNumber

Input. Specifies the version and release level of the structure passed in as the second parameter *pParmStruct*.

#### pParmStruct

Input/Output. A pointer to the *db2ImportStruct* structure.

#### pSqlca

Output. A pointer to the *sqlca* structure.

4 **piDataFileName**  
 4 Input. A string containing the path and the name of the external input file  
 4 from which the data is to be imported.

4 **piLobPathList**  
 4 Input. An *sqlu\_media\_list* using *media\_type* SQLU\_LOCAL\_MEDIA, and the  
 4 *sqlu\_media\_entry* structure listing paths on the client where the LOB files  
 4 can be found.

4 **piDataDescriptor**  
 4 Input. Pointer to an *sqldcol* structure containing information about the  
 4 columns being selected for import from the external file. The value of the  
 4 *dcolmeth* field determines how the remainder of the information provided  
 4 in this parameter is interpreted by the import utility. Valid values for this  
 4 parameter are:

4 **SQL\_METH\_N**  
 4 Names. Selection of columns from the external input file is by  
 4 column name.

4 **SQL\_METH\_P**  
 4 Positions. Selection of columns from the external input file is by  
 4 column position.

4 **SQL\_METH\_L**  
 4 Locations. Selection of columns from the external input file is by  
 4 column location. The database manager rejects an import call with  
 4 a location pair that is invalid because of any one of the following  
 4 conditions:

- 4 • Either the beginning or the ending location is not in the range
- 4 from 1 to the largest signed 2-byte integer.
- 4 • The ending location is smaller than the beginning location.
- 4 • The input column width defined by the location pair is not
- 4 compatible with the type and the length of the target column.

4 A location pair with both locations equal to zero indicates that a  
 4 nullable column is to be filled with NULLs.

4 **SQL\_METH\_D**  
 4 Default. If *piDataDescriptor* is NULL, or is set to SQL\_METH\_D, default  
 4 selection of columns from the external input file is done. In this  
 4 case, the number of columns and the column specification array  
 4 are both ignored. For DEL, IXF, or WSF files, the first *n* columns of  
 4 data in the external input file are taken in their natural order,  
 4 where *n* is the number of database columns into which the data is  
 4 to be imported.

4 **piActionString**  
 4 Input. Pointer to an *sqlchar* structure containing a 2-byte long field,  
 4 followed by an array of characters identifying the columns into which data  
 4 is to be imported.

4 The character array is of the form:

```
4 {INSERT | INSERT_UPDATE | REPLACE | CREATE | REPLACE_CREATE}
4 INTO {tname[(tcolumn-list)] |
4 [{ALL TABLES | (tname[(tcolumn-list)] [, tname[(tcolumn-list)]])]}]
4 [IN] HIERARCHY {STARTING tname | (tname [, tname])}
4 [UNDER sub-table-name | AS ROOT TABLE]}
4 [DATA LINK SPECIFICATION data link-spec]
```

4           **INSERT**  
4           Adds the imported data to the table without changing the existing  
4           table data.

4           **INSERT\_UPDATE**  
4           Adds the imported rows if their primary key values are not in the  
4           table, and uses them for update if their primary key values are  
4           found. This option is only valid if the target table has a primary  
4           key, and the specified (or implied) list of target columns being  
4           imported includes all columns for the primary key. This option  
4           cannot be applied to views.

4           **REPLACE**  
4           Deletes all existing data from the table by truncating the table  
4           object, and inserts the imported data. The table definition and the  
4           index definitions are not changed. (Indexes are deleted and  
4           replaced if `indexixf` is in *FileTypeMod*, and *FileType* is `SQL_IXF`.) If  
4           the table is not already defined, an error is returned.

4           **Attention:** If an error occurs after the existing data is deleted, that  
4           data is lost.

4           **CREATE**  
4           Creates the table definition and the row contents using the  
4           information in the specified PC/IXF file, if the specified table is not  
4           defined. If the file was previously exported by DB2, indexes are  
4           also created. If the specified table is already defined, an error is  
4           returned. This option is valid for the PC/IXF file format only.

4           **REPLACE\_CREATE**  
4           Replaces the table contents using the PC/IXF row information in  
4           the PC/IXF file, if the specified table is defined. If the table is not  
4           already defined, the table definition and row contents are created  
4           using the information in the specified PC/IXF file. If the PC/IXF  
4           file was previously exported by DB2, indexes are also created. This  
4           option is valid for the PC/IXF file format only.

4           **Attention:** If an error occurs after the existing data is deleted, that  
4           data is lost.

4           *tname*   The name of the table, typed table, view, or object view into which  
4           the data is to be inserted. An alias for `REPLACE`,  
4           `INSERT_UPDATE`, or `INSERT` can be specified, except in the case  
4           of a down-level server, when a qualified or unqualified name  
4           should be specified. If it is a view, it cannot be a read-only view.

4           *tcolumn-list*  
4           A list of table or view column names into which the data is to be  
4           inserted. The column names must be separated by commas. If  
4           column names are not specified, column names as defined in the  
4           `CREATE TABLE` or the `ALTER TABLE` statement are used. If no  
4           column list is specified for typed tables, data is inserted into all  
4           columns within each sub-table.

4           *sub-table-name*  
4           Specifies a parent table when creating one or more sub-tables  
4           under the `CREATE` option.

**ALL TABLES**

An implicit keyword for hierarchy only. When importing a hierarchy, the default is to import all tables specified in the *traversal-order-list*.

**HIERARCHY**

Specifies that hierarchical data is to be imported.

**STARTING**

Keyword for hierarchy only. Specifies that the default order, starting from a given sub-table name, is to be used.

**UNDER**

Keyword for hierarchy and CREATE only. Specifies that the new hierarchy, sub-hierarchy, or sub-table is to be created under a given sub-table.

**AS ROOT TABLE**

Keyword for hierarchy and CREATE only. Specifies that the new hierarchy, sub-hierarchy, or sub-table is to be created as a stand-alone hierarchy.

**DATALINK SPECIFICATION** *datalink-spec*

Specifies parameters pertaining to DB2 Data Links Manager. These parameters can be specified using the same syntax as in the IMPORT command.

The *tname* and the *tcolumn-list* parameters correspond to the *tablename* and the *colname* lists of SQL INSERT statements, and have the same restrictions.

The columns in *tcolumn-list* and the external columns (either specified or implied) are matched according to their position in the list or the structure (data from the first column specified in the *sqldcol* structure is inserted into the table or view field corresponding to the first element of the *tcolumn-list*).

If unequal numbers of columns are specified, the number of columns actually processed is the lesser of the two numbers. This could result in an error (because there are no values to place in some non-nullable table fields) or an informational message (because some external file columns are ignored).

**piFileType**

Input. A string that indicates the format of the data within the external file. Supported external file formats are:

**SQL\_ASC**

Non-delimited ASCII.

**SQL\_DEL**

Delimited ASCII, for exchange with dBase, BASIC, and the IBM Personal Decision Series programs, and many other database managers and file managers.

**SQL\_IXF**

PC version of the Integrated Exchange Format, the preferred method for exporting data from a table so that it can be imported later into the same table or into another database manager table.

**SQL\_WSF**

Worksheet formats for exchange with Lotus Symphony and 1-2-3 programs.

## db2Import - Import

4           **piFileTypeMod**  
4           Input. A pointer to a structure containing a 2-byte long field, followed by  
4           an array of characters that specify one or more processing options. If this  
4           pointer is NULL, or the structure pointed to has zero characters, this action  
4           is interpreted as selection of a default specification.  
4  
4           Not all options can be used with all of the supported file types. See File  
4           type modifiers for import.

4           **piMsgFileName**  
4           Input. A string containing the destination for error, warning, and  
4           informational messages returned by the utility. It can be the path and the  
4           name of an operating system file or a standard device. If the file already  
4           exists, it is appended to. If it does not exist, a file is created.

4           **iCallerAction**  
4           Input. An action requested by the caller. Valid values are:  
4  
4           **SQLU\_INITIAL**  
4           Initial call. This value must be used on the first call to the API.  
4  
4           If the initial call or any subsequent call returns and requires the calling  
4           application to perform some action prior to completing the requested  
4           import operation, the caller action must be set to one of the following:  
4  
4           **SQLU\_CONTINUE**  
4           Continue processing. This value can only be used on subsequent  
4           calls to the API, after the initial call has returned with the utility  
4           requesting user input (for example, to respond to an end of tape  
4           condition). It specifies that the user action requested by the utility  
4           has completed, and the utility can continue processing the initial  
4           request.  
4  
4           **SQLU\_TERMINATE**  
4           Terminate processing. This value can only be used on subsequent  
4           calls to the API, after the initial call has returned with the utility  
4           requesting user input (for example, to respond to an end of tape  
4           condition). It specifies that the user action requested by the utility  
4           was not performed, and the utility is to terminate processing the  
4           initial request.

4           **piImportInfoIn**  
4           Input. Pointer to the *db2ImportIn* structure.

4           **poImportInfoOut**  
4           Output. Pointer to the *db2ImportOut* structure.

4           **piNullIndicators**  
4           Input. For ASC files only. An array of integers that indicate whether or not  
4           the column data is nullable. The number of elements in this array must  
4           match the number of columns in the input file; there is a one-to-one  
4           ordered correspondence between the elements of this array and the  
4           columns being imported from the data file. Therefore, the number of  
4           elements must equal the *dcolnum* field of the *piDataDescriptor* parameter.  
4           Each element of the array contains a number identifying a column in the  
4           data file that is to be used as a null indicator field, or a zero indicating that  
4           the table column is not nullable. If the element is not zero, the identified  
4           column in the data file must contain a Y or an N. A Y indicates that the  
4           table column data is NULL, and N indicates that the table column data is  
4           not NULL.

4 **iRowcount**  
 4 Input. The number of physical records to be loaded. Allows a user to load  
 4 only the first *iRowcount* rows in a file. If *iRowcount* is 0, import will attempt  
 4 to process all the rows from the file.

4 **iSkipcount**  
 4 Input. The number of records to skip before starting to insert or update  
 4 records. Functionally equivalent to *iRestartcount*.

4 **piCommitcount**  
 4 Input. The number of records to import before committing them to the  
 4 database. A commit is performed whenever *piCommitcount* records are  
 4 imported. A NULL value specifies the default commit count value, which  
 4 is zero for offline import and AUTOMATIC for online import.  
 4 Commitcount AUTOMATIC is specified by passing in the value  
 4 DB2IMPORT\_COMMIT\_AUTO.

4 **iWarningcount**  
 4 Input. Stops the import operation after *iWarningcount* warnings. Set this  
 4 parameter if no warnings are expected, but verification that the correct file  
 4 and table are being used is desired. If the import file or the target table is  
 4 specified incorrectly, the import utility will generate a warning for each  
 4 row that it attempts to import, which will cause the import to fail. If  
 4 *iWarningcount* is 0, or this option is not specified, the import operation will  
 4 continue regardless of the number of warnings issued.

4 **iNoTimeout**  
 4 Input. Specifies that the import utility will not time out while waiting for  
 4 locks. This option supersedes the *locktimeout* database configuration  
 4 parameter. Other applications are not affected. Valid values are:

4 **DB2IMPORT\_LOCKTIMEOUT**  
 4 Indicates that the value of the *locktimeout* configuration parameter  
 4 is respected.

4 **DB2IMPORT\_NO\_LOCKTIMEOUT**  
 4 Indicates there is no timeout.

4 **iAccessLevel**  
 4 Input. Specifies the access level. Valid values are:

4 **SQLU\_ALLOW\_NO\_ACCESS**  
 4 Specifies that the import utility locks the table exclusively.

4 **SQLU\_ALLOW\_WRITE\_ACCESS**  
 4 Specifies that the data in the table should still be accessible to  
 4 readers and writers while the import is in progress.

4 **oRowsRead**  
 4 Output. Number of records read from the file during import.

4 **oRowsSkipped**  
 4 Output. Number of records skipped before inserting or updating begins.

4 **oRowsInserted**  
 4 Output. Number of rows inserted into the target table.

4 **oRowsUpdated**  
 4 Output. Number of rows in the target table updated with information from  
 4 the imported records (records whose primary key value already exists in  
 4 the table).

## db2Import - Import

- 4           **oRowsRejected**
- 4                 Output. Number of records that could not be imported.
- 4           **oRowsCommitted**
- 4                 Output. Number of records imported successfully and committed to the
- 4                 database.

### Usage notes:

Be sure to complete all table operations and release all locks before starting an import operation. This can be done by issuing a COMMIT after closing all cursors opened WITH HOLD, or by issuing a ROLLBACK.

The import utility adds rows to the target table using the SQL INSERT statement. The utility issues one INSERT statement for each row of data in the input file. If an INSERT statement fails, one of two actions result:

- If it is likely that subsequent INSERT statements can be successful, a warning message is written to the message file, and processing continues.
- If it is likely that subsequent INSERT statements will fail, and there is potential for database damage, an error message is written to the message file, and processing halts.

The utility performs an automatic COMMIT after the old rows are deleted during a REPLACE or a REPLACE\_CREATE operation. Therefore, if the system fails, or the application interrupts the database manager after the table object is truncated, all of the old data is lost. Ensure that the old data is no longer needed before using these options.

If the log becomes full during a CREATE, REPLACE, or REPLACE\_CREATE operation, the utility performs an automatic COMMIT on inserted records. If the system fails, or the application interrupts the database manager after an automatic COMMIT, a table with partial data remains in the database. Use the REPLACE or the REPLACE\_CREATE option to rerun the whole import operation, or use INSERT with the *iRestartcount* parameter set to the number of rows successfully imported.

By default, automatic COMMITs are not performed for the INSERT or the INSERT\_UPDATE option. They are, however, performed if the *\*piCommitcount* parameter is not zero. A full log results in a ROLLBACK.

Whenever the import utility performs a COMMIT, two messages are written to the message file: one indicates the number of records to be committed, and the other is written after a successful COMMIT. When restarting the import operation after a failure, specify the number of records to skip, as determined from the last successful COMMIT.

The import utility accepts input data with minor incompatibility problems (for example, character data can be imported using padding or truncation, and numeric data can be imported with a different numeric data type), but data with major incompatibility problems is not accepted.

One cannot REPLACE or REPLACE\_CREATE an object table if it has any dependents other than itself, or an object view if its base table has any dependents (including itself). To replace such a table or a view, do the following:

1. Drop all foreign keys in which the table is a parent.

2. Run the import utility.
3. Alter the table to recreate the foreign keys.

If an error occurs while recreating the foreign keys, modify the data to maintain referential integrity.

Referential constraints and foreign key definitions are not preserved when creating tables from PC/IXF files. (Primary key definitions *are* preserved if the data was previously exported using SELECT \*.)

Importing to a remote database requires enough disk space on the server for a copy of the input data file, the output message file, and potential growth in the size of the database.

If an import operation is run against a remote database, and the output message file is very long (more than 60 KB), the message file returned to the user on the client may be missing messages from the middle of the import operation. The first 30 KB of message information and the last 30 KB of message information are always retained.

Importing PC/IXF files to a remote database is much faster if the PC/IXF file is on a hard drive rather than on diskettes. Non-default values for *piDataDescriptor*, or specifying an explicit list of table columns in *piActionString*, makes importing to a remote database slower.

The database table or hierarchy must exist before data in the ASC, DEL, or WSF file formats can be imported; however, if the table does not already exist, IMPORT CREATE or IMPORT REPLACE\_CREATE creates the table when it imports data from a PC/IXF file. For typed tables, IMPORT CREATE can create the type hierarchy and the table hierarchy as well.

PC/IXF import should be used to move data (including hierarchical data) between databases. If character data containing row separators is exported to a delimited ASCII (DEL) file and processed by a text transfer program, fields containing the row separators will shrink or expand.

The data in ASC and DEL files is assumed to be in the code page of the client application performing the import. PC/IXF files, which allow for different code pages, are recommended when importing data in different code pages. If the PC/IXF file and the import utility are in the same code page, processing occurs as for a regular application. If the two differ, and the FORCEIN option is specified, the import utility assumes that data in the PC/IXF file has the same code page as the application performing the import. This occurs even if there is a conversion table for the two code pages. If the two differ, the FORCEIN option is not specified, and there is a conversion table, all data in the PC/IXF file will be converted from the file code page to the application code page. If the two differ, the FORCEIN option is not specified, and there is no conversion table, the import operation will fail. This applies only to PC/IXF files on DB2 for AIX clients.

For table objects on an 8KB page that are close to the limit of 1012 columns, import of PC/IXF data files may cause DB2 to return an error, because the maximum size of an SQL statement was exceeded. This situation can occur only if the columns are of type CHAR, VARCHAR, or CLOB. The restriction does not apply to import of DEL or ASC files.

## db2Import - Import

DB2 Connect can be used to import data to DRDA servers such as DB2 for OS/390, DB2 for VM and VSE, and DB2 for OS/400. Only PC/IXF import (INSERT option) is supported. The restartcnt parameter, but not the commitcnt parameter, is also supported.

When using the CREATE option with typed tables, create every sub-table defined in the PC/IXF file; sub-table definitions cannot be altered. When using options other than CREATE with typed tables, the traversal order list enables one to specify the traverse order; therefore, the traversal order list must match the one used during the export operation. For the PC/IXF file format, one need only specify the target sub-table name, and use the traverse order stored in the file.

The import utility can be used to recover a table previously exported to a PC/IXF file. The table returns to the state it was in when exported.

Data cannot be imported to a system table, a declared temporary table, or a summary table.

Views cannot be created through the import utility.

On the Windows NT operating system:

- Importing logically split PC/IXF files is not supported.
- Importing bad format PC/IXF or WSF files is not supported.

### DB2 Data Links Manager Considerations

Before running the DB2 import utility, do the following:

1. Copy the files that will be referenced to the appropriate Data Links servers. The **dlfm\_import** utility can be used to extract files from an archive that is generated by the **dlfm\_export** utility.
2. Register the required prefix names to the DB2 Data Links Managers. There may be other administrative tasks, such as registering the database, if required.
3. Update the Data Links server information in the URLs (of the DATALINK columns) from the exported data for the SQL table, if required. (If the original configuration's Data Links servers are the same at the target location, the Data Links server names need not be updated.)
4. Define the Data Links servers at the target configuration in the DB2 Data Links Manager configuration file.

When the import utility runs against the target database, files referred to by DATALINK column data are linked on the appropriate Data Links servers.

During the insert operation, DATALINK column processing links the files in the appropriate Data Links servers according to the column specifications at the target database.

#### Related reference:

- "SQLCA" in the *Administrative API Reference*
- "SQLDCOL" in the *Administrative API Reference*
- "SQLU-MEDIA-LIST" in the *Administrative API Reference*
- "File type modifiers for import" on page 59
- "Delimiter restrictions for moving data" on page 217

**Related samples:**

- “dtformat.sqc -- Load and import data format extensions (C)”
- “tbmove.sqc -- How to move table data (C)”
- “exp samp.sqb -- Export and import tables with table data to a DRDA database (IBM COBOL)”
- “impexp.sqb -- Export and import tables with table data (IBM COBOL)”
- “tbmove.sqC -- How to move table data (C++)”

---

## File type modifiers for import

Table 4. Valid file type modifiers for import: All file formats

Modifier	Description
compound= <i>x</i>	<p><i>x</i> is a number between 1 and 100 inclusive. Uses nonatomic compound SQL to insert the data, and <i>x</i> statements will be attempted each time.</p> <p>If this modifier is specified, and the transaction log is not sufficiently large, the import operation will fail. The transaction log must be large enough to accommodate either the number of rows specified by COMMITCOUNT, or the number of rows in the data file if COMMITCOUNT is not specified. It is therefore recommended that the COMMITCOUNT option be specified to avoid transaction log overflow.</p> <p>This modifier is incompatible with INSERT_UPDATE mode, hierarchical tables, and the following modifiers: usedefaults, identitymissing, identityignore, generatedmissing, and generatedignore.</p>
generatedignore	This modifier informs the import utility that data for all generated columns is present in the data file but should be ignored. This results in all values for the generated columns being generated by the utility. This modifier cannot be used with the generatedmissing modifier.
generatedmissing	If this modifier is specified, the utility assumes that the input data file contains no data for the generated columns (not even NULLs), and will therefore generate a value for each row. This modifier cannot be used with the generatedignore modifier.
identityignore	This modifier informs the import utility that data for the identity column is present in the data file but should be ignored. This results in all identity values being generated by the utility. The behavior will be the same for both GENERATED ALWAYS and GENERATED BY DEFAULT identity columns. This means that for GENERATED ALWAYS columns, no rows will be rejected. This modifier cannot be used with the identitymissing modifier.
identitymissing	If this modifier is specified, the utility assumes that the input data file contains no data for the identity column (not even NULLs), and will therefore generate a value for each row. The behavior will be the same for both GENERATED ALWAYS and GENERATED BY DEFAULT identity columns. This modifier cannot be used with the identityignore modifier.

## db2Import - Import

Table 4. Valid file type modifiers for import: All file formats (continued)

Modifier	Description
lobsinfile	<p><i>lob-path</i> specifies the path to the files containing LOB data.</p> <p>Each path contains at least one file that contains at least one LOB pointed to by a Lob Location Specifier (LLS) in the data file. The LLS is a string representation of the location of a LOB in a file stored in the LOB file path. The format of an LLS is <i>filename.ext.nnn.mmm/</i>, where <i>filename.ext</i> is the name of the file that contains the LOB, <i>nnn</i> is the offset in bytes of the LOB within the file, and <i>mmm</i> is the length of the LOB in bytes. For example, if the string <i>db2exp.001.123.456/</i> is stored in the data file, the LOB is located at offset 123 in the file <i>db2exp.001</i>, and is 456 bytes long.</p> <p>The LOBS FROM clause specifies where the LOB files are located when the "lobsinfile" modifier is used. The LOBS FROM clause means nothing outside the context of the <i>lobsinfile</i> modifier. The LOBS FROM clause conveys to the IMPORT utility the list of paths to search for the LOB files while importing the data.</p> <p>To indicate a null LOB, enter the size as -1. If the size is specified as 0, it is treated as a 0 length LOB. For null LOBS with length of -1, the offset and the file name are ignored. For example, the LLS of a null LOB might be <i>db2exp.001.7.-1/</i>.</p>
no_type_id	Valid only when importing into a single sub-table. Typical usage is to export data from a regular table, and then to invoke an import operation (using this modifier) to convert the data into a single sub-table.
nodefaults	<p>If a source column for a target table column is not explicitly specified, and the table column is not nullable, default values are not loaded. Without this option, if a source column for one of the target table columns is not explicitly specified, one of the following occurs:</p> <ul style="list-style-type: none"> <li>• If a default value can be specified for a column, the default value is loaded</li> <li>• If the column is nullable, and a default value cannot be specified for that column, a NULL is loaded</li> <li>• If the column is not nullable, and a default value cannot be specified, an error is returned, and the utility stops processing.</li> </ul>
4 norowwarnings	Suppresses all warnings about rejected rows.
usedefaults	<p>If a source column for a target table column has been specified, but it contains no data for one or more row instances, default values are loaded. Examples of missing data are:</p> <ul style="list-style-type: none"> <li>• For DEL files: ",," is specified for the column</li> <li>• For ASC files: The NULL indicator is set to yes for the column</li> <li>• For DEL/ASC/WSF files: A row that does not have enough columns, or is not long enough for the original specification.</li> </ul> <p>Without this option, if a source column contains no data for a row instance, one of the following occurs:</p> <ul style="list-style-type: none"> <li>• If the column is nullable, a NULL is loaded</li> <li>• If the column is not nullable, the utility rejects the row.</li> </ul>

Table 5. Valid file type modifiers for import: ASCII file formats (ASC/DEL)

Modifier	Description
codepage= <i>x</i>	<p><i>x</i> is an ASCII character string. The value is interpreted as the code page of the data in the output data set. Converts character data to this code page from the application code page during the import operation.</p> <p>The following rules apply:</p> <ul style="list-style-type: none"> <li>• For pure DBCS (graphic) mixed DBCS, and EUC, delimiters are restricted to the range of x00 to x3F, inclusive.</li> <li>• nullindchar must specify symbols included in the standard ASCII set between code points x20 and x7F, inclusive. This refers to ASCII symbols and code points.</li> </ul> <p><b>Notes:</b></p> <ol style="list-style-type: none"> <li>1. The codepage modifier cannot be used with the lobsinfile modifier.</li> <li>2. If data expansion occurs when the code page is converted from the application code page to the database code page, the data may be truncated and loss of data can occur.</li> </ol>
dateformat=" <i>x</i> "	<p><i>x</i> is the format of the date in the source file.<sup>2</sup> Valid date elements are:</p> <p>YYYY - Year (four digits ranging from 0000 - 9999)  M - Month (one or two digits ranging from 1 - 12)  MM - Month (two digits ranging from 1 - 12;  mutually exclusive with M)  D - Day (one or two digits ranging from 1 - 31)  DD - Day (two digits ranging from 1 - 31;  mutually exclusive with D)  DDD - Day of the year (three digits ranging  from 001 - 366; mutually exclusive  with other day or month elements)</p> <p>A default value of 1 is assigned for each element that is not specified. Some examples of date formats are:</p> <p>"D-M-YYYY"  "MM.DD.YYYY"  "YYYYDDD"</p>
implieddecimal	<p>The location of an implied decimal point is determined by the column definition; it is no longer assumed to be at the end of the value. For example, the value 12345 is loaded into a DECIMAL(8,2) column as 123.45, <i>not</i> 12345.00.</p>
noeofchar	<p>The optional end-of-file character x'1A' is not recognized as the end of file. Processing continues as if it were a normal character.</p>

## db2Import - Import

Table 5. Valid file type modifiers for import: ASCII file formats (ASC/DEL) (continued)

Modifier	Description
timeformat="x"	<p>x is the format of the time in the source file.<sup>2</sup> Valid time elements are:</p> <ul style="list-style-type: none"> <li>H - Hour (one or two digits ranging from 0 - 12 for a 12 hour system, and 0 - 24 for a 24 hour system)</li> <li>HH - Hour (two digits ranging from 0 - 12 for a 12 hour system, and 0 - 24 for a 24 hour system; mutually exclusive with H)</li> <li>M - Minute (one or two digits ranging from 0 - 59)</li> <li>MM - Minute (two digits ranging from 0 - 59; mutually exclusive with M)</li> <li>S - Second (one or two digits ranging from 0 - 59)</li> <li>SS - Second (two digits ranging from 0 - 59; mutually exclusive with S)</li> <li>SSSSS - Second of the day after midnight (5 digits ranging from 00000 - 86399; mutually exclusive with other time elements)</li> <li>TT - Meridian indicator (AM or PM)</li> </ul> <p>A default value of 0 is assigned for each element that is not specified. Some examples of time formats are:</p> <pre> "HH:MM:SS" "HH.MM TT" "SSSSS" </pre>

Table 5. Valid file type modifiers for import: ASCII file formats (ASC/DEL) (continued)

Modifier	Description
timestampformat="x"	<p data-bbox="558 254 1448 310">x is the format of the time stamp in the source file.<sup>2</sup> Valid time stamp elements are:</p> <p data-bbox="558 321 1448 352">YYYY - Year (four digits ranging from 0000 - 9999)</p> <p data-bbox="558 352 1448 384">M - Month (one or two digits ranging from 1 - 12)</p> <p data-bbox="558 384 1448 436">MM - Month (two digits ranging from 01 - 12; mutually exclusive with M and MMM)</p> <p data-bbox="558 436 1448 489">MMM - Month (three-letter case-insensitive abbreviation for the month name; mutually exclusive with M and MM)</p> <p data-bbox="558 489 1448 520">D - Day (one or two digits ranging from 1 - 31)</p> <p data-bbox="558 520 1448 552">DD - Day (two digits ranging from 1 - 31; mutually exclusive with D)</p> <p data-bbox="558 552 1448 604">DDD - Day of the year (three digits ranging from 001 - 366; mutually exclusive with other day or month elements)</p> <p data-bbox="558 604 1448 657">H - Hour (one or two digits ranging from 0 - 12 for a 12 hour system, and 0 - 24 for a 24 hour system)</p> <p data-bbox="558 657 1448 720">HH - Hour (two digits ranging from 0 - 12 for a 12 hour system, and 0 - 24 for a 24 hour system; mutually exclusive with H)</p> <p data-bbox="558 720 1448 751">M - Minute (one or two digits ranging from 0 - 59)</p> <p data-bbox="558 751 1448 804">MM - Minute (two digits ranging from 0 - 59; mutually exclusive with M, minute)</p> <p data-bbox="558 804 1448 835">S - Second (one or two digits ranging from 0 - 59)</p> <p data-bbox="558 835 1448 888">SS - Second (two digits ranging from 0 - 59; mutually exclusive with S)</p> <p data-bbox="558 888 1448 961">SSSSS - Second of the day after midnight (5 digits ranging from 00000 - 86399; mutually exclusive with other time elements)</p> <p data-bbox="558 961 1448 1014">UUUUUU - Microsecond (6 digits ranging from 000000 - 999999; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1014 1448 1087">UUUUU - Microsecond (5 digits ranging from 00000 - 99999, maps to range from 000000 - 999990; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1087 1448 1161">UUUU - Microsecond (4 digits ranging from 0000 - 9999, maps to range from 000000 - 999900; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1161 1448 1234">UUU - Microsecond (3 digits ranging from 000 - 999, maps to range from 000000 - 999000; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1234 1448 1308">UU - Microsecond (2 digits ranging from 00 - 99, maps to range from 000000 - 990000; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1308 1448 1381">U - Microsecond (1 digit ranging from 0 - 9, maps to range from 000000 - 900000; mutually exclusive with all other microsecond elements)</p> <p data-bbox="558 1381 1448 1413">TT - Meridian indicator (AM or PM)</p> <p data-bbox="558 1465 1448 1581">A default value of 1 is assigned for unspecified YYYY, M, MM, D, DD, or DDD elements. A default value of 'Jan' is assigned to an unspecified MMM element. A default value of 0 is assigned for all other unspecified elements. Following is an example of a time stamp format: "YYYY/MM/DD HH:MM:SS.UUUUUU"</p> <p data-bbox="558 1644 1448 1696">The valid values for the MMM element include: 'jan', 'feb', 'mar', 'apr', 'may', 'jun', 'jul', 'aug', 'sep', 'oct', 'nov' and 'dec'. These values are case insensitive.</p> <p data-bbox="558 1728 1448 1780">The following example illustrates how to import data containing user defined date and time formats into a table called schedule:</p> <pre data-bbox="558 1791 1448 1869">db2 import from delfile2 of del modified by timestampformat="yyyy.mm.dd hh:mm tt" insert into schedule</pre>

## db2Import - Import

Table 5. Valid file type modifiers for import: ASCII file formats (ASC/DEL) (continued)

Modifier	Description
usegraphiccodepage	<p>If usegraphiccodepage is given, the assumption is made that data being imported into graphic or double-byte character large object (DBCLOB) data fields is in the graphic code page. The rest of the data is assumed to be in the character code page. The graphic code page is associated with the character code page. IMPORT determines the character code page through either the codepage modifier, if it is specified, or through the code page of the application if the codepage modifier is not specified.</p> <p>This modifier should be used in conjunction with the delimited data file generated by drop table recovery only if the table being recovered has graphic data.</p> <p><b>Restrictions</b></p> <p>The usegraphiicodepage modifier MUST NOT be specified with DEL or ASC files created by the EXPORT utility, as these files contain data encoded in only one code page. The usegraphiccodepage modifier is also ignored by the double-byte character large objects (DBCLOBs) in files.</p>

Table 6. Valid file type modifiers for import: ASC (non-delimited ASCII) file format

Modifier	Description
nochecklengths	<p>If nochecklengths is specified, an attempt is made to import each row, even if the source data has a column definition that exceeds the size of the target table column. Such rows can be successfully imported if code page conversion causes the source data to shrink; for example, 4-byte EUC data in the source could shrink to 2-byte DBCS data in the target, and require half the space. This option is particularly useful if it is known that the source data will fit in all cases despite mismatched column definitions.</p>
nullindchar= <i>x</i>	<p><i>x</i> is a single character. Changes the character denoting a null value to <i>x</i>. The default value of <i>x</i> is Y.<sup>3</sup></p> <p>This modifier is case sensitive for EBCDIC data files, except when the character is an English letter. For example, if the null indicator character is specified to be the letter N, then n is also recognized as a null indicator.</p>
reclen= <i>x</i>	<p><i>x</i> is an integer with a maximum value of 32 767. <i>x</i> characters are read for each row, and a new-line character is not used to indicate the end of the row.</p>
striptblanks	<p>Truncates any trailing blank spaces when loading data into a variable-length field. If this option is not specified, blank spaces are kept.</p> <p>In the following example, striptblanks causes the import utility to truncate trailing blank spaces:</p> <pre>db2 import from myfile.asc of asc modified by striptblanks method 1 (1 10, 12 15) messages msgs.txt insert into staff</pre> <p>This option cannot be specified together with striptnulls. These are mutually exclusive options.</p> <p><b>Note:</b> This option replaces the obsolete t option, which is supported for back-level compatibility only.</p>

Table 6. Valid file type modifiers for import: ASC (non-delimited ASCII) file format (continued)

Modifier	Description
striptnulls	<p>Truncates any trailing NULLs (0x00 characters) when loading data into a variable-length field. If this option is not specified, NULLs are kept.</p> <p>This option cannot be specified together with striptblanks. These are mutually exclusive options.</p> <p><b>Note:</b> This option replaces the obsolete padwithzero option, which is supported for back-level compatibility only.</p>

Table 7. Valid file type modifiers for import: DEL (delimited ASCII) file format

Modifier	Description
chardelx	<p><i>x</i> is a single character string delimiter. The default value is a double quotation mark ("). The specified character is used in place of double quotation marks to enclose a character string.<sup>34</sup> If you want to explicitly specify the double quotation mark as the character string delimiter, it should be specified as follows:</p> <pre>modified by chardel'"</pre> <p>The single quotation mark (') can also be specified as a character string delimiter. In the following example, chardel'' causes the import utility to interpret any single quotation mark (') it encounters as a character string delimiter:</p> <pre>db2 "import from myfile.del of del modified by chardel'' method p (1, 4) insert into staff (id, years)"</pre>
coldelx	<p><i>x</i> is a single character column delimiter. The default value is a comma (.). The specified character is used in place of a comma to signal the end of a column.<sup>34</sup></p> <p>In the following example, coldel; causes the import utility to interpret any semicolon (;) it encounters as a column delimiter:</p> <pre>db2 import from myfile.del of del modified by coldel; messages msgs.txt insert into staff</pre>
datesiso	Date format. Causes all date data values to be imported in ISO format.
decplusblank	Plus sign character. Causes positive decimal values to be prefixed with a blank space instead of a plus sign (+). The default action is to prefix positive decimal values with a plus sign.
decptx	<p><i>x</i> is a single character substitute for the period as a decimal point character. The default value is a period (.). The specified character is used in place of a period as a decimal point character.<sup>34</sup></p> <p>In the following example, decpt; causes the import utility to interpret any semicolon (;) it encounters as a decimal point:</p> <pre>db2 "import from myfile.del of del modified by chardel' decpt; messages msgs.txt insert into staff"</pre>

## db2Import - Import

Table 7. Valid file type modifiers for import: DEL (delimited ASCII) file format (continued)

Modifier	Description
delprioritychar	<p>The current default priority for delimiters is: record delimiter, character delimiter, column delimiter. This modifier protects existing applications that depend on the older priority by reverting the delimiter priorities to: character delimiter, record delimiter, column delimiter. Syntax:</p> <pre>db2 import ... modified by delprioritychar ...</pre> <p>For example, given the following DEL data file:</p> <pre>"Smith, Joshua",4000,34.98&lt;row delimiter&gt; "Vincent,&lt;row delimiter&gt;, is a manager", ... ... 4005,44.37&lt;row delimiter&gt;</pre> <p>With the delprioritychar modifier specified, there will be only two rows in this data file. The second &lt;row delimiter&gt; will be interpreted as part of the first data column of the second row, while the first and the third &lt;row delimiter&gt; are interpreted as actual record delimiters. If this modifier is <i>not</i> specified, there will be three rows in this data file, each delimited by a &lt;row delimiter&gt;.</p>
dldelx	<p><i>x</i> is a single character DATALINK delimiter. The default value is a semicolon (;). The specified character is used in place of a semicolon as the inter-field separator for a DATALINK value. It is needed because a DATALINK value may have more than one sub-value. <sup>34</sup></p> <p><b>Note:</b> <i>x</i> must not be the same character specified as the row, column, or character string delimiter.</p>
keepblanks	<p>Preserves the leading and trailing blanks in each field of type CHAR, VARCHAR, LONG VARCHAR, or CLOB. Without this option, all leading and trailing blanks that are not inside character delimiters are removed, and a NULL is inserted into the table for all blank fields.</p>
nochardel	<p>The import utility will assume all bytes found between the column delimiters to be part of the column's data. Character delimiters will be parsed as part of column data. This option should not be specified if the data was exported using DB2 (unless nochardel was specified at export time). It is provided to support vendor data files that do not have character delimiters. Improper usage may result in data loss or corruption.</p> <p>This option cannot be specified with chardelx, delprioritychar or nodoubledel. These are mutually exclusive options.</p>
nodoubledel	<p>Suppresses recognition of double character delimiters.</p>

Table 8. Valid file type modifiers for import: IXF file format

Modifier	Description
forcein	<p>Directs the utility to accept data despite code page mismatches, and to suppress translation between code pages.</p> <p>Fixed length target fields are checked to verify that they are large enough for the data. If nochecklengths is specified, no checking is done, and an attempt is made to import each row.</p>
indexixf	<p>Directs the utility to drop all indexes currently defined on the existing table, and to create new ones from the index definitions in the PC/IXF file. This option can only be used when the contents of a table are being replaced. It cannot be used with a view, or when a <i>insert-column</i> is specified.</p>
indexschema= <i>schema</i>	<p>Uses the specified <i>schema</i> for the index name during index creation. If <i>schema</i> is not specified (but the keyword <i>indexschema</i> is specified), uses the connection user ID. If the keyword is not specified, uses the schema in the IXF file.</p>

Table 8. Valid file type modifiers for import: IXF file format (continued)

Modifier	Description
nochecklengths	If nochecklengths is specified, an attempt is made to import each row, even if the source data has a column definition that exceeds the size of the target table column. Such rows can be successfully imported if code page conversion causes the source data to shrink; for example, 4-byte EUC data in the source could shrink to 2-byte DBCS data in the target, and require half the space. This option is particularly useful if it is known that the source data will fit in all cases despite mismatched column definitions.

**Notes:**

1. The import utility does not issue a warning if an attempt is made to use unsupported file types with the MODIFIED BY option. If this is attempted, the import operation fails, and an error code is returned.
2. Double quotation marks around the date format string are mandatory. Field separators cannot contain any of the following: a-z, A-Z, and 0-9. The field separator should not be the same as the character delimiter or field delimiter in the DEL file format. A field separator is optional if the start and end positions of an element are unambiguous. Ambiguity can exist if (depending on the modifier) elements such as D, H, M, or S are used, because of the variable length of the entries.

For time stamp formats, care must be taken to avoid ambiguity between the month and the minute descriptors, since they both use the letter M. A month field must be adjacent to other date fields. A minute field must be adjacent to other time fields. Following are some ambiguous time stamp formats:

```
"M" (could be a month, or a minute)
"M:M" (Which is which?)
"M:YYYY:M" (Both are interpreted as month.)
"S:M:YYYY" (adjacent to both a time value and a date value)
```

In ambiguous cases, the utility will report an error message, and the operation will fail.

Following are some unambiguous time stamp formats:

```
"M:YYYY" (Month)
"S:M" (Minute)
"M:YYYY:S:M" (Month...Minute)
"M:H:YYYY:M:D" (Minute...Month)
```

Some characters, such as double quotation marks and back slashes, must be preceded by an escape character (for example, \).

3. The character must be specified in the code page of the source data. The character code point (instead of the character symbol), can be specified using the syntax xJJ or 0xJJ, where JJ is the hexadecimal representation of the code point. For example, to specify the # character as a column delimiter, use one of the following:
 

```
... modified by coldel# ...
... modified by coldel0x23 ...
... modified by coldelX23 ...
```
4. Delimiter restrictions for moving data lists restrictions that apply to the characters that can be used as delimiter overrides.

Table 9. IMPORT behavior when using codepage and usegraphiccodepage

codepage=N	usegraphiccodepage	IMPORT behavior
Absent	Absent	All data in the file is assumed to be in the application code page.

## db2Import - Import

Table 9. *IMPORT* behavior when using *codepage* and *usegraphiccodepage* (continued)

<i>codepage=N</i>	<i>usegraphiccodepage</i>	<b>IMPORT</b> behavior
Present	Absent	All data in the file is assumed to be in code page N. <b>Warning:</b> Graphic data will be corrupted when imported into the database if N is a single-byte code page.
Absent	Present	Character data in the file is assumed to be in the application code page. Graphic data is assumed to be in the code page of the application graphic data.  If the application code page is single-byte, then all data is assumed to be in the application code page. <b>Warning:</b> If the application code page is single-byte, graphic data will be corrupted when imported into the database, even if the database contains graphic columns.
Present	Present	Character data is assumed to be in code page N. Graphic data is assumed to be in the graphic code page of N.  If N is a single-byte or double-byte code page, then all data is assumed to be in code page N. <b>Warning:</b> Graphic data will be corrupted when imported into the database if N is a single-byte code page.

**Related reference:**

- “db2Import - Import” on page 48
- “IMPORT” on page 35
- “Delimiter restrictions for moving data” on page 217

---

## Character Set and NLS Considerations

Unequal code page situations, involving expansion or contraction of the character data, can sometimes occur. For example, Japanese or Traditional-Chinese Extended UNIX<sup>®</sup> Code (EUC) and double-byte character sets (DBCS) might encode different lengths for the same character. Normally, comparison of input data length to target column length is performed before reading in any data. If the input length is greater than the target length, NULLs are inserted into that column if it is nullable. Otherwise, the request is rejected. If the *nochecklengths* modifier is specified, no initial comparison is performed, and an attempt is made to import the data. If the data is too long after translation is complete, the row is rejected. Otherwise, the data is imported.

**Related concepts:**

- “Character set and national language support” on page 165

**Related reference:**

- “IMPORT” on page 35

---

## Import Sessions - CLP Examples

### Example 1

The following example shows how to import information from myfile.ixf to the STAFF table:

```
db2 import from myfile.ixf of ixf messages msg.txt insert into staff

SQL3150N The H record in the PC/IXF file has product "DB2 01.00", date
"19970220", and time "140848".

SQL3153N The T record in the PC/IXF file has name "myfile",
qualifier " ", and source " ".

SQL3109N The utility is beginning to load data from file "myfile".

SQL3110N The utility has completed processing. "58" rows were read from the
input file.

SQL3221W ...Begin COMMIT WORK. Input Record Count = "58".

SQL3222W ...COMMIT of any database changes was successful.

SQL3149N "58" rows were processed from the input file. "58" rows were
successfully inserted into the table. "0" rows were rejected.
```

## Example 2

The following example shows how to import the table MOVIE TABLE from the input file delfile1, which has data in the DEL format:

```
db2 import from delfile1 of del
modified by dldel|
insert into movietable (actorname, description, url_making_of,
url_movie) datalink specification (dl_url_default_prefix
"http://narang"), (dl_url_replace_prefix "http://bomdel"
dl_url_suffix ".mpeg")
```

### Notes:

1. The table has four columns:

actorname	VARCHAR(n)
description	VARCHAR(m)
url_making_of	DATALINK (with LINKTYPE URL)
url_movie	DATALINK (with LINKTYPE URL)

2. The DATALINK data in the input file has the vertical bar (|) character as the sub-field delimiter.
3. If any column value for url\_making\_of does not have the prefix character sequence, "http://narang" is used.
4. Each non-NULL column value for url\_movie will get "http://bomdel" as its prefix. Existing values are replaced.
5. Each non-NULL column value for url\_movie will get ".mpeg" appended to the path. For example, if a column value of url\_movie is "http://server1/x/y/z", it will be stored as "http://bomdel/x/y/z.mpeg"; if the value is "/x/y/z", it will be stored as "http://bomdel/x/y/z.mpeg".

## Example 3 (Importing into a Table with an Identity Column)

TABLE1 has 4 columns:

- C1 VARCHAR(30)
- C2 INT GENERATED BY DEFAULT AS IDENTITY
- C3 DECIMAL(7,2)
- C4 CHAR(1)

## db2Import - Import

TABLE2 is the same as TABLE1, except that C2 is a GENERATED ALWAYS identity column.

Data records in DATAFILE1 (DEL format):

```
"Liszt"  
"Hummel",,187.43, H  
"Grieg",100, 66.34, G  
"Satie",101, 818.23, I
```

Data records in DATAFILE2 (DEL format):

```
"Liszt", 74.49, A  
"Hummel", 0.01, H  
"Grieg", 66.34, G  
"Satie", 818.23, I
```

The following command generates identity values for rows 1 and 2, since no identity values are supplied in DATAFILE1 for those rows. Rows 3 and 4, however, are assigned the user-supplied identity values of 100 and 101, respectively.

```
db2 import from datafile1.del of del replace into table1
```

To import DATAFILE1 into TABLE1 so that identity values are generated for all rows, issue one of the following commands:

```
db2 import from datafile1.del of del method P(1, 3, 4)  
replace into table1 (c1, c3, c4)  
db2 import from datafile1.del of del modified by identityignore  
replace into table1
```

To import DATAFILE2 into TABLE1 so that identity values are generated for each row, issue one of the following commands:

```
db2 import from datafile2.del of del replace into table1 (c1, c3, c4)  
db2 import from datafile2.del of del modified by identitymissing  
replace into table1
```

If DATAFILE1 is imported into TABLE2 without using any of the identity-related file type modifiers, rows 1 and 2 will be inserted, but rows 3 and 4 will be rejected, because they supply their own non-NULL values, and the identity column is GENERATED ALWAYS.

### Example 4 (Importing Using Null Indicators)

TABLE1 has 5 columns:

- COL1 VARCHAR 20 NOT NULL WITH DEFAULT
- COL2 SMALLINT
- COL3 CHAR 4
- COL4 CHAR 2 NOT NULL WITH DEFAULT
- COL5 CHAR 2 NOT NULL

ASCFE1 has 6 elements:

- ELE1 positions 01 to 20
- ELE2 positions 21 to 22
- ELE5 positions 23 to 23
- ELE3 positions 24 to 27
- ELE4 positions 28 to 31
- ELE6 positions 32 to 32

- ELE6 positions 33 to 40

Data Records:

```

1...5...10...15...20...25...30...35...40
Test data 1          XXN 123abcdN
Test data 2 and 3   QQY   wxyzN
Test data 4,5 and 6 WWN6789   Y

```

The following command imports records from ASCFILE1 into TABLE1:

```

db2 import from ascfile1 of asc
method L (1 20, 21 22, 24 27, 28 31)
null indicators (0, 0, 23, 32)
insert into table1 (col1, col5, col2, col3)

```

**Notes:**

1. Since COL4 is not provided in the input file, it will be inserted into TABLE1 with its default value (it is defined NOT NULL WITH DEFAULT).
2. Positions 23 and 32 are used to indicate whether COL2 and COL3 of TABLE1 will be loaded NULL for a given row. If there is a Y in the column's null indicator position for a given record, the column will be NULL. If there is an N, the data values in the column's data positions of the input record (as defined in L(.....)) are used as the source of column data for the row. In this example, neither column in row 1 is NULL; COL2 in row 2 is NULL; and COL3 in row 3 is NULL.
3. In this example, the NULL INDICATORS for COL1 and COL5 are specified as 0 (zero), indicating that the data is not nullable.
4. The NULL INDICATOR for a given column can be anywhere in the input record, but the position must be specified, and the Y or N values must be supplied.

**Related concepts:**

- "Nicknames and data source objects" in the *Federated Systems Guide*

## db2Import - Import

---

## Chapter 3. Load

This chapter describes the DB2 UDB load utility, which moves data from files, named pipes, devices or a cursor into a DB2 table. These data sources can reside either on the node where the database resides, or on a remotely connected client. The table being loaded must exist. If the table receiving the new data already contains data, you can replace or append to the existing data.

The following topics are covered:

- “Load Overview” on page 74
- “Parallelism and loading” on page 80
- “Privileges, authorities, and authorizations required to use Load” on page 81
- “Using Load” on page 81
- “Read access load operations” on page 83
- “Building indexes” on page 86
- “Using load with identity columns” on page 87
- “Using load with generated columns” on page 89
- “Checking for integrity violations” on page 91
- “Refreshing dependent immediate materialized query tables” on page 94
- “Propagating dependent immediate staging tables” on page 95
- “Multidimensional clustering considerations” on page 96
- “Restarting an interrupted load operation” on page 97
- “Recovering data with the load copy location file” on page 98
- “LOAD” on page 100
- “LOAD QUERY” on page 121
- “db2Load - Load” on page 123
- “db2LoadQuery - Load Query” on page 145
- “Load exception table” on page 160
- “Load dump file” on page 160
- “Load temporary files” on page 161
- “Load utility log records” on page 162
- “Table locking, table states and table space states” on page 162
- “Character set and national language support” on page 165
- “Pending states after a load operation” on page 165
- “Optimizing load performance” on page 166
- “Load - CLP Examples” on page 171

For information about loading DB2 Data Links Manager data, see “Using import to move DB2 Data Links Manager data” on page 202.

## Load Overview

The load utility is capable of efficiently moving large quantities of data into newly created tables, or into tables that already contain data. The utility can handle most data types, including large objects (LOBs) and user-defined types (UDTs). The load utility is faster than the import utility, because it writes formatted pages directly into the database, while the import utility performs SQL INSERTs. The load utility does not fire triggers, and does not perform referential or table constraints checking (other than validating the uniqueness of the indexes).

The load process consists of four distinct phases (see Figure 1):

- Load, during which the data is written to the table.

During the load phase, data is loaded into the table, and index keys and table statistics are collected, if necessary. Save points, or points of consistency, are established at intervals specified through the SAVECOUNT parameter in the LOAD command. Messages are generated, indicating how many input rows were successfully loaded at the time of the save point. For DATALINK columns defined with FILE LINK CONTROL, link operations are performed for non-NULL column values. If a failure occurs, you can restart the load operation; the RESTART option automatically restarts the load operation from the last successful consistency point. The TERMINATE option rolls back the failed load operation.



*Figure 1. The Four Phases of the Load Process: Load, Build, Delete, and Index Copy.* While the load operation is taking place, the target table is in the load in progress state. If the table has constraints, the table will also be in the check pending state. If the ALLOW READ ACCESS option was specified, the table will also be in the read access only state.

- Build, during which indexes are produced.  
During the build phase, indexes are produced based on the index keys collected during the load phase. The index keys are sorted during the load phase, and index statistics are collected (if the STATISTICS YES with INDEXES option was specified). The statistics are similar to those collected through the RUNSTATS command. If a failure occurs during the build phase, the RESTART option automatically restarts the load operation at the appropriate point.
- Delete, during which the rows that caused a unique key violation or a DATALINK violation are removed from the table. Unique key violations are placed into the exception table, if one was specified, and messages about rejected rows are written to the message file. Following the completion of the load process, review these messages, resolve any problems, and insert corrected rows into the table.

Do not attempt to delete or to modify any temporary files created by the load utility. Some temporary files are critical to the delete phase. If a failure occurs during the delete phase, the RESTART option automatically restarts the load operation at the appropriate point.

**Note:** Each deletion event is logged. If you have a large number of records that violate the uniqueness condition, the log could fill up during the delete phase.



### Notes:

1. You can only view the contents of a message file after the operation is finished.
  2. Each message in a message file begins on a new line and contains information provided by the DB2 message retrieval facility.
- Whether column values being loaded have implied decimal points. The `implieddecimal` modifier tells the load utility that decimal points are to be applied to the data as it enters the table. For example, the value 12345 is loaded into a `DECIMAL(8,2)` column as 123.45, not 12345.00.
  - Whether the utility should modify the amount of free space available after a table is loaded. Additional free space permits `INSERT` and `UPDATE` growth to the table following the completion of a load operation. Reduced free space keeps related rows more closely together and can enhance table performance.
  - Whether statistics are to be gathered during the load process. This option is only supported if the load operation is running in `REPLACE` mode.

If data is appended to a table, statistics are not collected. To collect current statistics on an appended table, invoke the `runstats` utility following completion of the load process. If gathering statistics on a table with a unique index, and duplicate keys are deleted during the delete phase, statistics are not updated to account for the deleted records. If you expect to have a significant number of duplicate records, do not collect statistics during the load operation. Instead, invoke the `runstats` utility following completion of the load process.

- Whether to collect statistics during the load operation. Statistics are collected according to the profile defined for the table. The profile must be created by the `RUNSTATS` command before the `LOAD` command is executed. If the profile does not exist and the load operation is instructed to collect statistics according to the profile, the load will fail, and an error message will be returned.
- Whether to keep a copy of the changes made. This is done to enable rollforward recovery of the database. This option is not supported if forward log recovery is disabled for the database; that is, if the database configuration parameters `logretain` and `userexit` are disabled. If no copy is made, and forward log recovery is enabled, the table space is left in backup pending state at the completion of the load operation.

Logging is required for fully recoverable databases. The load utility almost completely eliminates the logging associated with the loading of data. In place of logging, you have the option of making a copy of the loaded portion of the table. If you have a database environment that allows for database recovery following a failure, you can do one of the following:

- Explicitly request that a copy of the loaded portion of the table be made.
- Take a backup of the table spaces in which the table resides immediately after the completion of the load operation.

If you are loading a table that already contains data, and the database is non-recoverable, ensure that you have a backed-up copy of the database, or the table spaces for the table being loaded, before invoking the load utility, so that you can recover from errors.

If you want to perform a sequence of multiple load operations on a recoverable database, the sequence of operations will be faster if you specify that each load operation is non-recoverable, and take a backup at the end of the load sequence, than if you invoke each of the load operations with the `COPY YES` option. You can use the `NONRECOVERABLE` option to specify that a load transaction is to be marked as non-recoverable, and that it will not be possible to recover it by a subsequent rollforward operation. The rollforward utility will skip the transaction, and will mark the table into which data was being loaded as

"invalid". The utility will also ignore any subsequent transactions against that table. After the rollforward operation is completed, such a table can only be dropped (see Figure 2). With this option, table spaces are not put in backup pending state following the load operation, and a copy of the loaded data does not have to be made during the load operation.




Figure 2. Non-recoverable Processing During a Roll Forward Operation

- Whether to log all index modifications. If the database configuration parameter *logindexbuild* is set, and if the load operation is invoked with the COPY YES recoverability option and the INCREMENTAL indexing option, the load will log all index modifications. The benefit of using these options is that when you roll forward through the log records for this load, you will also recover the indexes (whereas normally the indexes would not be recovered unless the load had used REBUILD indexing mode).
- The fully qualified path to be used when creating temporary files during a load operation. The name is specified by the TEMPFILES PATH parameter of the LOAD command. The default value is the database path. The path resides on the server machine, and is accessed by the DB2 instance exclusively. Therefore, any path name qualification given to this parameter must reflect the directory structure of the server, not the client, and the DB2 instance owner must have read and write permission on the path. This is true even if you are the instance owner. If you are not the instance owner, you must specify a location that is writable by the instance owner.

## Changes to Previous Load Behavior Introduced in Version 6 and Version 7

The Version 6 and the Version 7 load utilities have full back-level compatibility with previous releases; that is, they will accept syntax from previous releases and operate normally. Following is a summary of syntax changes and changes to load behavior introduced in Version 6 and Version 7:

- Load restart no longer uses a RESTARTCOUNT value, and the parameter is now reserved. When a previously interrupted load operation is restarted, the load operation will automatically continue from the last consistency point in the load, build, or delete phase.
- The sorting of index keys during index creation takes advantage of a new sorting algorithm used by the DB2 UDB Version 6 database engine. The amount of memory dedicated to sorting is controlled by the values of the sort heap (*sortheap*) database configuration parameter, and the sort heap threshold (*sheapthres*) database manager configuration parameter. If these options are specified in Version 6, an informational warning message is returned, but the load operation proceeds normally.

Sort spills that occur during load index creation are now performed inside a temporary table space. Sort operations do not spill directly to disk; rather, they spill to the buffer pool associated with the temporary table space. Having a large buffer pool associated with the temporary table space can improve index

creation time. To achieve the same type of I/O parallelism that was available in pre-Version 6 load sort operations (by specifying multiple temporary sort directories), it is recommended that temporary table spaces be declared with multiple containers, each residing on a different disk device. It is also recommended that temporary table spaces be declared as SMS (System Managed Space), so that they can grow to accommodate large volumes of data without holding disk resources when those resources are not being used.

- The REMOTE FILE option has been renamed (although the utility still accepts the REMOTE FILE parameter when specifying the path to temporary files). This is a purely syntactical change to better reflect the meaning and purpose of this parameter. The TEMPFILES PATH parameter refers to a directory, rather than a file.
- The load utility now supports several indexing modes (full REBUILD, INCREMENTAL extensions, index maintenance DEFERRED until after a load operation completes, and an AUTOSELECTION mode, which chooses between full rebuild and incremental maintenance at run time). The full rebuild mode mirrors the behavior of pre-Version 6 releases. The default behavior for Version 6 is AUTOSELECT mode.
- In Version 6, the TERMINATE option can be used to roll back a load operation. Previously this option would put a table space in restore pending state. Note, however, that a TERMINATE request after a failed LOAD REPLACE operation will *not* restore the table data.

The Version 7 load utility can load data residing on a remotely connected client, in fully qualified files or named pipes. (Separate files containing LOB values, when the lobsinfile file type modifier is specified, should be located on the server.)

## Changes to Previous Load Behavior Introduced in Version 8

Following is a summary of syntax changes and changes to load behavior introduced in Version 8:

- Prior to Version 8, load required exclusive access to table spaces that contained objects belonging to the table being loaded. In Version 8, load operates at the table level and no longer requires exclusive access to the table space. Load will place a lock only on the table objects associated with the load operation taking place. Concurrent access to other table objects in the same table spaces is permitted.
- Note:** Prior to Version 8, when the COPY NO option was specified on a recoverable database, the table space was put in backup pending state only after the load operation was committed. In Version 8, the table space will be placed in backup pending state when the load operation begins and will remain in that state even if the load operation fails and is rolled back. As in previous releases, when the COPY NO option is specified and load operation completes successfully, the rollforward utility will put dependent table spaces in restore pending state during a rollforward operation.
- You can also specify that users have read access to the data that existed in the table prior to the load. This means that after the load operation has completed, you will not be able to view the new data if there are constraints on the table and integrity checking has not been completed. You can also specify that the index be rebuilt in a separate table space during a load operation by specifying the READ ACCESS and INDEXING MODE REBUILD options. The index will be copied back to the original table space during the index copy phase which occurs after the other phases of the load operation.

- The functionality of the LOAD QUERY command has been expanded and it now returns the table state of the target into which data is being loaded in addition to the status information it previously included on a load operation in progress. The LOAD QUERY command might also be used to query the table state whether or not a load operation is in progress on that table.
- Extent allocations in DMS table spaces are now logged. The LOAD command will now write two log records for every extent it allocates in a DMS table space. Also, when the READ ACCESS and INDEXING MODE INCREMENTAL options are specified, some log records will be written while data is being incrementally inserted into the index.
- Dependent table spaces will no longer be quiesced prior to a load operation. When the COPY NO option is specified, the new table space state *load in progress* will be used. The load in progress table space state prevents the backup of dependent tables during a load operation. The load in progress table space state is different from the load in progress table space state in that all load operations use the load in progress table space state, but load operations with the COPY NO option specified also use the load in progress table space state.
- When executing a load operation with the ALLOW READ ACCESS and INDEXING MODE REBUILD options, a new copy of the indexes is created in addition to the original indexes. This means that the space requirement for the index table space might have to be doubled. To avoid this, the USE TABLESPACE option can be used to specify a temporary table space for the storage of new indexes. After the new indexes are built in the temporary table space, the target table is taken offline before the new indexes are copied into the target table space.
- Calls to quiesce table spaces from the LOAD command have been removed. If you quiesce table spaces in exclusive mode prior to a load operation, you will now have to explicitly remove the table spaces from the quiesced exclusive state. In previous releases, after issuing the following commands LOAD would have implicitly reset the quiesced table spaces and made them accessible to other applications:

```
quiesce tablespaces for table t1 exclusive
load from data.del of del insert into t1
```

In Version 8, you must issue the following command to remove the table space from the quiesced exclusive state:

```
quiesce tablespaces for table t1 reset
```

- A LOCK WITH FORCE option has been added to the LOAD command. It allows you to force other applications to release locks they have on a table and to allow the load operation to proceed and acquire the locks it needs.
- The load utility now has the ability to load from an SQL statement, using the new CURSOR file type.
- Loading data that resides on a remotely connected client is now supported under the following conditions:
  - The database that the client is connected to is in a partitioned database environment.
  - The database that the client is connected to is cataloged against an already cataloged database.
- Loading data into multi-dimensional clustering (MDC) tables is supported.
- Prior to Version 8, following a load operation the target table remained in check pending state if it contained generated columns. The load utility will now

generate column values, and you are no longer required issue the SET INTEGRITY statement after a load operation.

- Tables can now be loaded in a partitioned database environment. The AutoLoader utility (**db2atld**) is no longer required to accomplish this. The load API (**db2Load**) has also been enhanced to support the partitioned database load options.

**Related concepts:**

- “Rollforward recovery” in the *Data Recovery and High Availability Guide and Reference*

**Related reference:**

- “RUNSTATS Command” in the *Command Reference*
- “LOAD QUERY” on page 121
- “LOAD” on page 100
- “db2Load - Load” on page 123
- “LIST UTILITIES Command” in the *Command Reference*

---

## Parallelism and loading

The load utility takes advantage of a hardware configuration in which multiple processors or multiple storage devices are used, such as in a symmetric multiprocessor (SMP) environment. There are several ways in which parallel processing of large amounts of data can take place using the load utility. One way is through the use of multiple storage devices, which allows for I/O parallelism during the load operation (see Figure 3). Another way involves the use of multiple processors in an SMP environment, which allows for intra-partition parallelism (see Figure 4 on page 81). Both can be used together to provide even faster loading of data.




Figure 3. Taking Advantage of I/O Parallelism When Loading Data




Figure 4. Taking Advantage of Intra-partition Parallelism When Loading Data

**Related concepts:**

- “Optimizing load performance” on page 166

---

## Privileges, authorities, and authorizations required to use Load

To load data into a table, you must have one of the following:

- SYSADM authority
- DBADM authority
- LOAD authority on the database and
  - INSERT privilege on the table when the load utility is invoked in INSERT mode, TERMINATE mode (to terminate a previous load insert operation), or RESTART mode (to restart a previous load insert operation)
  - INSERT and DELETE privilege on the table when the load utility is invoked in REPLACE mode, TERMINATE mode (to terminate a previous load replace operation), or RESTART mode (to restart a previous load replace operation)
  - INSERT privilege on the exception table, if such a table is used as part of the load operation.

Since all load processes (and all DB2<sup>®</sup> server processes, in general), are owned by the instance owner, and all of these processes use the identification of the instance owner to access needed files, the instance owner must have read access to input data files. These input data files must be readable by the instance owner, regardless of who invokes the command.

On Windows<sup>®</sup> NT, Windows 2000 and Windows.NET operating systems where DB2 is running as a Windows service, if you are loading data from files that reside on a network drive, you must configure the DB2 service to run under a user account that has read access to these files.

**Related reference:**

- “LOAD” on page 100
- “db2Load - Load” on page 123

---

## Using Load

**Prerequisites:**

Before invoking the load utility, you must be connected to (or be able to implicitly connect to) the database into which the data will be loaded. Since the utility will issue a COMMIT statement, you should complete all transactions and release all locks by performing either a COMMIT or a ROLLBACK before invoking load.

Since data is loaded in the sequence that appears in the input file (except when using multi-dimensional clustering (MDC) tables), if a particular sequence is desired, the data should be sorted before a load operation is attempted.

If clustering is required, the data should be sorted on the clustering index prior to loading. When loading data into MDC tables, sorting is not required prior to the load operation, and data will be clustered according to the MDC table definition.

### Restrictions:

The following restrictions apply to the load utility:

- Loading data into nicknames is not supported.
- Loading data into typed tables, or tables with structured type columns, is not supported.
- Loading data into declared temporary tables is not supported.
- Attempts to create or drop tables in a table space that is in backup pending state will fail.
- You cannot load data into a database accessed through DB2 Connect or a down-level server prior to DB2 Version 2. Options that are only available with this release of DB2 cannot be used with a server from the previous release.
- If an error occurs during a LOAD REPLACE operation, the original data in the table is lost. Retain a copy of the input data to allow the load operation to be restarted.
- Triggers are not activated on newly loaded rows. Business rules associated with triggers are not enforced by the load utility.

### Procedure:

The load utility can be invoked through the command line processor (CLP), the Load notebook in the Control Centre, or an application programming interface (API), **db2Load**.

Following is an example of the LOAD command issued through the CLP:

```
db2 load from stafftab.ixf of ixf messages staff.msgs
insert into userid.staff copy yes use tsm data buffer 4000
```

In this example:

- Any warning or error messages are placed in the staff.msgs file.
- A copy of the changes made is stored in Tivoli Storage Manager (TSM, formerly ADSM).
- Four thousand pages of buffer space are to be used during the load operation.

Following is another example of the LOAD command issued through the CLP:

```
db2 load from stafftab.ixf of ixf messages staff.msgs
tempfiles path /u/myuser replace into staff
```

In this example:

- The table data is being replaced.

- The `TEMPFILES PATH` parameter is used to specify `/u/myuser` as the server path into which temporary files will be written.

**Note:** These examples use relative path names for the load input file. Relative path names are only allowed on calls from a client on the same node as the database. The use of fully qualified path names is recommended.

To open the Load notebook:

1. From the Control Center, expand the object tree until you find the Tables folder.
2. Click on the Tables folder. Any existing tables are displayed in the pane on the right side of the window (the contents pane).
3. Click the right mouse button on the table you want in the contents pane, and select Load from the pop-up menu. The Load notebook opens.

Detailed information about the Control Center is provided through its online help facility.

After you invoke the load utility, you can use the `LIST UTILITIES` command to monitor the progress of the load operation. In the case of a load operation performed in either `INSERT` mode, `REPLACE` mode, or `RESTART` mode, detailed progress monitoring support will be available. Issue the `LIST UTILITIES` command with the `SHOW DETAILS` option to view detailed information about the phase of load the utility is in currently. In the case of a load operation performed in `TERMINATE` mode however, details are not available. The `LIST UTILITIES` command will simply show that a load terminate utility is currently running. For more information, refer to `LIST UTILITIES Command`.

Load does not maintain any constraints other than the `UNIQUE` constraints. Instead, the table will be put into `CHECK PENDING` state at the beginning of Load. After the load operation is completed, the `SET INTEGRITY` command must be used to take the table out of `CHECK PENDING` state.

**Related reference:**

- “`LIST UTILITIES Command`” in the *Command Reference*
- “Tivoli Storage Manager” in the *Data Recovery and High Availability Guide and Reference*
- “`LOAD`” on page 100
- “`db2Load - Load`” on page 123

**Related samples:**

- “`tbmove.out -- HOW TO MOVE TABLE DATA (C)`”
- “`tbmove.sqc -- How to move table data (C)`”
- “`tbmove.out -- HOW TO MOVE TABLE DATA (C++)`”
- “`tbmove.sqC -- How to move table data (C++)`”

---

## Read access load operations

The load utility provides two options that control the amount of access other applications have to a table being loaded. The `ALLOW NO ACCESS` option locks the table exclusively and allows no access to the table data while the table is being loaded. This is the default behavior. The `ALLOW READ ACCESS` option prevents all write access to the table by other applications, but allows read access to pre-loaded data. This section deals with the `ALLOW READ ACCESS` option.

Table data and index data that exist prior to the start of a load operation are visible to queries while the load operation is in progress. Consider the following example:

1. Create a table with one integer column:

```
create table ED (ed int)
```

2. Load three rows:

```
load from File1 of del insert into ED
```

```
...
```

```
Number of rows read      = 3  
Number of rows skipped   = 0  
Number of rows loaded    = 3  
Number of rows rejected  = 0  
Number of rows deleted   = 0  
Number of rows committed = 3
```

3. Query the table:

```
select * from ED
```

```
ED  
-----  
      1  
      2  
      3
```

3 record(s) selected.

4. Perform a load operation with the ALLOW READ ACCESS option specified and load two more rows of data:

```
load from File2 of del insert into ED allow read access
```

5. At the same time, on another connection query the table while the load operation is in progress:

```
select * from ED
```

```
ED  
-----  
      1  
      2  
      3
```

3 record(s) selected.

6. Wait for the load operation to finish and then query the table:

```
select * from ED
```

```
ED  
-----  
      1  
      2  
      3  
      4  
      5
```

5 record(s) selected.

The ALLOW READ ACCESS option is very useful when loading large amounts of data because it gives users access to table data at all times, even when the load operation is in progress or after a load operation has failed. The behavior of a load operation in ALLOW READ ACCESS mode is independent of the isolation level of the application. That is, readers with any isolation level can always read the pre-existing data, but they will not be able to read the newly loaded data until the load operation has finished.

Read access is provided throughout the load operation except at the very end. Before data is committed the load utility acquires an exclusive lock (Z-lock) on the table. The load utility will wait until all applications that have locks on the table, release them. This might cause a delay before the data can be committed. The LOCK WITH FORCE option can be used to force off conflicting applications, and allow the load operation to proceed without having to wait.

Usually, a load operation in ALLOW READ ACCESS mode acquires an exclusive lock for a short amount of time; however, if the USE <tablespaceName> option is specified, the exclusive lock will last for the entire period of the index copy phase.

**Notes:**

1. If a load operation is aborted, it remains at the same access level that was specified when the load operation was issued. So, if a load operation in ALLOW NO ACCESS mode aborts, the table data is inaccessible until a load terminate or a load restart is issued. If a load operation in ALLOW READ ACCESS mode aborts, the pre-loaded table data is still accessible for read access.
2. If the ALLOW READ ACCESS option was specified for an aborted load operation, it can also be specified for the load restart or load terminate operation. However, if the aborted load operation specified the ALLOW NO ACCESS option, the ALLOW READ ACCESS option cannot be specified for the load restart or load terminate operation.

The ALLOW READ ACCESS option is not supported if:

- The REPLACE option is specified. Since a load replace operation truncates the existing table data before loading the new data, there is no pre-existing data to query until after the load operation is complete.
- The indexes have been marked invalid and are waiting to be rebuilt. Indexes can be marked invalid in some rollforward scenarios or through the use of the **db2dart** command.
- The INDEXING MODE DEFERRED option is specified. This mode marks the indexes as requiring a rebuild.
- An ALLOW NO ACCESS load operation is being restarted or terminated. Until it is brought fully online, a load operation in ALLOW READ ACCESS mode cannot take place on the table.
- A load operation is taking place to a table that is in check pending state and is not in read access state. This is also the case for multiple load operations on tables with constraints. A table is not brought online until the SET INTEGRITY statement is issued.

Generally, if table data is taken offline, read access is not available during a load operation until the table data is back online.

**Related concepts:**

- “Checking for integrity violations” on page 91
- “Table locking, table states and table space states” on page 162
- “Building indexes” on page 86

---

## Building indexes

Indexes are built during the build phase of a load operation. There are four indexing modes that can be specified in the LOAD command:

1. REBUILD. All indexes will be rebuilt.
2. INCREMENTAL. Indexes will be extended with new data.
3. AUTOSELECT. The load utility will automatically decide between REBUILD or INCREMENTAL mode. This is the default.

**Note:** You might decide to explicitly choose an indexing mode because the behavior of the REBUILD and INCREMENTAL modes are quite different.

4. DEFERRED. The load utility will not attempt index creation if this mode is specified. Indexes will be marked as needing a refresh, and a rebuild might be forced the first time they are accessed. This option is not compatible with the ALLOW READ ACCESS option because it does not maintain the indexes and index scanners require a valid index.

Load operations that specify the ALLOW READ ACCESS option require special consideration in terms of space usage and logging depending on the type of indexing mode chosen. When the ALLOW READ ACCESS option is specified, the load utility keeps indexes available for queries even while they are being rebuilt.

When a load operation in ALLOW READ ACCESS mode specifies the INDEXING MODE INCREMENTAL option, the load utility will write some log records that protect the integrity of the index tree. The number of log records written is a fraction of the number of inserted keys and is a number considerably less than would be needed by a similar SQL insert operation. A load operation in ALLOW NO ACCESS mode with the INDEXING MODE INCREMENTAL option specified writes only a small log record beyond the normal space allocation logs.

When a load operation in ALLOW READ ACCESS mode specifies the INDEXING MODE REBUILD option, new indexes are built as a *shadow* either in the same table space as the original index or in a system temporary table space. The original indexes remain intact and are available during the load operation and are only replaced by the new indexes at the end of the load operation while the table is exclusively locked. If the load operation fails and the transaction is rolled back, the original indexes will remain intact.

### Building New Indexes in the Same Table Space as the Original

By default, the *shadow* index is built in the same table space as the original index. Since both the original index and the new index are maintained simultaneously, there must be sufficient table space to hold both indexes at the same time. If the load operation is aborted, the extra space used to build the new index is released. If the load operation commits, the space used for the original index is released and the new index becomes the current index. When the new indexes are built in the same table space as the original indexes, replacing the original indexes will take place almost instantaneously.

If the indexes are built in a DMS table space, the new *shadow* index cannot be seen by the user. If the indexes are built within an SMS table space, the user can see

index files in the table space directory with the .IN1 suffix and the .INX suffix. These suffixes do not indicate which is the original index and which is the *shadow* index.

### Building New Indexes in a System Temporary Table Space

The new index can be built in a system temporary table space to avoid running out of space in the original table space. The USE <tablespaceName> option allows the indexes to be rebuilt in a system temporary table space when using INDEXING MODE REBUILD and ALLOW READ ACCESS options. The system temporary table can be an SMS or a DMS table space, but the page size of the system temporary table space must match the page size of the original index table space.

The USE <tablespaceName> option is ignored if the load operation is not in ALLOW READ ACCESS mode, or if the indexing mode is incompatible. The USE <tablespaceName> option is only supported for the INDEXING MODE REBUILD or INDEXING MODE AUTOSELECT options. If the INDEXING MODE AUTOSELECT option is specified and the load utility selects incremental maintenance of the indexes, the USE <tablespaceName> option will be ignored.

A load restart operation can use an alternate table space for building an index even if the original load operation did not use an alternate table space. A load restart operation cannot be issued in ALLOW READ ACCESS mode if the original load operation was not issued in ALLOW READ ACCESS mode. Load terminate operations do not rebuild indexes, so the USE <tablespaceName> option will be ignored.

During the build phase of the load operation, the indexes are built in the system temporary table space. Then, during the index copy phase, the index is copied from the system temporary table space to the original index table space. To make sure that there is sufficient space in the original index table space for the new index, space is allocated in the original table space during the build phase. So, if the load operation is going to run out of index space, it will do it during the build phase. If this happens, the original index will not be lost.

The index copy phase occurs after the build and delete phases. Before the index copy phase begins, the table is locked exclusively. That is, it is unavailable for read access throughout the index copy phase. Since the index copy phase is a physical copy, the table might be unavailable for a significant amount of time.

**Note:** If either the system temporary table space or the index table space are DMS table spaces, the read from the system temporary table space can cause random I/O on the system temporary table space and can cause a delay. The write to the index table space is still optimized and the DISK\_PARALLELISM values will be used.

#### Related concepts:

- “Load Overview” on page 74
- “Read access load operations” on page 83

---

## Using load with identity columns

The load utility can be used to load data into a table containing an identity column. If no identity-related file type modifiers are used, the utility works according to the following rules:

- If the identity column is `GENERATED ALWAYS`, an identity value is generated for a table row whenever the corresponding row in the input file is missing a value for the identity column, or a `NULL` value is explicitly given. If a non-`NULL` value is specified for the identity column, the row is rejected (SQL3550W).
- If the identity column is `GENERATED BY DEFAULT`, the load utility makes use of user-supplied values, if they are provided; if the data is missing or explicitly `NULL`, a value is generated.

The load utility does not perform any extra validation of user-supplied identity values beyond what is normally done for values of the identity column's data type (that is, `SMALLINT`, `INT`, `BIGINT`, or `DECIMAL`). Duplicate values will not be reported.

For a partitioned database, when an identity column is in the partitioning key for a table, or the identity column is referenced in a generated column that is part of the partitioning key, and the `identityoverride` modifier is not specified, then a load `RESTART` operation is not permitted when all of the loading partitions are not restarting from the "load" phase. Such a load is not allowed because hashing of rows during the restarted load might be different from the hashing in the initial load, due to the dependence on the identity column. In this case, you usually need to use the `TERMINATE` option of load to terminate the load.

Three (mutually exclusive) file type modifiers are supported by the load utility to simplify its use with tables that contain an identity column:

- The `identitymissing` modifier makes loading a table with an identity column more convenient if the input data file does not contain any values (not even `NULLS`) for the identity column. For example, consider a table defined with the following SQL statement:

```
create table table1 (c1 varchar(30),
                   c2 int generated by default as identity,
                   c3 decimal(7,2),
                   c4 char(1))
```

A user might want to load `TABLE1` with data from a file (`load.del`) that has been exported from a table that does not have an identity column. The following is an example of such a file:

```
Robert, 45.2, J
Mike, 76.9, K
Leo, 23.4, I
```

One way to load this file would be to explicitly list the columns to be loaded through the `LOAD` command as follows:

```
db2 load from load.del of del replace into table1 (c1, c3, c4)
```

For a table with many columns, however, this syntax might be cumbersome and prone to error. An alternate method of loading the file is to use the `identitymissing` file type modifier as follows:

```
db2 load from load.del of del modified by identitymissing
replace into table1
```

- The `identityignore` modifier is in some ways the opposite of the `identitymissing` modifier: it indicates to the load utility that even though the input data file contains data for the identity column, the data should be ignored, and an identity value should be generated for each row. For example, a user might want to load `TABLE1`, as defined above, from a data file (`load.del`) containing the following data:

```
Robert, 1, 45.2, J
Mike, 2, 76.9, K
Leo, 3, 23.4, I
```

If the user-supplied values of 1, 2, and 3 are not to be used for the identity column, the user could issue the following LOAD command:

```
db2 load from load.del of del method P(1, 3, 4)
replace into table1 (c1, c3, c4)
```

Again, this approach might be cumbersome and prone to error if the table has many columns. The `identityignore` modifier simplifies the syntax as follows:

```
db2 load from load.del of del modified by identityignore
replace into table1
```

- The `identityoverride` modifier is used for loading user-supplied values into a table with a `GENERATED ALWAYS` identity column. This can be quite useful when migrating data from another database system, and the table must be defined as `GENERATED ALWAYS`, or when loading a table from data that was recovered using the `DROPPED TABLE RECOVERY` option on the `ROLLFORWARD DATABASE` command. When this modifier is used, any rows with no data (or NULL data) for the identity column are rejected (SQL3116W).

**Note:** When using this modifier, it is possible to violate the uniqueness property of `GENERATED ALWAYS` columns.

#### Related concepts:

- “Identity columns” in the *Administration Guide: Planning*

---

## Using load with generated columns

The load utility can be used to load data into a table containing (non-identity) generated columns. The column values will be generated by this utility.

**Note:** If you initiate a load operation between a Version 7 or earlier client and a Version 8 or later server, the load utility will place tables with generated columns in check pending state.

If a table has been placed in check pending state because a Version 7 or earlier client was used to load data into a table with generated columns, the following statement will take the table out of check pending state and force the generation of values:

```
SET INTEGRITY FOR tablename IMMEDIATE CHECKED FORCE GENERATED;
```

If no generated column-related file type modifiers are used, the load utility works according to the following rules:

- Values will be created for generated columns when the corresponding row of the data file is missing a value for the column or a NULL value is supplied. If a non-NULL value is supplied for a generated column, the row is rejected (SQL3550W).
- If a NULL value is created for a generated column that is not nullable, the entire row of data will be rejected (SQL0407N). This could occur if, for example, a non-nullable generated column is defined as the sum of two table columns that include NULL values in the data file.

Three (mutually exclusive) file type modifiers are supported by the load utility to simplify its use with tables that contain generated columns:

- The `generatedmissing` modifier makes loading a table with generated columns more convenient if the input data file does not contain any values (not even NULLS) for all generated columns present in the table. For example, consider a table defined with the following SQL statement:

```
create table table1 (c1 int,
                   c2 int,
                   g1 int generated always as (c1 + c2),
                   g2 int generated always as (2 * c1),
                   c3 char(1))
```

A user might want to load TABLE1 with data from a file (`load.del`) that has been exported from a table that does not have any generated columns. The following is an example of such a file:

```
1, 5, J
2, 6, K
3, 7, I
```

One way to load this file would be to explicitly list the columns to be loaded through the LOAD command as follows:

```
db2 load from load.del of del replace into table1 (c1, c2, c3)
```

For a table with many columns, however, this syntax might be cumbersome and prone to error. An alternate method of loading the file is to use the `generatedmissing` file type modifier as follows:

```
db2 load from load.del of del modified by generatedmissing
replace into table1
```

- The `generatedignore` modifier is in some ways the opposite of the `generatedmissing` modifier: it indicates to the load utility that even though the input data file contains data for all generated columns present in the target table, the data should be ignored, and the computed values should be loaded into each generated column. For example, a user might want to load TABLE1, as defined above, from a data file (`load.del`) containing the following data:

```
1, 5, 10, 15, J
2, 6, 11, 16, K
3, 7, 12, 17, I
```

The user-supplied, non-NULL values of 10, 11, and 12 (for `g1`), and 15, 16, and 17 (for `g2`) result in the row being rejected (SQL3550W). To avoid this, the user could issue the following LOAD command:

```
db2 load from load.del of del method P(1, 2, 5)
replace into table1 (c1, c2, c3)
```

Again, this approach might be cumbersome and prone to error if the table has many columns. The `generatedignore` modifier simplifies the syntax as follows:

```
db2 load from load.del of del modified by generatedignore
replace into table1
```

- The `generatedoverride` modifier is used for loading user-supplied values into a table with generated columns. This can be useful when migrating data from another database system, or when loading a table from data that was recovered using the RECOVER DROPPED TABLE option of the ROLLFORWARD DATABASE command. When this modifier is used, any rows with no data (or NULL data) for non-nullable generated columns are rejected (SQL3116W).

When this modifier is used, the table will be placed in check pending state after the load operation. To take the table out of check pending state without verifying the user-supplied values, issue the following command:

```
SET INTEGRITY FOR table-name GENERATED COLUMN IMMEDIATE
UNCHECKED
```

To take the table out of check pending state and force verification of the user-supplied values, issue the following command:

```
SET INTEGRITY FOR table-name IMMEDIATE CHECKED.
```

The load utility supports loading tables with generated columns in the partitioning key. For these generated columns, the data for the dependent columns must appear within the first 32KB of data for each row being loaded.

For example, consider a table created with the following SQL statement:

```
create table table1 (c1 int, c2 int, g1 int generated always as (c1 + c2))
partitioning key (g1)
```

In order to successfully load data into this table, all of the data for columns c1 and c2 must be located within the first 32KB of each row being loaded. Any row that does not satisfy this restriction will be rejected.

**Note:** There is one case where load does NOT support generating column values: that is when one of the generated column expressions contains a user-defined function that is FENCED. If you attempt to load into such a table the utility will fail. However, you can provide your own values for these types of generated columns by using the generatedoverride file type modifier of load.

**Related concepts:**

- “Generated Columns” in the *Application Development Guide: Programming Client Applications*

---

## Checking for integrity violations

Following a load operation, the loaded table might be in check pending state in either READ or NO ACCESS mode if any of the following conditions exist:

- The table has table check constraints or referential integrity constraints defined on it.
- The table has datalink columns defined on it.
- The table has generated columns and a Version 7 or earlier client was used to initiate the load operation.
- The table has descendent immediate materialized query tables or descendent immediate staging tables referencing it.
- The table is a staging table or a materialized query table.

The STATUS flag of the SYSCAT.TABLES entry corresponding to the loaded table indicates the check pending state of the table. For the loaded table to be fully usable, the STATUS must have a value of N and the ACCESS MODE must have a value of F, indicating that the table is fully accessible and in normal state.

If the loaded table has descendent tables, the CHECK PENDING CASCADE parameter can be specified to indicate whether or not the check pending state of the loaded table should be immediately cascaded to the descendent tables.

If the loaded table has constraints as well as descendent foreign key tables, dependent materialized query tables and dependent staging tables, and if all of the tables are in normal state prior to the load operation, the following will result based on the load parameters specified:

**INSERT, ALLOW READ ACCESS, and CHECK PENDING CASCADE IMMEDIATE**

The loaded table, its dependent materialized query tables and dependent staging tables will be placed in check pending state with read access.

**INSERT, ALLOW READ ACCESS, and CHECK PENDING CASCADE DEFERRED**

Only the loaded table will be placed in check pending with read access. Descendent foreign key tables, descendent materialized query tables and descendent staging tables will remain in their original states.

**INSERT, ALLOW NO ACCESS, and CHECK PENDING CASCADE IMMEDIATE**

The loaded table, its dependent materialized query tables and dependent staging tables will be placed in check pending state with no access.

**INSERT or REPLACE, ALLOW NO ACCESS, and CHECK PENDING CASCADE DEFERRED**

Only the loaded table will be placed in check pending state with no access. Descendent foreign key tables, descendent immediate materialized query tables and descendent immediate staging tables will remain in their original states.

**REPLACE, ALLOW NO ACCESS, and CHECK PENDING CASCADE IMMEDIATE**

The table and all its descendent foreign key tables, descendent immediate materialized query tables, and descendent immediate staging tables will be placed in check pending state with no access.

**Note:** Specifying the ALLOW READ ACCESS option in a load replace operation will result in an error.

To remove the check pending state, use the SET INTEGRITY statement. The SET INTEGRITY statement checks a table for constraints violations, and takes the table out of check pending state. If all the load operations are performed in INSERT mode, the SET INTEGRITY statement can be used to incrementally process the constraints (that is, it will check only the appended portion of the table for constraints violations). For example:

```
db2 load from infile1.ixf of ixf insert into table1
db2 set integrity for table1 immediate checked
```

Only the appended portion of TABLE1 is checked for constraint violations. Checking only the appended portion for constraints violations is faster than checking the entire table, especially in the case of a large table with small amounts of appended data.

If a table is loaded with the CHECK PENDING CASCADE DEFERRED option specified, and the SET INTEGRITY statement is used to check for integrity violations, the descendent tables will be placed in check pending state with no access. To take the tables out of this state, you must issue an explicit request.

If a table with dependent materialized query tables or dependent staging tables is loaded using the INSERT option, and the SET INTEGRITY statement is used to check for integrity violations, the table will be taken out of check pending state and placed in NO DATA MOVEMENT mode. This is done to facilitate the subsequent incremental refreshes of the dependent materialized query tables and

the incremental propagation of the dependent staging tables. In the NO DATA MOVEMENT, operations that might cause the movement of rows within the table are not allowed.

You can override the NO DATA MOVEMENT mode by specifying the FULL ACCESS option when you issue the SET INTEGRITY statement. The table will be fully accessible, however a full recomputation of the dependent materialized query tables will take place in subsequent REFRESH TABLE statements and the dependent staging tables will be forced into an incomplete state.

If the ALLOW READ ACCESS option is specified for a load operation, the table will remain in read access state until the SET INTEGRITY statement is used to check for constraints violations. Applications will be able to query the table for data that existed prior to the load operation once it has been committed, but will not be able to view the newly loaded data until the SET INTEGRITY statement has been issued.

Several load operations can take place on a table before checking for constraints violations. If all of the load operations are completed in ALLOW READ ACCESS mode, only the data that it existed in the table prior to the first load operation will be available for queries.

One or more tables can be checked in a single invocation of this statement. If a dependent table is to be checked on its own, the parent table can not be in check pending state. Otherwise, both the parent table and the dependent table must be checked at the same time. In the case of a referential integrity cycle, all the tables involved in the cycle must be included in a single invocation of the SET INTEGRITY statement. It might be convenient to check the parent table for constraints violations while a dependent table is being loaded. This can only occur if the two tables are not in the same table space.

When issuing the SET INTEGRITY statement, you can specify the INCREMENTAL option to explicitly request incremental processing. In most cases, this option is not needed, because DB2® will select incremental processing. If incremental processing is not possible, full processing is used automatically. When the INCREMENTAL option is specified, but incremental processing is not possible, an error is returned if:

- New constraints were added to the table while it was in check pending state.
- A load replace operation has taken place, or the NOT LOGGED INITIALLY WITH EMPTY TABLE option was activated, after the last integrity check on the table.
- A parent table has been load replaced or checked for integrity non-incrementally.
- The table was in check pending state before migration. Full processing is required the first time the table is checked for integrity after migration.
- The table space containing the table or its parent has been rolled forward to a point in time and the table and its parent reside in different table spaces.

If a table has one or more W values in the CONST\_CHECKED column of the SYSCAT.TABLES catalog, and if the NOT INCREMENTAL option is not specified in the SET INTEGRITY statement, the table will be incrementally processed and the CONST\_CHECKED column of SYSCAT.TABLES will be marked as U to indicate that not all data has been verified by the system.

Use the load exception table option to capture information about rows with constraints violations.

The SET INTEGRITY statement does not activate any DELETE triggers as a result of deleting rows that violate constraints, but once the table is removed from check pending state, triggers are active. Thus, if we correct data and insert rows from the exception table into the loaded table, any INSERT triggers defined on the table will be activated. The implications of this should be considered. One option is to drop the INSERT trigger, insert rows from the exception table, and then recreate the INSERT trigger.

**Related concepts:**

- “Pending states after a load operation” on page 165
- “Read access load operations” on page 83

**Related reference:**

- “SET INTEGRITY statement” in the *SQL Reference, Volume 2*

---

## Refreshing dependent immediate materialized query tables

If the underlying table of an immediate refresh materialized query table is loaded using the INSERT option, executing the SET INTEGRITY statement on the dependent materialized query tables defined with REFRESH IMMEDIATE will result in an incremental refresh of the materialized query table. During an incremental refresh, the rows corresponding to the appended rows in the underlying tables are updated and inserted into the materialized query tables. Incremental refresh is faster in the case of large underlying tables with small amounts of appended data. There are cases in which incremental refresh is not allowed, and full refresh (that is, recomputation of the materialized query table definition query) will be used.

When the INCREMENTAL option is specified, but incremental processing of the materialized query table is not possible, an error is returned if:

- A load replace operation has taken place into an underlying table of the materialized query table or the NOT LOGGED INITIALLY WITH EMPTY TABLE option has been activated since the last integrity check on the underlying table.
- The materialized query table has been loaded (in either REPLACE or INSERT mode).
- An underlying table has been taken out of check pending state before the materialized query table is refreshed by using the FULL ACCESS option during integrity checking.
- An underlying table of the materialized query table has been checked for integrity non-incrementally.
- The materialized query table was in check pending state before migration.
- The table space containing the materialized query table or its underlying table has been rolled forward to a point in time, and the materialized query table and its underlying table reside in different table spaces.

If the materialized query table has one or more W values in the CONST\_CHECKED column of the SYSCAT.TABLES catalog, and if the NOT INCREMENTAL option is not specified in the SET INTEGRITY statement, the table will be incrementally refreshed and the CONST\_CHECKED column of SYSCAT.TABLES will be marked U to indicate that not all data has been verified by the system.

The following example illustrates a load insert operation into the underlying table UT1 of the materialized query table AST1. UT1 will be checked for data integrity and will be placed in no data movement mode. UT1 will be put back into full access state once the incremental refresh of AST1 is complete. In this scenario, both the integrity checking for UT1 and the refreshing of AST1 will be processed incrementally.

```
LOAD FROM IMTFILE1.IXF of IXF INSERT INTO UT1;  
LOAD FROM IMTFILE2.IXF of IXF INSERT INTO UT1;  
SET INTEGRITY FOR UT1 IMMEDIATE CHECKED;  
REFRESH TABLE AST1;
```

**Related concepts:**

- “Checking for integrity violations” on page 91

---

## Propagating dependent immediate staging tables

If the table being loaded is an underlying table of a staging table with the immediate propagate attribute, and if the load operation is done in insert mode, the subsequent propagation into the dependent immediate staging tables will be incremental.

During incremental propagation, the rows corresponding to the appended rows in the underlying tables are appended into the staging tables. Incremental propagation is faster in the case of large underlying tables with small amounts of appended data. Performance will also be improved if the staging table is used to refresh its dependent deferred materialized query table. There are cases in which incremental propagation is not allowed, and the staging table will be marked incomplete. That is, the staging byte of the CONST\_CHECKED column will have a value of F. In this state, the staging table can not be used to refresh its dependent deferred materialized query table, and a full refresh will be required in the materialized query table maintenance process.

If a table is in incomplete state and the INCREMENTAL option has been specified, but incremental propagation of the table is not possible, an error is returned. If any of the following have taken place, the system will turn off immediate data propagation and set the table state to incomplete:

- A load replace operation has taken place on an underlying table of the staging table, or the NOT LOGGED INITIALLY WITH EMPTY TABLE option has been activated after the last integrity check on the underlying table.
- The dependent materialized query table of the staging table, or the staging table has been loaded in REPLACE or INSERT mode.
- An underlying table has been taken out of check pending state before the staging table has been propagated by using the FULL ACCESS option during integrity checking.
- An underlying table of the staging table has been checked for integrity non-incrementally.
- The table space containing the staging table or its underlying table has been rolled forward to a point in time, and the staging table and its underlying table reside in different table spaces.

If the staging table has a W value in the CONST\_CHECKED column of the SYSCAT.TABLES catalog, and the NOT INCREMENTAL option is not specified, incremental propagation to the staging table takes place and the

CONST\_CHECKED column of SYSCAT.TABLES will be marked as U to indicate that not all data has been verified by the system.

The following example illustrates a load insert operation into the underlying table UT1 of staging table G1 and its dependent deferred materialized query table AST1. In this scenario, both the integrity checking for UT1 and the refreshing of AST1 will be processed incrementally:

```
LOAD FROM IMTFILE1.IXF of IXF INSERT INTO UT1;  
LOAD FROM IMTFILE2.IXF of IXF INSERT INTO UT1;  
SET INTEGRITY FOR UT1,G1 IMMEDIATE CHECKED;  
  
REFRESH TABLE AST1 INCREMENTAL;
```

**Related concepts:**

- “Checking for integrity violations” on page 91

---

## Multidimensional clustering considerations

The following restrictions apply to multi-dimensional clustering (MDC) tables:

- The SAVECOUNT option of the LOAD command is not supported.
- The TOTALFREESPACE file type modifier is not supported since these tables manage their own free space.
- The ANYORDER modifier is required for MDC tables. If a load is executed into an MDC table without the ANYORDER modifier, it will be explicitly enabled by the utility.

When using the LOAD command with MDC, violations of unique constraints will be handled as follows:

- If the table included a unique key prior to the load operation and duplicate records are loaded into the table, the original record will remain and the new records will be deleted during the delete phase.
- If the table did not include a unique key prior to the load operation and both a unique key and duplicate records are loaded into the table, only one of the records with the unique key will be loaded and the others will be deleted during the delete phase.

**Note:** There is no explicit technique for determining which record will be loaded and which will be deleted.

### Performance Considerations

To improve the performance of the load utility when loading MDC tables, the UTIL\_HEAP\_SZ database configuration parameter value should be increased. The mdc-load algorithm will perform significantly better when more memory is available to the utility. This will reduce disk I/O during the clustering of data that is performed during the load phase. When the DATA BUFFER option of LOAD command is specified, its value should also be increased. If the LOAD command is being used to load several MDC tables concurrently, the UTIL\_HEAP\_SZ configuration parameter should be increased accordingly.

MDC load operations will always have a build phase since all MDC tables have block indexes.

During the load phase, extra logging for the maintenance of the block map will be performed. There are approximately two extra log records per extent allocated. To ensure good performance, the LOGBUFSZ database configuration parameter should be set to a value that takes this into account.

A system temporary table with an index is used to load data into MDC tables. The size of the table is proportional to the number of distinct cells loaded. The size of each row in the table is proportional to the size of the MDC dimension key. To minimize disk I/O caused by the manipulation of this table during a load operation, ensure that the buffer pool for the temporary table space is large enough.

**Related concepts:**

- “Optimizing load performance” on page 166
- “Multidimensional clustering tables” in the *Administration Guide: Planning*

---

## Restarting an interrupted load operation

If the load utility cannot start because of a user error, such as a nonexistent data file or invalid column names, it will terminate and leave the table in a normal state.

If a failure occurs while loading data, you can restart the load operation from the last consistency point (using the RESTART option), or reload the entire table (using the REPLACE option). Specify the same parameters as in the previous invocation, so that the utility can find the necessary temporary files. Because the SAVECOUNT parameter is not supported for multi-dimensional clustering (MDC) tables, a load restart will only take place at the beginning of the load, build, or delete phase.

**Note:** A load operation that specified the ALLOW READ ACCESS option can be restarted using either the ALLOW READ ACCESS option or the ALLOW NO ACCESS option. Conversely, a load operation that specified the ALLOW NO ACCESS option can not be restarted using the ALLOW READ ACCESS option.

## Restarting or Terminating an Allow Read Access Load Operation

A aborted load operation that specified the ALLOW READ ACCESS option might also be restarted or terminated using the ALLOW READ ACCESS option. This will allow other applications to query the table data while the terminate or restart operation is in progress. As with a load operation in ALLOW READ ACCESS mode, the table is locked exclusively prior to the data being committed.

If the index object is unavailable or marked invalid, a load restart or terminate operation in ALLOW READ ACCESS mode will not be permitted.

If the original load operation was aborted in the index copy phase, a restart operation in the ALLOW READ ACCESS mode is not permitted because the index might be corrupted.

If a load operation in ALLOW READ ACCESS mode was aborted in the load phase, it will restart in the load phase. If it was aborted in any phase other than the load phase, it will restart in the build phase. If the original load operation was in ALLOW NO ACCESS mode, a restart operation might occur in the delete phase

if the original load operation reached that point and the index is valid. If the index is marked invalid, the load utility will restart the load operation from the build phase.

**Note:** All load restart operations will choose the REBUILD indexing mode even if the INDEXING MODE INCREMENTAL option is specified.

Issuing a LOAD TERMINATE command will generally cause the aborted load operation to be rolled back with minimal delay. However, when issuing a LOAD TERMINATE command for a load operation where ALLOW READ ACCESS and INDEXING MODE INCREMENTAL are specified, there might be a delay while the load utility scans the indexes and corrects any inconsistencies. The length of this delay will depend on the size of the indexes and will occur whether or not the ALLOW READ ACCESS option is specified for the load terminate operation. The delay will not occur if the original load operation failed prior to the build phase.

**Note:** The delay resulting from corrections to inconsistencies in the index will be considerably less than the delay caused by marking the indexes as invalid and rebuilding them.

A load restart operation cannot be undertaken on a table that is in the not load restartable table state. The table can be placed in the not load restartable table state during a rollforward operation. This can occur if you roll forward to a point in time that is prior to the end of a load operation, or if you roll forward through an aborted load operation but do not roll forward to the end of the load terminate or load restart operation.

**Related concepts:**

- “Table locking, table states and table space states” on page 162
- “Restarting or terminating a load operation in a partitioned database environment” on page 186

**Related reference:**

- “Partitioned database load configuration options” on page 187

---

## Recovering data with the load copy location file

The DB2LOADREC registry variable is used to identify the file with the load copy location information. This file is used during rollforward recovery to locate the load copy. It has information about:

- Media type
- Number of media devices to be used
- Location of the load copy generated during a table load operation
- File name of the load copy, if applicable

If the location file does not exist, or no matching entry is found in the file, the information from the log record is used.

The information in the file might be overwritten before rollforward recovery takes place.

**Notes:**

1. In a partitioned database environment, the DB2LOADREC registry variable must be set for all the database partition servers using the **db2set** command.

2. In a partitioned database environment, the load copy file must exist at each database partition server, and the file name (including the path) must be the same.
3. If an entry in the file identified by the DB2LOADREC registry variable is not valid, the old load copy location file is used to provide information to replace the invalid entry.

The following information is provided in the location file. The first five parameters must have valid values, and are used to identify the load copy. The entire structure is repeated for each load copy recorded. For example:

```

| TIMestamp      19950725182542      * Time stamp generated at load time
| SCHEMA        PAYROLL              * Schema of table loaded
| TABlename     EMPLOYEES            * Table name
| DATAbasename  DBT                  * Database name
| DB2instance   toronto              * DB2INSTANCE
| BUffernumber  NULL                 * Number of buffers to be used for
|                                     recovery
|
| SESSionnumber NULL                 * Number of sessions to be used for
|                                     recovery
|
| TYPeofmedia   L                    * Type of media - L for local device
|                                     A for TSM
|                                     0 for other vendors
|
| LOCationnumber 3                    * Number of locations
|   ENtry       /u/toronto/dbt.payroll.employees.001
|   ENT         /u/toronto/dbt.payroll.employees.002
|   ENT         /dev/rmt0
|
| TIM           19950725192054
| SCH          PAYROLL
| TAB          DEPT
| DAT          DBT
| DB2®         toronto
| BUF          NULL
| SES          NULL
| TYP          A
|
| TIM           19940325192054
| SCH          PAYROLL
| TAB          DEPT
| DAT          DBT
| DB2          toronto
| BUF          NULL
| SES          NULL
| TYP          0
|
| SHRlib       /@sys/lib/backup_vendor.a

```

**Notes:**

1. The first three characters in each keyword are significant. All keywords are required in the specified order. Blank lines are not accepted.
2. The time stamp is in the form *yyyymmddhhmmss*.
3. All fields are mandatory, except for BUF and SES, which can be NULL. If SES is NULL, the value specified by the *numloadrecses* configuration parameter is used. If BUF is NULL, the default value is SES+2.
4. If even one of the entries in the location file is invalid, the previous load copy location file is used to provide those values.
5. The media type can be local device (L for tape, disk or diskettes), TSM (A), or other vendor (0). If the type is L, the number of locations, followed by the location entries, is required. If the type is A, no further input is required. If the type is 0, the shared library name is required.
6. The SHRlib parameter points to a library that has a function to store the load copy data.

7. If you invoke a load operation, specifying the COPY NO or the NONRECOVERABLE option, and do not take a backup copy of the database or affected table spaces after the operation completes, you cannot restore the database or table spaces to a point in time that follows the load operation. That is, you cannot use rollforward recovery to rebuild the database or table spaces to the state they were in following the load operation. You can only restore the database or table spaces to a point in time that precedes the load operation.

If you want to use a particular load copy, you can use the recovery history file for the database to determine the time stamp for that specific load operation. In a partitioned database environment, the recovery history file is local to each database partition.

**Related reference:**

- “Tivoli Storage Manager” in the *Data Recovery and High Availability Guide and Reference*

---

## LOAD

Loads data into a DB2 table. Data residing on the server may be in the form of a file, tape, or named pipe. Data residing on a remotely connected client may be in the form of a fully qualified file or named pipe. Data can also be loaded from a user-defined cursor.

**Restrictions:**

- 4 The load utility does not support loading data at the hierarchy level. The load
- 4 utility is not compatible with range-clustered tables.

**Scope:**

This command may be issued against multiple database partitions in a single request.

**Authorization:**

One of the following:

- *sysadm*
- *dbadm*
- load authority on the database and
  - INSERT privilege on the table when the load utility is invoked in INSERT mode, TERMINATE mode (to terminate a previous load insert operation), or RESTART mode (to restart a previous load insert operation)
  - INSERT and DELETE privilege on the table when the load utility is invoked in REPLACE mode, TERMINATE mode (to terminate a previous load replace operation), or RESTART mode (to restart a previous load replace operation)
  - INSERT privilege on the exception table, if such a table is used as part of the load operation.


Since all load processes (and all DB2 server processes, in general) are owned by the instance owner, and all of these processes use the identification of the instance owner to access needed files, the instance owner must have read access to input data files. These input data files must be readable by the instance owner, regardless of who invokes the command.

**Required connection:**


Database. If implicit connect is enabled, a connection to the default database is established.

Instance. An explicit attachment is not required. If a connection to the database has been established, an implicit attachment to the local instance is attempted.


**Command syntax:**



## LOAD



### datalink-spec:



### Command parameters:

#### ALLOW NO ACCESS

Load will lock the target table for exclusive access during the load. The table state will be set to LOAD IN PROGRESS during the load. ALLOW NO ACCESS is the default behavior. It is the only valid option for LOAD REPLACE.

When there are constraints on the table, the table state will be set to CHECK PENDING as well as LOAD IN PROGRESS. The SET INTEGRITY statement must be used to take the table out of CHECK PENDING.

#### ALLOW READ ACCESS

Load will lock the target table in a share mode. The table state will be set to both LOAD IN PROGRESS and READ ACCESS. Readers may access the non-delta portion of the data while the table is being load. In other words, data that existed before the start of the load will be accessible by readers to the table, data that is being loaded is not available until the load is complete. LOAD TERMINATE or LOAD RESTART of an ALLOW READ ACCESS load may use this option; LOAD TERMINATE or LOAD RESTART of an ALLOW NO ACCESS load may not use this option. Furthermore, this option is not valid if the indexes on the target table are marked as requiring a rebuild.

When there are constraints on the table, the table state will be set to CHECK PENDING as well as LOAD IN PROGRESS, and READ ACCESS. At the end of the load the table state LOAD IN PROGRESS state will be removed but the table states CHECK PENDING and READ ACCESS will remain. The SET INTEGRITY statement must be used to take the table out of CHECK PENDING. While the table is in CHECK PENDING and READ ACCESS, the non-delta portion of the data is still accessible to readers, the new (delta) portion of the data will remain inaccessible until the SET INTEGRITY statement has completed. A user may perform multiple loads on the same table without issuing a SET INTEGRITY statement. Only the original (checked) data will remain visible, however, until the SET INTEGRITY statement is issued.

ALLOW READ ACCESS also supports the following modifiers:

#### USE *tablespace-name*

If the indexes are being rebuilt, a shadow copy of the index is built in table space *tablespace-name* and copied over to the original table space at the end of the load during an INDEX COPY PHASE. Only system temporary table spaces can be used with this option. If not

specified then the shadow index will be created in the same table space as the index object. If the shadow copy is created in the same table space as the index object, the copy of the shadow index object over the old index object is instantaneous. If the shadow copy is in a different table space from the index object a physical copy is performed. This could involve considerable I/O and time. The copy happens while the table is offline at the end of a load during the INDEX COPY PHASE.

Without this option the shadow index is built in the same table space as the original. Since both the original index and shadow index by default reside in the same table space simultaneously, there may be insufficient space to hold both indexes within one table space. Using this option ensures that you retain enough table space for the indexes.

This option is ignored if the user does not specify INDEXING MODE REBUILD or INDEXING MODE AUTOSELECT. This option will also be ignored if INDEXING MODE AUTOSELECT is chosen and load chooses to incrementally update the index.

### **CHECK PENDING CASCADE**

If LOAD puts the table into a check pending state, the CHECK PENDING CASCADE option allows the user to specify whether or not the check pending state of the loaded table is immediately cascaded to all descendents (including descendent foreign key tables, descendent immediate materialized query tables and descendent immediate staging tables).

### **IMMEDIATE**

Indicates that the check pending state (read or no access mode) for foreign key constraints is immediately extended to all descendent foreign key tables. If the table has descendent immediate materialized query tables or descendent immediate staging tables, the check pending state is extended immediately to the materialized query tables and the staging tables. Note that for a LOAD INSERT operation, the check pending state is not extended to descendent foreign key tables even if the IMMEDIATE option is specified.

When the loaded table is later checked for constraint violations (using the IMMEDIATE CHECKED option of the SET INTEGRITY statement), descendent foreign key tables that were placed in check pending read state will be put into check pending no access state.

### **DEFERRED**

Indicates that only the loaded table will be placed in the check pending state (read or no access mode). The states of the descendent foreign key tables, descendent immediate materialized query tables and descendent immediate staging tables will remain unchanged.

Descendent foreign key tables may later be implicitly placed in the check pending no access state when their parent tables are checked for constraint violations (using the IMMEDIATE CHECKED option of the SET INTEGRITY statement). Descendent immediate materialized query tables and descendent immediate staging tables will be implicitly placed in the check pending no access state when one of its underlying tables is checked for integrity violations. A

## LOAD

warning (SQLSTATE 01586) will be issued to indicate that dependent tables have been placed in the check pending state. See the Notes section of the SET INTEGRITY statement in the SQL Reference for when these descendent tables will be put into the check pending state.

If the CHECK PENDING CASCADE option is not specified:

- Only the loaded table will be placed in the check pending state. The state of descendent foreign key tables, descendent immediate materialized query tables and descendent immediate staging tables will remain unchanged, and may later be implicitly put into the check pending state when the loaded table is checked for constraint violations.

If LOAD does not put the target table into check pending state, the CHECK PENDING CASCADE option is ignored.

### CLIENT

Specifies that the data to be loaded resides on a remotely connected client. This option is ignored if the load operation is not being invoked from a remote client. This option is not supported in conjunction with the CURSOR filetype.

#### Notes:

1. The dumpfile and lobsinfile modifiers refer to files on the server even when the CLIENT keyword is specified.
2. Code page conversion is not performed during a remote load operation. If the code page of the data is different from that of the server, the data code page should be specified using the codepage modifier.

In the following example, a data file (/u/user/data.del) residing on a remotely connected client is to be loaded into MYTABLE on the server database:

```
db2 load client from /u/user/data.del of del
      modified by codepage=850 insert into mytable
```

### COPY NO

Specifies that the table space in which the table resides will be placed in backup pending state if forward recovery is enabled (that is, *logretain* or *userexit* is on). The COPY NO option will also put the table space state into the Load in Progress table space state. This is a transient state that will disappear when the load completes or aborts. The data in any table in the table space cannot be updated or deleted until a table space backup or a full database backup is made. However, it is possible to access the data in any table by using the SELECT statement.

LOAD with COPY NO on a recoverable database leaves the table spaces in a backup pending state. For example, performing a LOAD with COPY NO and INDEXING MODE DEFERRED will leave indexes needing a refresh. Certain queries on the table may require an index scan and will not succeed until the indexes are refreshed. The index cannot be refreshed if it resides in a table space which is in the backup pending state. In that case, access to the table will not be allowed until a backup is taken.

**Note:** Index refresh is done automatically by the database when the index is accessed by a query.

### COPY YES

Specifies that a copy of the loaded data will be saved. This option is

invalid if forward recovery is disabled (both *logretain* and *userexit* are off). The option is not supported for tables with DATALINK columns.

#### USE TSM

Specifies that the copy will be stored using Tivoli Storage Manager (TSM).

#### OPEN num-sess SESSIONS

The number of I/O sessions to be used with TSM or the vendor product. The default value is 1.

#### TO device/directory

Specifies the device or directory on which the copy image will be created.

#### LOAD lib-name

The name of the shared library (DLL on Windows operating systems) containing the vendor backup and restore I/O functions to be used. It may contain the full path. If the full path is not given, it will default to the path where the user exit programs reside.

#### CPU\_PARALLELISM n

Specifies the number of processes or threads that the load utility will spawn for parsing, converting, and formatting records when building table objects. This parameter is designed to exploit intra-partition parallelism. It is particularly useful when loading presorted data, because record order in the source data is preserved. If the value of this parameter is zero, or has not been specified, the load utility uses an intelligent default value (usually based on the number of CPUs available) at run time.

#### Notes:

1. If this parameter is used with tables containing either LOB or LONG VARCHAR fields, its value becomes one, regardless of the number of system CPUs or the value specified by the user.
2. Specifying a small value for the SAVECOUNT parameter causes the loader to perform many more I/O operations to flush both data and table metadata. When CPU\_PARALLELISM is greater than one, the flushing operations are asynchronous, permitting the loader to exploit the CPU. When CPU\_PARALLELISM is set to one, the loader waits on I/O during consistency points. A load operation with CPU\_PARALLELISM set to two, and SAVECOUNT set to 10 000, completes faster than the same operation with CPU\_PARALLELISM set to one, even though there is only one CPU.

#### DATA BUFFER buffer-size

Specifies the number of 4KB pages (regardless of the degree of parallelism) to use as buffered space for transferring data within the utility. If the value specified is less than the algorithmic minimum, the minimum required resource is used, and no warning is returned.

This memory is allocated directly from the utility heap, whose size can be modified through the *util\_heap\_sz* database configuration parameter.

If a value is not specified, an intelligent default is calculated by the utility at run time. The default is based on a percentage of the free space available in the utility heap at the instantiation time of the loader, as well as some characteristics of the table.

**DATALINK SPECIFICATION**

For each DATALINK column, there can be one column specification enclosed by parentheses. Each column specification consists of one or more DL\_LINKTYPE, prefix, and a DL\_URL\_SUFFIX specification. The prefix specification can be either DL\_URL\_REPLACE\_PREFIX or DL\_URL\_DEFAULT\_PREFIX.

There can be as many DATALINK column specifications as the number of DATALINK columns defined in the table. The order of specifications follows the order of DATALINK columns found within the *insert-column* list, or within the table definition (if an *insert-column* list is not specified).

**DISK\_PARALLELISM n**

Specifies the number of processes or threads that the load utility will spawn for writing data to the table space containers. If a value is not specified, the utility selects an intelligent default based on the number of table space containers and the characteristics of the table.

**DL\_LINKTYPE**

If specified, it should match the LINKTYPE of the column definition. Thus, DL\_LINKTYPE URL is acceptable if the column definition specifies LINKTYPE URL.

**DL\_URL\_DEFAULT\_PREFIX "prefix"**

If specified, it should act as the default prefix for all DATALINK values within the same column. In this context, prefix refers to the "scheme host port" part of the URL specification.

Examples of prefix are:

```
"http://server"
"file://server"
"file:"
"http://server:80"
```

If no prefix is found in the column data, and a default prefix is specified with DL\_URL\_DEFAULT\_PREFIX, the default prefix is prefixed to the column value (if not NULL).

For example, if DL\_URL\_DEFAULT\_PREFIX specifies the default prefix "http://toronto":

- The column input value "/x/y/z" is stored as "http://toronto/x/y/z".
- The column input value "http://coyote/a/b/c" is stored as "http://coyote/a/b/c".
- The column input value NULL is stored as NULL.

**DL\_URL\_REPLACE\_PREFIX "prefix"**

This clause is useful when loading or importing data previously generated by the export utility, if the user wants to globally replace the host name in the data with another host name. If specified, it becomes the prefix for *all* non-NULL column values. If a column value has a prefix, this will replace it. If a column value has no prefix, the prefix specified by DL\_URL\_REPLACE\_PREFIX is prefixed to the column value.

For example, if DL\_URL\_REPLACE\_PREFIX specifies the prefix "http://toronto":

- The column input value "/x/y/z" is stored as "http://toronto/x/y/z".
- The column input value "http://coyote/a/b/c" is stored as "http://toronto/a/b/c". Note that "toronto" replaces "coyote".

- The column input value NULL is stored as NULL.

**DL\_URL\_SUFFIX "suffix"**

If specified, it is appended to every non-NULL column value for the column. It is, in fact, appended to the "path" component of the data location part of the DATALINK value.

**FOR EXCEPTION table-name**

Specifies the exception table into which rows in error will be copied. Any row that is in violation of a unique index or a primary key index is copied. DATALINK exceptions are also captured in the exception table. If an unqualified table name is specified, the table will be qualified with the CURRENT SCHEMA.

Information that is written to the exception table is *not* written to the dump file. In a partitioned database environment, an exception table must be defined for those partitions on which the loading table is defined. The dump file, on the other hand, contains rows that cannot be loaded because they are invalid or have syntax errors.

**FROM filename/pipename/device/cursorname**

Specifies the file, pipe, device, or cursor referring to an SQL statement that contains the data being loaded. If the input source is a file, pipe, or device, it must reside on the database partition where the database resides, unless the CLIENT option is specified. If several names are specified, they will be processed in sequence. If the last item specified is a tape device, the user is prompted for another tape. Valid response options are:

- c** Continue. Continue using the device that generated the warning message (for example, when a new tape has been mounted).
- d** Device terminate. Stop using the device that generated the warning message (for example, when there are no more tapes).
- t** Terminate. Terminate all devices.

**Notes:**

1. It is recommended that the fully qualified file name be used. If the server is remote, the fully qualified file name must be used. If the database resides on the same database partition as the caller, relative paths may be used.
2. Loading data from multiple IXF files is supported if the files are physically separate, but logically one file. It is *not* supported if the files are both logically and physically separate. (Multiple physical files would be considered logically one if they were all created with one invocation of the EXPORT command.)
3. If loading data that resides on a client machine, the data must be in the form of either a fully qualified file or a named pipe.

**INDEXING MODE**

Specifies whether the load utility is to rebuild indexes or to extend them incrementally. Valid values are:

**AUTOSELECT**

The load utility will automatically decide between REBUILD or INCREMENTAL mode.

**REBUILD**

All indexes will be rebuilt. The utility must have sufficient resources to sort all index key parts for both old and appended table data.

## LOAD

### INCREMENTAL

Indexes will be extended with new data. This approach consumes index free space. It only requires enough sort space to append index keys for the inserted records. This method is only supported in cases where the index object is valid and accessible at the start of a load operation (it is, for example, not valid immediately following a load operation in which the DEFERRED mode was specified). If this mode is specified, but not supported due to the state of the index, a warning is returned, and the load operation continues in REBUILD mode. Similarly, if a load restart operation is begun in the load build phase, INCREMENTAL mode is not supported.

Incremental indexing is not supported when all of the following conditions are true:

- The LOAD COPY option is specified (*logretain* or *userexit* is enabled).
- The table resides in a DMS table space.
- The index object resides in a table space that is shared by other table objects belonging to the table being loaded.

To bypass this restriction, it is recommended that indexes be placed in a separate table space.

### DEFERRED

The load utility will not attempt index creation if this mode is specified. Indexes will be marked as needing a refresh. The first access to such indexes that is unrelated to a load operation may force a rebuild, or indexes may be rebuilt when the database is restarted. This approach requires enough sort space for all key parts for the largest index. The total time subsequently taken for index construction is longer than that required in REBUILD mode. Therefore, when performing multiple load operations with deferred indexing, it is advisable (from a performance viewpoint) to let the last load operation in the sequence perform an index rebuild, rather than allow indexes to be rebuilt at first non-load access.

Deferred indexing is only supported for tables with non-unique indexes, so that duplicate keys inserted during the load phase are not persistent after the load operation.

**Note:** Deferred indexing is not supported for tables that have DATALINK columns.

### INSERT

One of four modes under which the load utility can execute. Adds the loaded data to the table without changing the existing table data.

#### insert-column

Specifies the table column into which the data is to be inserted.

The load utility cannot parse columns whose names contain one or more spaces. For example,

```
db2 load from delfile1 of del modified by noeofchar noheader
method P (1, 2, 3, 4, 5, 6, 7, 8, 9)
insert into table1 (BLOB1, S2, I3, Int 4, I5, I6, DT7, I8, TM9)
```

will fail because of the Int 4 column. The solution is to enclose such column names with double quotation marks:

```
db2 load from delfile1 of del modified by noeofchar noheader
method P (1, 2, 3, 4, 5, 6, 7, 8, 9)
insert into table1 (BLOB1, S2, I3, "Int 4", I5, I6, DT7, I8, TM9)
```

**INTO table-name**

Specifies the database table into which the data is to be loaded. This table cannot be a system table or a declared temporary table. An alias, or the fully qualified or unqualified table name can be specified. A qualified table name is in the form *schema.tablename*. If an unqualified table name is specified, the table will be qualified with the CURRENT SCHEMA.

**LOBS FROM lob-path**

The path to the data files containing LOB values to be loaded. The path must end with a slash (/). If the CLIENT option is specified, the path must be fully qualified. The names of the LOB data files are stored in the main data file (ASC, DEL, or IXF), in the column that will be loaded into the LOB column. This option is ignored if lobsinfile is not specified within the *filetype-mod* string.

This option is not supported in conjunction with the CURSOR filetype.

**LOCK WITH FORCE**

2 The utility acquires various locks including table locks in the process of  
 2 loading. Rather than wait, and possibly timeout, when acquiring a lock,  
 2 this option allows load to force off other applications that hold conflicting  
 2 locks on the target table. Applications holding conflicting locks on the  
 2 system catalog tables will not be forced off by the load utility. Forced  
 2 applications will roll back and release the locks the load utility needs. The  
 2 load utility can then proceed. This option requires the same authority as  
 2 the FORCE APPLICATIONS command (SYSADM or SYSCTRL).

2 ALLOW NO ACCESS loads may force applications holding conflicting  
 2 locks at the start of the load operation. At the start of the load the utility  
 2 may force applications that are attempting to either query or modify the  
 2 table.

2 ALLOW READ ACCESS loads may force applications holding conflicting  
 2 locks at the start or end of the load operation. At the start of the load the  
 2 load utility may force applications that are attempting to modify the table.  
 2 At the end of the load the load utility may force applications that are  
 2 attempting to either query or modify the table.

**MESSAGES message-file**

Specifies the destination for warning and error messages that occur during the load operation. If a message file is not specified, messages are written to standard output. If the complete path to the file is not specified, the load utility uses the current directory and the default drive as the destination. If the name of a file that already exists is specified, the utility appends the information.

The message file is usually populated with messages at the end of the load operation and, as such, is not suitable for monitoring the progress of the operation.

**METHOD**

L Specifies the start and end column numbers from which to load data. A column number is a byte offset from the beginning of a row of data. It is numbered starting from 1.

## LOAD

**Note:** This method can only be used with ASC files, and is the only valid method for that file type.

**N** Specifies the names of the columns in the data file to be loaded. The case of these column names must match the case of the corresponding names in the system catalogs. Each table column that is not nullable should have a corresponding entry in the METHOD N list. For example, given data fields F1, F2, F3, F4, F5, and F6, and table columns C1 INT, C2 INT NOT NULL, C3 INT NOT NULL, and C4 INT, method N (F2, F1, F4, F3) is a valid request, while method N (F2, F1) is not valid.

**Note:** This method can only be used with file types IXF or CURSOR.

**P** Specifies the field numbers (numbered from 1) of the input data fields to be loaded. Each table column that is not nullable should have a corresponding entry in the METHOD P list. For example, given data fields F1, F2, F3, F4, F5, and F6, and table columns C1 INT, C2 INT NOT NULL, C3 INT NOT NULL, and C4 INT, method P (2, 1, 4, 3) is a valid request, while method P (2, 1) is not valid.

**Note:** This method can only be used with file types IXF, DEL, or CURSOR, and is the only valid method for the DEL file type.

### **MODIFIED BY filetype-mod**

Specifies file type modifier options. See File type modifiers for load.

### **NONRECOVERABLE**

Specifies that the load transaction is to be marked as non-recoverable and that it will not be possible to recover it by a subsequent roll forward action. The roll forward utility will skip the transaction and will mark the table into which data was being loaded as "invalid". The utility will also ignore any subsequent transactions against that table. After the roll forward operation is completed, such a table can only be dropped or restored from a backup (full or table space) taken after a commit point following the completion of the non-recoverable load operation.

With this option, table spaces are not put in backup pending state following the load operation, and a copy of the loaded data does not have to be made during the load operation.

This option should not be used when DATALINK columns with the FILE LINK CONTROL attribute are present in, or being added to, the table.

### **NULL INDICATORS null-indicator-list**

This option can only be used when the METHOD L parameter is specified; that is, the input file is an ASC file). The null indicator list is a comma-separated list of positive integers specifying the column number of each null indicator field. The column number is the byte offset of the null indicator field from the beginning of a row of data. There must be one entry in the null indicator list for each data field defined in the METHOD L parameter. A column number of zero indicates that the corresponding data field always contains data.

A value of Y in the NULL indicator column specifies that the column data is NULL. Any character *other than* Y in the NULL indicator column

specifies that the column data is not NULL, and that column data specified by the METHOD L option will be loaded.

The NULL indicator character can be changed using the MODIFIED BY option.

### OF filetype

Specifies the format of the data:

- ASC (non-delimited ASCII format)
- DEL (delimited ASCII format)
- IXF (integrated exchange format, PC version), exported from the same or from another DB2 table
- CURSOR (a cursor declared against a SELECT or VALUES statement).

### PARTITIONED DB CONFIG

Allows you to execute a load into a partitioned table. The PARTITIONED DB CONFIG parameter allows you to specify partitioned database-specific configuration options. The partitioned-db-option values may be any of the following:

```

HOSTNAME x
FILE_TRANSFER_CMD x
PART_FILE_LOCATION x
OUTPUT_DBPARTNUMS x
PARTITIONING_DBPARTNUMS x
MODE x
MAX_NUM_PART_AGENTS x
ISOLATE_PART_ERRS x
STATUS_INTERVAL x
PORT_RANGE x
CHECK_TRUNCATION
MAP_FILE_INPUT x
MAP_FILE_OUTPUT x
TRACE x
NEWLINE
DISTFILE x
OMIT_HEADER
RUN_STAT_DBPARTNUM x

```

Detailed descriptions of these options are provided in Partitioned database load configuration options.

### REPLACE

One of four modes under which the load utility can execute. Deletes all existing data from the table, and inserts the loaded data. The table definition and index definitions are not changed. If this option is used when moving data between hierarchies, only the data for an entire hierarchy, not individual subtables, can be replaced.

This option is not supported for tables with DATALINK columns.

### RESTART

One of four modes under which the load utility can execute. Restarts a previously interrupted load operation. The load operation will automatically continue from the last consistency point in the load, build, or delete phase.

### RESTARTCOUNT

Reserved.

### ROWCOUNT n

Specifies the number of *n* physical records in the file to be loaded. Allows a user to load only the first *n* rows in a file.

## LOAD

### SAVECOUNT *n*

Specifies that the load utility is to establish consistency points after every *n* rows. This value is converted to a page count, and rounded up to intervals of the extent size. Since a message is issued at each consistency point, this option should be selected if the load operation will be monitored using LOAD QUERY. If the value of *n* is not sufficiently high, the synchronization of activities performed at each consistency point will impact performance.

The default value is zero, meaning that no consistency points will be established, unless necessary.

This option is not supported in conjunction with the CURSOR filetype.

### SORT BUFFER *buffer-size*

This option specifies a value that overrides the SORTHEAP database configuration parameter during a load operation. It is relevant only when loading tables with indexes and only when the INDEXING MODE parameter is not specified as DEFERRED. The value that is specified cannot exceed the value of SORTHEAP. This parameter is useful for throttling the sort memory that is used when loading tables with many indexes without changing the value of SORTHEAP, which would also affect general query processing.

### STATISTICS USE PROFILE

Instructs load to collect statistics during the load according to the profile defined for this table. This profile must be created before load is executed. The profile is created by the RUNSTATS command. If the profile does not exist and load is instructed to collect statistics according to the profile, a warning is returned and no statistics are collected.

### STATISTICS NO

Specifies that no statistics are to be collected, and that the statistics in the catalogs are not to be altered. This is the default.

### TEMPFILES PATH *temp-pathname*

Specifies the name of the path to be used when creating temporary files during a load operation, and should be fully qualified according to the server database partition.

Temporary files take up file system space. Sometimes, this space requirement is quite substantial. Following is an estimate of how much file system space should be allocated for all temporary files:

- 4 bytes for each duplicate or rejected row containing DATALINK values
- 136 bytes for each message that the load utility generates
- 15KB overhead if the data file contains long field data or LOBs. This quantity can grow significantly if the INSERT option is specified, and there is a large amount of long field or LOB data already in the table.

### TERMINATE

One of four modes under which the load utility can execute. Terminates a previously interrupted load operation, and rolls back the operation to the point in time at which it started, even if consistency points were passed. The states of any table spaces involved in the operation return to normal, and all table objects are made consistent (index objects may be marked as invalid, in which case index rebuild will automatically take place at next access). If the load operation being terminated is a load REPLACE, the table will be truncated to an empty table after the load TERMINATE

operation. If the load operation being terminated is a load INSERT, the table will retain all of its original records after the load TERMINATE operation.

The load terminate option will not remove a backup pending state from table spaces.

**Note:** This option is not supported for tables with DATALINK columns.

#### USING directory

Reserved.

#### WARNINGCOUNT *n*

Stops the load operation after *n* warnings. Set this parameter if no warnings are expected, but verification that the correct file and table are being used is desired. If the load file or the target table is specified incorrectly, the load utility will generate a warning for each row that it attempts to load, which will cause the load to fail. If *n* is zero, or this option is not specified, the load operation will continue regardless of the number of warnings issued. If the load operation is stopped because the threshold of warnings was encountered, another load operation can be started in RESTART mode. The load operation will automatically continue from the last consistency point. Alternatively, another load operation can be initiated in REPLACE mode, starting at the beginning of the input file.

#### WITHOUT PROMPTING

Specifies that the list of data files contains all the files that are to be loaded, and that the devices or directories listed are sufficient for the entire load operation. If a continuation input file is not found, or the copy targets are filled before the load operation finishes, the load operation will fail, and the table will remain in load pending state.

If this option is not specified, and the tape device encounters an end of tape for the copy image, or the last item listed is a tape device, the user is prompted for a new tape on that device.

#### Examples:

##### Example 1

TABLE1 has 5 columns:

- COL1 VARCHAR 20 NOT NULL WITH DEFAULT
- COL2 SMALLINT
- COL3 CHAR 4
- COL4 CHAR 2 NOT NULL WITH DEFAULT
- COL5 CHAR 2 NOT NULL

ASCFILE1 has 6 elements:

- ELE1 positions 01 to 20
- ELE2 positions 21 to 22
- ELE5 positions 23 to 23
- ELE3 positions 24 to 27
- ELE4 positions 28 to 31
- ELE6 positions 32 to 32
- ELE6 positions 33 to 40

## LOAD

Data Records:

```
1...5...10...15...20...25...30...35...40
Test data 1      XXN 123abcdN
Test data 2 and 3  QQY   wxyzN
Test data 4,5 and 6 WWN6789   Y
```

The following command loads the table from the file:

```
db2 load from ascfile1 of asc modified by striptblanks reclen=40
method L (1 20, 21 22, 24 27, 28 31)
null indicators (0,0,23,32)
insert into table1 (col1, col5, col2, col3)
```

### Notes:

1. The specification of `striptblanks` in the `MODIFIED BY` parameter forces the truncation of blanks in `VARCHAR` columns (`COL1`, for example, which is 11, 17 and 19 bytes long, in rows 1, 2 and 3, respectively).
2. The specification of `reclen=40` in the `MODIFIED BY` parameter indicates that there is no new-line character at the end of each input record, and that each record is 40 bytes long. The last 8 bytes are not used to load the table.
3. Since `COL4` is not provided in the input file, it will be inserted into `TABLE1` with its default value (it is defined `NOT NULL WITH DEFAULT`).
4. Positions 23 and 32 are used to indicate whether `COL2` and `COL3` of `TABLE1` will be loaded `NULL` for a given row. If there is a `Y` in the column's null indicator position for a given record, the column will be `NULL`. If there is an `N`, the data values in the column's data positions of the input record (as defined in `L(.....)`) are used as the source of column data for the row. In this example, neither column in row 1 is `NULL`; `COL2` in row 2 is `NULL`; and `COL3` in row 3 is `NULL`.
5. In this example, the `NULL INDICATORS` for `COL1` and `COL5` are specified as 0 (zero), indicating that the data is not nullable.
6. The `NULL INDICATOR` for a given column can be anywhere in the input record, but the position must be specified, and the `Y` or `N` values must be supplied.

### Example 2 (Loading LOBs from Files)

`TABLE1` has 3 columns:

- `COL1 CHAR 4 NOT NULL WITH DEFAULT`
- `LOB1 LOB`
- `LOB2 LOB`

`ASCFILE1` has 3 elements:

- `ELE1` positions 01 to 04
- `ELE2` positions 06 to 13
- `ELE3` positions 15 to 22

The following files reside in either `/u/user1` or `/u/user1/bin`:

- `ASCFILE2` has LOB data
- `ASCFILE3` has LOB data
- `ASCFILE4` has LOB data
- `ASCFILE5` has LOB data
- `ASCFILE6` has LOB data
- `ASCFILE7` has LOB data

Data Records in ASCFILE1:

```
1...5...10...15...20...25...30.
REC1 ASCFILE2 ASCFILE3
REC2 ASCFILE4 ASCFILE5
REC3 ASCFILE6 ASCFILE7
```

The following command loads the table from the file:

```
db2 load from ascfile1 of asc
  lobs from /u/user1, /u/user1/bin
  modified by lobsinfile reclen=22
  method L (1 4, 6 13, 15 22)
  insert into table1
```

#### Notes:

1. The specification of `lobsinfile` in the `MODIFIED BY` parameter tells the loader that all LOB data is to be loaded from files.
2. The specification of `reclen=22` in the `MODIFIED BY` parameter indicates that there is no new-line character at the end of each input record, and that each record is 22 bytes long.
3. LOB data is contained in 6 files, `ASCFILE2` through `ASCFILE7`. Each file contains the data that will be used to load a LOB column for a specific row. The relationship between LOBs and other data is specified in `ASCFILE1`. The first record of this file tells the loader to place `REC1` in `COL1` of row 1. The contents of `ASCFILE2` will be used to load `LOB1` of row 1, and the contents of `ASCFILE3` will be used to load `LOB2` of row 1. Similarly, `ASCFILE4` and `ASCFILE5` will be used to load `LOB1` and `LOB2` of row 2, and `ASCFILE6` and `ASCFILE7` will be used to load the LOBs of row 3.
4. The `LOBS FROM` parameter contains 2 paths that will be searched for the named LOB files when those files are required by the loader.
5. To load LOBs directly from `ASCFILE1` (a non-delimited ASCII file), without the `lobsinfile` modifier, the following rules must be observed:
  - The total length of any record, including LOBs, cannot exceed 32KB.
  - LOB fields in the input records must be of fixed length, and LOB data padded with blanks as necessary.
  - The `striptblanks` modifier must be specified, so that the trailing blanks used to pad LOBs can be removed as the LOBs are inserted into the database.

#### Example 3 (Using Dump Files)

Table `FRIENDS` is defined as:

```
table friends "( c1 INT NOT NULL, c2 INT, c3 CHAR(8) )"
```

If an attempt is made to load the following data records into this table,

```
23, 24, bobby
, 45, john
4,, mary
```

the second row is rejected because the first `INT` is `NULL`, and the column definition specifies `NOT NULL`. Columns which contain initial characters that are not consistent with the `DEL` format will generate an error, and the record will be rejected. Such records can be written to a dump file.

`DEL` data appearing in a column outside of character delimiters is ignored, but does generate a warning. For example:

## LOAD

```
22,34,"bob"  
24,55,"sam" sdf
```

The utility will load "sam" in the third column of the table, and the characters "sdf" will be flagged in a warning. The record is not rejected. Another example:

```
22 3, 34,"bob"
```

The utility will load 22,34,"bob", and generate a warning that some data in column one following the 22 was ignored. The record is not rejected.

### Example 4 (Loading DATALINK Data)

The following command loads the table MOVIE TABLE from the input file delfile1, which has data in the DEL format:

```
db2 load from delfile1 of del  
modified by dldel|  
insert into movietable (actorname, description, url_making_of,  
url_movie) datalink specification (dl_url_default_prefix  
"http://narang"), (dl_url_replace_prefix "http://bomdel"  
dl_url_suffix ".mpeg") for exception excptab
```

#### Notes:

1. The table has four columns:

actorname	VARCHAR(n)
description	VARCHAR(m)
url_making_of	DATALINK (with LINKTYPE URL)
url_movie	DATALINK (with LINKTYPE URL)

2. The DATALINK data in the input file has the vertical bar (|) character as the sub-field delimiter.
3. If any column value for url\_making\_of does not have the prefix character sequence, "http://narang" is used.
4. Each non-NULL column value for url\_movie will get "http://bomdel" as its prefix. Existing values are replaced.
5. Each non-NULL column value for url\_movie will get ".mpeg" appended to the path. For example, if a column value of url\_movie is "http://server1/x/y/z", it will be stored as "http://bomdel/x/y/z.mpeg"; if the value is "/x/y/z", it will be stored as "http://bomdel/x/y/z.mpeg".
6. If any unique index or DATALINK exception occurs while loading the table, the affected records are deleted from the table and put into the exception table excptab.

### Example 5 (Loading a Table with an Identity Column)

TABLE1 has 4 columns:

- C1 VARCHAR(30)
- C2 INT GENERATED BY DEFAULT AS IDENTITY
- C3 DECIMAL(7,2)
- C4 CHAR(1)

TABLE2 is the same as TABLE1, except that C2 is a GENERATED ALWAYS identity column.

Data records in DATAFILE1 (DEL format):

```
"Liszt"
"Hummel",,187.43, H
"Grieg",100, 66.34, G
"Satie",101, 818.23, I
```

Data records in DATAFILE2 (DEL format):

```
"Liszt", 74.49, A
"Hummel", 0.01, H
"Grieg", 66.34, G
"Satie", 818.23, I
```

#### Notes:

1. The following command generates identity values for rows 1 and 2, since no identity values are supplied in DATAFILE1 for those rows. Rows 3 and 4, however, are assigned the user-supplied identity values of 100 and 101, respectively.
 

```
db2 load from datafile1.del of del replace into table1
```
2. To load DATAFILE1 into TABLE1 so that identity values are generated for all rows, issue one of the following commands:
 

```
db2 load from datafile1.del of del method P(1, 3, 4)
  replace into table1 (c1, c3, c4)
db2load from datafile1.del of del modified by identityignore
  replace into table1
```
3. To load DATAFILE2 into TABLE1 so that identity values are generated for each row, issue one of the following commands:
 

```
db2 load from datafile2.del of del replace into table1 (c1, c3, c4)
db2 load from datafile2.del of del modified by identitymissing
  replace into table1
```
4. To load DATAFILE1 into TABLE2 so that the identity values of 100 and 101 are assigned to rows 3 and 4, issue the following command:
 

```
db2 load from datafile1.del of del modified by identityoverride
  replace into table2
```

In this case, rows 1 and 2 will be rejected, because the utility has been instructed to override system-generated identity values in favor of user-supplied values. If user-supplied values are not present, however, the row must be rejected, because identity columns are implicitly not NULL.

5. If DATAFILE1 is loaded into TABLE2 without using any of the identity-related file type modifiers, rows 1 and 2 will be loaded, but rows 3 and 4 will be rejected, because they supply their own non-NULL values, and the identity column is GENERATED ALWAYS.

#### Example 6 (Loading using the CURSOR filetype)

Table ABC.TABLE1 has 3 columns:

```
ONE INT
TWO CHAR(10)
THREE DATE
```

Table ABC.TABLE2 has 3 columns:

```
ONE VARCHAR
TWO INT
THREE DATE
```

Executing the following commands will load all the data from ABC.TABLE1 into ABC.TABLE2:

## LOAD

```
db2 declare mycurs cursor for select two,one,three from abc.table1
db2 load from mycurs of cursor insert into abc.table2
```

### Usage notes:

Data is loaded in the sequence that appears in the input file. If a particular sequence is desired, the data should be sorted before a load is attempted.

The load utility builds indexes based on existing definitions. The exception tables are used to handle duplicates on unique keys. The utility does not enforce referential integrity, perform constraints checking, or update summary tables that are dependent on the tables being loaded. Tables that include referential or check constraints are placed in check pending state. Summary tables that are defined with REFRESH IMMEDIATE, and that are dependent on tables being loaded, are also placed in check pending state. Issue the SET INTEGRITY statement to take the tables out of check pending state. Load operations cannot be carried out on replicated summary tables.

If a clustering index exists on the table, the data should be sorted on the clustering index prior to loading. Data does not need to be sorted prior to loading into a multidimensional clustering (MDC) table, however.

### DB2 Data Links Manager considerations:

For each DATALINK column, there can be one column specification within parentheses. Each column specification consists of one or more of DL\_LINKTYPE, *prefix* and a DL\_URL\_SUFFIX specification. The *prefix* information can be either DL\_URL\_REPLACE\_PREFIX, or the DL\_URL\_DEFAULT\_PREFIX specification.

There can be as many DATALINK column specifications as the number of DATALINK columns defined in the table. The order of specifications follows the order of DATALINK columns as found within the insert-column list (if specified by INSERT INTO (insert-column, ...)), or within the table definition (if insert-column is not specified).

For example, if a table has columns C1, C2, C3, C4, and C5, and among them only columns C2 and C5 are of type DATALINK, and the insert-column list is (C1, C5, C3, C2), there should be two DATALINK column specifications. The first column specification will be for C5, and the second column specification will be for C2. If an insert-column list is not specified, the first column specification will be for C2, and the second column specification will be for C5.

If there are multiple DATALINK columns, and some columns do not need any particular specification, the column specification should have at least the parentheses to unambiguously identify the order of specifications. If there are no specifications for any of the columns, the entire list of empty parentheses can be dropped. Thus, in cases where the defaults are satisfactory, there need not be any DATALINK specification.

If data is being loaded into a table with a DATALINK column that is defined with FILE LINK CONTROL, perform the following steps before invoking the load utility. (If all the DATALINK columns are defined with NO LINK CONTROL, these steps are not necessary).

1. Ensure that the DB2 Data Links Manager is installed on the Data Links servers that will be referred to by the DATALINK column values.
2. Ensure that the database is registered with the DB2 Data Links Manager.

3. Copy to the appropriate Data Links servers, all files that will be inserted as DATALINK values.
4. Define the prefix name (or names) to the DB2 Data Links Managers on the Data Links servers.
5. Register the Data Links servers referred to by DATALINK data (to be loaded) in the DB2 Data Links Manager configuration file.

The connection between DB2 and the Data Links server may fail while running the load utility, causing the load operation to fail. If this occurs:


1. Start the Data Links server and the DB2 Data Links Manager.
2. Invoke a load restart operation.

Links that fail during the load operation are considered to be data integrity violations, and are handled in much the same way as unique index violations. Consequently, a special exception has been defined for loading tables that have one or more DATALINK columns.

### Representation of DATALINK information in an input file

The LINKTYPE (currently only URL is supported) is not specified as part of DATALINK information. The LINKTYPE is specified in the LOAD or the IMPORT command, and for input files of type PC/IXF, in the appropriate column descriptor records.

The syntax of DATALINK information for a URL LINKTYPE is as follows:



Note that both *urlname* and *comment* are optional. If neither is provided, the NULL value is assigned.

#### urlname

The URL name must conform to valid URL syntax.

#### Notes:

1. Currently "http", "file", and "unc" are permitted as a schema name.
2. The prefix (schema, host, and port) of the URL name is optional. If a prefix is not present, it is taken from the DL\_URL\_DEFAULT\_PREFIX or the DL\_URL\_REPLACE\_PREFIX specification of the load or the import utility. If none of these is specified, the prefix defaults to "file://localhost". Thus, in the case of local files, the file name with full path name can be entered as the URL name, without the need for a DATALINK column specification within the LOAD or the IMPORT command.
3. Prefixes, even if present in URL names, are overridden by a different prefix name on the DL\_URL\_REPLACE\_PREFIX specification during a load or import operation.
4. The "path" (after appending DL\_URL\_SUFFIX, if specified) is the full path name of the remote file in the remote server. Relative path names are not allowed. The http server default path-prefix is not taken into account.

## LOAD

### **dl\_delimiter**

For the delimited ASCII (DEL) file format, a character specified via the `d|del` modifier, or defaulted to on the LOAD or the IMPORT command. For the non-delimited ASCII (ASC) file format, this should correspond to the character sequence `\;` (a backslash followed by a semicolon). Whitespace characters (blanks, tabs, and so on) are permitted before and after the value specified for this parameter.

### **comment**

The comment portion of a DATALINK value. If specified for the delimited ASCII (DEL) file format, the *comment* text must be enclosed by the character string delimiter, which is double quotation marks (") by default. This character string delimiter can be overridden by the MODIFIED BY *filetype-mod* specification of the LOAD or the IMPORT command.

If no comment is specified, the comment defaults to a string of length zero.

Following are DATALINK data examples for the delimited ASCII (DEL) file format:

- `http://www.almaden.ibm.com:80/mrep/intro.mpeg; "Intro Movie"`

This is stored with the following parts:

- scheme = http
- server = www.almaden.ibm.com
- path = /mrep/intro.mpeg
- comment = "Intro Movie"

- `file://narang/u/narang; "InderPal's Home Page"`

This is stored with the following parts:

- scheme = file
- server = narang
- path = /u/narang
- comment = "InderPal's Home Page"

Following are DATALINK data examples for the non-delimited ASCII (ASC) file format:

- `http://www.almaden.ibm.com:80/mrep/intro.mpeg\;Intro Movie`

This is stored with the following parts:

- scheme = http
- server = www.almaden.ibm.com
- path = /mrep/intro.mpeg
- comment = "Intro Movie"

- `file://narang/u/narang\; InderPal's Home Page`

This is stored with the following parts:

- scheme = file
- server = narang
- path = /u/narang
- comment = "InderPal's Home Page"

Following are DATALINK data examples in which the load or import specification for the column is assumed to be `DL_URL_REPLACE_PREFIX` ("http://qso"):

- `http://www.almaden.ibm.com/mrep/intro.mpeg`

This is stored with the following parts:

- schema = http
- server = qso
- path = /mrep/intro.mpeg
- comment = NULL string
- /u/me/myfile.ps
  - This is stored with the following parts:
    - schema = http
    - server = qso
    - path = /u/me/myfile.ps
    - comment = NULL string

**Related concepts:**

- “Load Overview” on page 74
- “Privileges, authorities, and authorizations required to use Load” on page 81

**Related tasks:**

- “Using Load” on page 81

**Related reference:**

- “QUIESCE TABLESPACES FOR TABLE Command” in the *Command Reference*
- “db2atld - Autoloader Command” in the *Command Reference*
- “Load - CLP Examples” on page 171
- “Partitioned database load configuration options” on page 187
- “db2Load - Load” on page 123
- “File type modifiers for load” on page 149

---

## LOAD QUERY

Checks the status of a load operation during processing and returns the table state. If a load is not processing, then the table state alone is returned. A connection to the same database, and a separate CLP session are also required to successfully invoke this command. It can be used either by local or remote users.

**Authorization:**

None

**Required connection:**

Database

**Command syntax:**

```

▶▶—LOAD QUERY—TABLE—table-name—┬──TO—local-message-file—┘
└──┬──NOSUMMARY—┘
   └──SUMMARYONLY—┘
▶▶—┬──SHOWDELTA—┘

```

**Command parameters:**

## LOAD QUERY

### NOSUMMARY

Specifies that no load summary information (rows read, rows skipped, rows loaded, rows rejected, rows deleted, rows committed, and number of warnings) is to be reported.

### SHOWDELTA

Specifies that only new information (pertaining to load events that have occurred since the last invocation of the LOAD QUERY command) is to be reported.

### SUMMARYONLY

Specifies that only load summary information is to be reported.

### TABLE *table-name*

Specifies the name of the table into which data is currently being loaded. If an unqualified table name is specified, the table will be qualified with the CURRENT SCHEMA.

### TO *local-message-file*

Specifies the destination for warning and error messages that occur during the load operation. This file cannot be the *message-file* specified for the LOAD command. If the file already exists, all messages that the load utility has generated are appended to it.

### Examples:

A user loading a large amount of data into the STAFF table wants to check the status of the load operation. The user can specify:

```
db2 connect to <database>
db2 load query table staff to /u/mydir/staff.tempmsg
```

The output file /u/mydir/staff.tempmsg might look like the following:

```
SQL3501W The table space(s) in which the table resides will not be placed in
backup pending state since forward recovery is disabled for the database.
```

```
SQL3109N The utility is beginning to load data from file
"/u/mydir/data/staffbig.del"
```

```
SQL3500W The utility is beginning the "LOAD" phase at time "03-21-2002
11:31:16.597045".
```

```
SQL3519W Begin Load Consistency Point. Input record count = "0".
```

```
SQL3520W Load Consistency Point was successful.
```

```
SQL3519W Begin Load Consistency Point. Input record count = "104416".
```

```
SQL3520W Load Consistency Point was successful.
```

```
SQL3519W Begin Load Consistency Point. Input record count = "205757".
```

```
SQL3520W Load Consistency Point was successful.
```

```
SQL3519W Begin Load Consistency Point. Input record count = "307098".
```

```
SQL3520W Load Consistency Point was successful.
```

```
SQL3519W Begin Load Consistency Point. Input record count = "408439".
```

```
SQL3520W Load Consistency Point was successful.
```

```
SQL3532I The Load utility is currently in the "LOAD" phase.
```

```

Number of rows read      = 453376
Number of rows skipped  = 0
Number of rows loaded   = 453376
Number of rows rejected = 0
Number of rows deleted  = 0
Number of rows committed = 408439
Number of warnings      = 0

```

```

Tablestate:
  Load in Progress

```

### Usage Notes:

In addition to locks, the load utility uses table states to control access to the table. The LOAD QUERY command can be used to determine the table state; LOAD QUERY may be used on tables that are not currently being loaded. The table states described by LOAD QUERY are described in Table locking, table states and table space states.

The progress of a load operation can also be monitored with the LIST UTILITIES command.

### Related concepts:

- “Load Overview” on page 74
- “Table locking, table states and table space states” on page 162

### Related reference:

- “LOAD” on page 100
- “LIST UTILITIES Command” in the *Command Reference*

---

## db2Load - Load

Loads data into a DB2 table. Data residing on the server may be in the form of a file, cursor, tape, or named pipe. Data residing on a remotely connected client may be in the form of a fully qualified file, a cursor, or named pipe. The load utility does not support loading data at the hierarchy level.

### Authorization:

One of the following:

- *sysadm*
- *dbadm*
- load authority on the database and
  - INSERT privilege on the table when the load utility is invoked in INSERT mode, TERMINATE mode (to terminate a previous load insert operation), or RESTART mode (to restart a previous load insert operation)
  - INSERT and DELETE privilege on the table when the load utility is invoked in REPLACE mode, TERMINATE mode (to terminate a previous load replace operation), or RESTART mode (to restart a previous load replace operation)
  - INSERT privilege on the exception table, if such a table is used as part of the load operation.

**Note:** In general, all load processes and all DB2 server processes are owned by the instance owner. All of these processes use the identification of the instance

## db2Load - Load

owner to access needed files. Therefore, the instance owner must have read access to the input files, regardless of who invokes the command.

### Required connection:

Database. If implicit connect is enabled, a connection to the default database is established.

Instance. An explicit attachment is not required. If a connection to the database has been established, an implicit attachment to the local instance is attempted.

### API include file:

*db2ApiDf.h*

### C API syntax:

```
/* File: db2ApiDf.h */
/* API: Load */
/* ... */
SQL_API_RC SQL_API_FN
db2Load (
    db2UInt32 versionNumber,
    void * pParmStruct,
    struct sqlca * pSqlca);

typedef SQL_STRUCTURE db2LoadStruct
{
    struct sqlu_media_list *piSourceList;
    struct sqlu_media_list *piLobPathList;
    struct sqldcol *piDataDescriptor;
    struct sqlchar *piActionString;
    char *piFileType;
    struct sqlchar *piFileTypeMod;
    char *piLocalMsgFileName;
    char *piTempFilesPath;
    struct sqlu_media_list *piVendorSortWorkPaths;
    struct sqlu_media_list *piCopyTargetList;
    db2int32 *piNullIndicators;
    struct db2LoadIn *piLoadInfoIn;
    struct db2LoadOut *poLoadInfoOut;
    struct db2PartLoadIn *piPartLoadInfoIn;
    struct db2PartLoadOut *poPartLoadInfoOut;
    db2int16 iCallerAction;
} db2LoadStruct;

typedef SQL_STRUCTURE db2LoadIn
{
    db2UInt64 iRowcount;
    db2UInt64 iRestartcount;
    char *piUseTablespace;
    db2UInt32 iSavecount;
    db2UInt32 iDataBufferSize;
    db2UInt32 iSortBufferSize;
    db2UInt32 iWarningcount;
    db2UInt16 iHoldQuiesce;
    db2UInt16 iCpuParallelism;
    db2UInt16 iDiskParallelism;
    db2UInt16 iNonrecoverable;
    db2UInt16 iIndexingMode;
    db2UInt16 iAccessLevel;
    db2UInt16 iLockWithForce;
    db2UInt16 iCheckPending;
    char iRestartphase;
    char iStatsOpt;
```

```

} db2LoadIn;

typedef SQL_STRUCTURE db2LoadOut
{
    db2UInt64                oRowsRead;
    db2UInt64                oRowsSkipped;
    db2UInt64                oRowsLoaded;
    db2UInt64                oRowsRejected;
    db2UInt64                oRowsDeleted;
    db2UInt64                oRowsCommitted;
} db2LoadOut;

typedef SQL_STRUCTURE db2PartLoadIn
{
    char                    *piHostname;
    char                    *piFileTransferCmd;
    char                    *piPartFileLocation;
    struct db2LoadNodeList *piOutputNodes;
    struct db2LoadNodeList *piPartitioningNodes;
    db2UInt16               *piMode;
    db2UInt16               *piMaxNumPartAgents;
    db2UInt16               *piIsolatePartErrs;
    db2UInt16               *piStatusInterval;
    struct db2LoadPortRange *piPortRange;
    db2UInt16               *piCheckTruncation;
    char                    *piMapFileInput;
    char                    *piMapFileOutput;
    db2UInt16               *piTrace;
    db2UInt16               *piNewline;
    char                    *piDistfile;
    db2UInt16               *piOmitHeader;
    SQL_PDB_NODE_TYPE       *piRunStatDBPartNum;
} db2PartLoadIn;

typedef SQL_STRUCTURE db2LoadNodeList
{
    SQL_PDB_NODE_TYPE       *piNodeList;
    db2UInt16               iNumNodes;
} db2LoadNodeList;

typedef SQL_STRUCTURE db2LoadPortRange
{
    db2UInt16               iPortMin;
    db2UInt16               iPortMax;
} db2LoadPortRange;

typedef SQL_STRUCTURE db2PartLoadOut
{
    db2UInt64                oRowsRdPartAgents;
    db2UInt64                oRowsRejPartAgents;
    db2UInt64                oRowsPartitioned;
    struct db2LoadAgentInfo *poAgentInfoList;
    db2UInt32                iMaxAgentInfoEntries;
    db2UInt32                oNumAgentInfoEntries;
} db2PartLoadOut;

typedef SQL_STRUCTURE db2LoadAgentInfo
{
    db2int32                 oSqlcode;
    db2UInt32                oTableState;
    SQL_PDB_NODE_TYPE       oNodeNum;
    db2UInt16               oAgentType;
} db2LoadAgentInfo;
/* ... */

```

**Generic API syntax:**

## db2Load - Load

```
/* File: db2ApiDf.h */
/* API: Load */
/* ... */
SQL_API_RC SQL_API_FN
db2gLoad (
    db2UInt32 versionNumber,
    void * pParmStruct,
    struct sqlca * pSqlca);

typedef SQL_STRUCTURE db2gLoadStruct
{
    struct sqlu_media_list *piSourceList;
    struct sqlu_media_list *piLobPathList;
    struct sqldcol *piDataDescriptor;
    struct sqlchar *piActionString;
    char *piFileType;
    struct sqlchar *piFileTypeMod;
    char *piLocalMsgFileName;
    char *piTempFilesPath;
    struct sqlu_media_list *piVendorSortWorkPaths;
    struct sqlu_media_list *piCopyTargetList;
    db2int32 *piNullIndicators;
    struct db2gLoadIn *piLoadInfoIn;
    struct db2LoadOut *poLoadInfoOut;
    struct db2gPartLoadIn *piPartLoadInfoIn;
    struct db2PartLoadOut *poPartLoadInfoOut;
    db2int16 iCallerAction;
    db2UInt16 iFileTypeLen;
    db2UInt16 iLocalMsgFileLen;
    db2UInt16 iTempFilesPathLen;
} db2gLoadStruct;

typedef SQL_STRUCTURE db2gLoadIn
{
    db2UInt64 iRowcount;
    db2UInt64 iRestartcount;
    char *piUseTablespace;
    db2UInt32 iSavecount;
    db2UInt32 iDataBufferSize;
    db2UInt32 iSortBufferSize;
    db2UInt32 iWarningcount;
    db2UInt16 iHoldQuiesce;
    db2UInt16 iCpuParallelism;
    db2UInt16 iDiskParallelism;
    db2UInt16 iNonrecoverable;
    db2UInt16 iIndexingMode;
    db2UInt16 iAccessLevel;
    db2UInt16 iLockWithForce;
    db2UInt16 iCheckPending;
    char iRestartphase;
    char iStatsOpt;
    db2UInt16 iUseTablespaceLen;
} db2gLoadIn;

typedef SQL_STRUCTURE db2LoadOut
{
    db2UInt64 oRowsRead;
    db2UInt64 oRowsSkipped;
    db2UInt64 oRowsLoaded;
    db2UInt64 oRowsRejected;
    db2UInt64 oRowsDeleted;
    db2UInt64 oRowsCommitted;
} db2LoadOut;

typedef SQL_STRUCTURE db2gPartLoadIn
{
    char *piHostname;
```

```

char                *piFileTransferCmd;
char                *piPartFileLocation;
struct db2LoadNodeList *piOutputNodes;
struct db2LoadNodeList *piPartitioningNodes;
db2UInt16          *piMode;
db2UInt16          *piMaxNumPartAgents;
db2UInt16          *piIsolatePartErrs;
db2UInt16          *piStatusInterval;
struct db2LoadPortRange *piPortRange;
db2UInt16          *piCheckTruncation;
char                *piMapFileInput;
char                *piMapFileOutput;
db2UInt16          *piTrace;
db2UInt16          *piNewline;
char                *piDistfile;
db2UInt16          *piOmitHeader;
SQL_PDB_NODE_TYPE *piRunStatDBPartNum;
db2UInt16          iHostnameLen;
db2UInt16          iFileTransferLen;
db2UInt16          iPartFileLocLen;
db2UInt16          iMapFileInputLen;
db2UInt16          iMapFileOutputLen;
db2UInt16          iDistfileLen;
} db2gPartLoadIn;

typedef SQL_STRUCTURE db2LoadNodeList
{
    SQL_PDB_NODE_TYPE *piNodeList;
    db2UInt16          iNumNodes;
} db2LoadNodeList;

typedef SQL_STRUCTURE db2LoadPortRange
{
    db2UInt16          iPortMin;
    db2UInt16          iPortMax;
} db2LoadPortRange;

typedef SQL_STRUCTURE db2PartLoadOut
{
    db2UInt64          oRowsRdPartAgents;
    db2UInt64          oRowsRejPartAgents;
    db2UInt64          oRowsPartitioned;
    struct db2LoadAgentInfo *poAgentInfoList;
    db2UInt32          iMaxAgentInfoEntries;
    db2UInt32          oNumAgentInfoEntries;
} db2PartLoadOut;

typedef SQL_STRUCTURE db2LoadAgentInfo
{
    db2int32           oSqlcode;
    db2UInt32          oTableState;
    SQL_PDB_NODE_TYPE oNodeNum;
    db2UInt16          oAgentType;
} db2LoadAgentInfo;
/* ... */

```

**API parameters:****versionNumber**

Input. Specifies the version and release level of the structure passed as the second parameter *pParmStruct*.

**pParmStruct**

Input. A pointer to the *db2LoadStruct* structure.

**pSqlca**

Output. A pointer to the *sqlca* structure.

**piSourceList**

Input. A pointer to an *sqlu\_media\_list* structure used to provide a list of source files, devices, vendors, pipes, or SQL statements.

The information provided in this structure depends on the value of the *media\_type* field. Valid values (defined in `sqlutil`) are:

**SQLU\_SQL\_STMT**

If the *media\_type* field is set to this value, the caller provides an SQL query through the *pStatement* field of the target field. The *pStatement* field is of type *sqlu\_statement\_entry*. The *sessions* field must be set to the value of 1, since the load utility only accepts a single SQL query per load.

**SQLU\_SERVER\_LOCATION**

If the *media\_type* field is set to this value, the caller provides information through *sqlu\_location\_entry* structures. The *sessions* field indicates the number of *sqlu\_location\_entry* structures provided. This is used for files, devices, and named pipes.

**SQLU\_CLIENT\_LOCATION**

If the *media\_type* field is set to this value, the caller provides information through *sqlu\_location\_entry* structures. The *sessions* field indicates the number of *sqlu\_location\_entry* structures provided. This is used for fully qualified files and named pipes. Note that this *media\_type* is only valid if the API is being called via a remotely connected client.

**SQLU\_TSM\_MEDIA**

If the *media\_type* field is set to this value, the *sqlu\_vendor* structure is used, where *filename* is the unique identifier for the data to be loaded. There should only be one *sqlu\_vendor* entry, regardless of the value of *sessions*. The *sessions* field indicates the number of TSM sessions to initiate. The load utility will start the sessions with different sequence numbers, but with the same data in the one *sqlu\_vendor* entry.

**SQLU\_OTHER\_MEDIA**

If the *media\_type* field is set to this value, the *sqlu\_vendor* structure is used, where *shr\_lib* is the shared library name, and *filename* is the unique identifier for the data to be loaded. There should only be one *sqlu\_vendor* entry, regardless of the value of *sessions*. The *sessions* field indicates the number of other vendor sessions to initiate. The load utility will start the sessions with different sequence numbers, but with the same data in the one *sqlu\_vendor* entry.

**piLobPathList**

Input. A pointer to an *sqlu\_media\_list* structure. For IXF, ASC, and DEL file types, a list of fully qualified paths or devices to identify the location of the individual LOB files to be loaded. The file names are found in the IXF, ASC, or DEL files, and are appended to the paths provided.

The information provided in this structure depends on the value of the *media\_type* field. Valid values (defined in `sqlutil`) are:

**SQLU\_LOCAL\_MEDIA**

If set to this value, the caller provides information through *sqlu\_media\_entry* structures. The *sessions* field indicates the number of *sqlu\_media\_entry* structures provided.

**SQLU\_TSM\_MEDIA**

If set to this value, the *sqlu\_vendor* structure is used, where *filename* is the unique identifier for the data to be loaded. There should only be one *sqlu\_vendor* entry, regardless of the value of *sessions*. The *sessions* field indicates the number of TSM sessions to initiate. The load utility will start the sessions with different sequence numbers, but with the same data in the one *sqlu\_vendor* entry.

**SQLU\_OTHER\_MEDIA**

If set to this value, the *sqlu\_vendor* structure is used, where *shr\_lib* is the shared library name, and *filename* is the unique identifier for the data to be loaded. There should only be one *sqlu\_vendor* entry, regardless of the value of *sessions*. The *sessions* field indicates the number of other vendor sessions to initiate. The load utility will start the sessions with different sequence numbers, but with the same data in the one *sqlu\_vendor* entry.

**piDataDescriptor**

Input. Pointer to an *sqldcol* structure containing information about the columns being selected for loading from the external file.

If the *pFileType* parameter is set to SQL\_ASC, the *dcolmeth* field of this structure must either be set to SQL\_METH\_L or be set to SQL\_METH\_D and specifies a file name with POSITIONSFIL *pFileTypeMod* modifier which contains starting and ending pairs and null indicator positions. The user specifies the start and end locations for each column to be loaded.

If the file type is SQL\_DEL, *dcolmeth* can be either SQL\_METH\_P or SQL\_METH\_D. If it is SQL\_METH\_P, the user must provide the source column position. If it is SQL\_METH\_D, the first column in the file is loaded into the first column of the table, and so on.

If the file type is SQL\_IXF, *dcolmeth* can be one of SQL\_METH\_P, SQL\_METH\_D, or SQL\_METH\_N. The rules for DEL files apply here, except that SQL\_METH\_N indicates that file column names are to be provided in the *sqldcol* structure.

**piActionString**

Input. Pointer to an *sqlchar* structure, followed by an array of characters specifying an action that affects the table.

The character array is of the form:

```
"INSERT|REPLACE|RESTART|TERMINATE
INTO tname [(column_list)]
[DATA LINK SPECIFICATION data link-spec]
[FOR EXCEPTION e_tname]"
```

**INSERT**

Adds the loaded data to the table without changing the existing table data.

**REPLACE**

Deletes all existing data from the table, and inserts the loaded data. The table definition and the index definitions are not changed.

**RESTART**

Restarts a previously interrupted load operation. The load operation will automatically continue from the last consistency point in the load, build, or delete phase.

**TERMINATE**

Terminates a previously interrupted load operation, and rolls back the operation to the point in time at which it started, even if

consistency points were passed. The states of any table spaces involved in the operation return to normal, and all table objects are made consistent (index objects may be marked as invalid, in which case index rebuild will automatically take place at next access). If the table spaces in which the table resides are not in load pending state, this option does not affect the state of the table spaces.

The load terminate option will not remove a backup pending state from table spaces.

*tbname* The name of the table into which the data is to be loaded. The table cannot be a system table or a declared temporary table. An alias, or the fully qualified or unqualified table name can be specified. A qualified table name is in the form *schema.tablename*. If an unqualified table name is specified, the table will be qualified with the CURRENT SCHEMA.

*(column\_list)*

A list of table column names into which the data is to be inserted. The column names must be separated by commas. If a name contains spaces or lowercase characters, it must be enclosed by quotation marks.

**DATALINK SPECIFICATION** *datalink-spec*

Specifies parameters pertaining to DB2 Data Links. These parameters can be specified using the same syntax as in the LOAD command.

**FOR EXCEPTION** *e\_tbname*

Specifies the exception table into which rows in error will be copied. Any row that is in violation of a unique index or a primary key index is copied. DATALINK exceptions are also captured in the exception table.

**piFileType**

Input. A string that indicates the format of the input data source. Supported external formats (defined in `sqlutil`) are:

**SQL\_ASC**

Non-delimited ASCII.

**SQL\_DEL**

Delimited ASCII, for exchange with dBase, BASIC, and the IBM Personal Decision Series programs, and many other database managers and file managers.

**SQL\_IXF**

PC version of the Integrated Exchange Format, the preferred method for exporting data from a table so that it can be loaded later into the same table or into another database manager table.

**SQL\_CURSOR**

An SQL query. The *sqlu\_media\_list* structure passed in through the *piSourceList* parameter is of type `SQLU_SQL_STMT`, and refers to an actual SQL query and not a cursor declared against one.

**piFileTypeMod**

Input. A pointer to the *sqlchar* structure, followed by an array of characters that specify one or more processing options. If this pointer is NULL, or the structure pointed to has zero characters, this action is interpreted as selection of a default specification.

Not all options can be used with all of the supported file types. See File type modifiers for load.

**piLocalMsgFileName**

Input. A string containing the name of a local file to which output messages are to be written.

**piTempFilesPath**

Input. A string containing the path name to be used on the server for temporary files. Temporary files are created to store messages, consistency points, and delete phase information.

**piVendorSortWorkPaths**

Input. A pointer to the *sqlu\_media\_list* structure which specifies the Vendor Sort work directories.

**piCopyTargetList**

Input. A pointer to an *sqlu\_media\_list* structure used (if a copy image is to be created) to provide a list of target paths, devices, or a shared library to which the copy image is to be written.

The values provided in this structure depend on the value of the *media\_type* field. Valid values for this field (defined in *sqlutil*) are:

**SQLU\_LOCAL\_MEDIA**

If the copy is to be written to local media, set the *media\_type* to this value and provide information about the targets in *sqlu\_media\_entry* structures. The *sessions* field specifies the number of *sqlu\_media\_entry* structures provided.

**SQLU\_TSM\_MEDIA**

If the copy is to be written to TSM, use this value. No further information is required.

**SQLU\_OTHER\_MEDIA**

If a vendor product is to be used, use this value and provide further information via an *sqlu\_vendor* structure. Set the *shr\_lib* field of this structure to the shared library name of the vendor product. Provide only one *sqlu\_vendor* entry, regardless of the value of *sessions*. The *sessions* field specifies the number of *sqlu\_media\_entry* structures provided. The load utility will start the sessions with different sequence numbers, but with the same data provided in the one *sqlu\_vendor* entry.

**piNullIndicators**

Input. For ASC files only. An array of integers that indicate whether or not the column data is nullable. There is a one-to-one ordered correspondence between the elements of this array and the columns being loaded from the data file. That is, the number of elements must equal the *dcolnum* field of the *pDataDescriptor* parameter. Each element of the array contains a number identifying a location in the data file that is to be used as a NULL indicator field, or a zero indicating that the table column is not nullable. If the element is not zero, the identified location in the data file must contain a Y or an N. A Y indicates that the table column data is NULL, and N indicates that the table column data is not NULL.

**piLoadInfoIn**

Input. A pointer to the *db2LoadIn* structure.

**poLoadInfoOut**

Input. A pointer to the *db2LoadOut* structure.

## db2Load - Load

### **piPartLoadInfoIn**

Input. A pointer to the *db2PartLoadIn* structure.

### **poPartLoadInfoOut**

Output. A pointer to the *db2PartLoadOut* structure.

### **iCallerAction**

Input. An action requested by the caller. Valid values (defined in *sqlutil*) are:

#### **SQLU\_INITIAL**

Initial call. This value (or **SQLU\_NOINTERRUPT**) must be used on the first call to the API.

#### **SQLU\_NOINTERRUPT**

Initial call. Do not suspend processing. This value (or **SQLU\_INITIAL**) must be used on the first call to the API.

If the initial call or any subsequent call returns and requires the calling application to perform some action prior to completing the requested load operation, the caller action must be set to one of the following:

#### **SQLU\_CONTINUE**

Continue processing. This value can only be used on subsequent calls to the API, after the initial call has returned with the utility requesting user input (for example, to respond to an end of tape condition). It specifies that the user action requested by the utility has completed, and the utility can continue processing the initial request.

#### **SQLU\_TERMINATE**

Terminate processing. Causes the load utility to exit prematurely, leaving the table spaces being loaded in **LOAD\_PENDING** state. This option should be specified if further processing of the data is not to be done.

#### **SQLU\_ABORT**

Terminate processing. Causes the load utility to exit prematurely, leaving the table spaces being loaded in **LOAD\_PENDING** state. This option should be specified if further processing of the data is not to be done.

#### **SQLU\_RESTART**

Restart processing.

#### **SQLU\_DEVICE\_TERMINATE**

Terminate a single device. This option should be specified if the utility is to stop reading data from the device, but further processing of the data is to be done.

### **iFileTypeLen**

Input. Specifies the length in bytes of *iFileType*.

### **iLocalMsgFileLen**

Input. Specifies the length in bytes of *iLocalMsgFileName*.

### **iTempFilesPathLen**

Input. Specifies the length in bytes of *iTempFilesPath*.

### **iRowcount**

Input. The number of physical records to be loaded. Allows a user to load only the first *rowcnt* rows in a file.

**iRestartcount**

Input. Reserved for future use.

**piUseTablespace**

Input. If the indexes are being rebuilt, a shadow copy of the index is built in tablespace *iUseTablespaceName* and copied over to the original tablespace at the end of the load. Only system temporary table spaces can be used with this option. If not specified then the shadow index will be created in the same tablespace as the index object.

If the shadow copy is created in the same tablespace as the index object, the copy of the shadow index object over the old index object is instantaneous. If the shadow copy is in a different tablespace from the index object a physical copy is performed. This could involve considerable I/O and time. The copy happens while the table is offline at the end of a load.

This field is ignored if *iAccessLevel* is `SQLU_ALLOW_NO_ACCESS`.

This option is ignored if the user does not specify `INDEXING MODE REBUILD` or `INDEXING MODE AUTOSELECT`. This option will also be ignored if `INDEXING MODE AUTOSELECT` is chosen and load chooses to incrementally update the index.

**iSavecount**

The number of records to load before establishing a consistency point. This value is converted to a page count, and rounded up to intervals of the extent size. Since a message is issued at each consistency point, this option should be selected if the load operation will be monitored using *db2LoadQuery - Load Query*. If the value of *savecnt* is not sufficiently high, the synchronization of activities performed at each consistency point will impact performance.

The default value is 0, meaning that no consistency points will be established, unless necessary.

**iDataBufferSize**

The number of 4KB pages (regardless of the degree of parallelism) to use as buffered space for transferring data within the utility. If the value specified is less than the algorithmic minimum, the required minimum is used, and no warning is returned.

This memory is allocated directly from the utility heap, whose size can be modified through the *util\_heap\_sz* database configuration parameter.

If a value is not specified, an intelligent default is calculated by the utility at run time. The default is based on a percentage of the free space available in the utility heap at the instantiation time of the loader, as well as some characteristics of the table.

**iSortBufferSize**

Input. This option specifies a value that overrides the SORTHEAP database configuration parameter during a load operation. It is relevant only when loading tables with indexes and only when the *iIndexingMode* parameter is not specified as `SQLU_INX_DEFERRED`. The value that is specified cannot exceed the value of SORTHEAP. This parameter is useful for throttling the sort memory used by LOAD without changing the value of SORTHEAP, which would also affect general query processing.

**iWarningcount**

Input. Stops the load operation after *warningcnt* warnings. Set this

parameter if no warnings are expected, but verification that the correct file and table are being used is desired. If the load file or the target table is specified incorrectly, the load utility will generate a warning for each row that it attempts to load, which will cause the load to fail. If *warningcnt* is 0, or this option is not specified, the load operation will continue regardless of the number of warnings issued.

If the load operation is stopped because the threshold of warnings was exceeded, another load operation can be started in RESTART mode. The load operation will automatically continue from the last consistency point. Alternatively, another load operation can be initiated in REPLACE mode, starting at the beginning of the input file.

### **iHoldQuiesce**

Input. A flag whose value is set to TRUE if the utility is to leave the table in quiesced exclusive state after the load, and to FALSE if it is not.

### **iCpuParallelism**

Input. The number of processes or threads that the load utility will spawn for parsing, converting and formatting records when building table objects. This parameter is designed to exploit intra-partition parallelism. It is particularly useful when loading presorted data, because record order in the source data is preserved. If the value of this parameter is zero, the load utility uses an intelligent default value at run time. Note: If this parameter is used with tables containing either LOB or LONG VARCHAR fields, its value becomes one, regardless of the number of system CPUs, or the value specified by the user.

### **iDiskParallelism**

Input. The number of processes or threads that the load utility will spawn for writing data to the table space containers. If a value is not specified, the utility selects an intelligent default based on the number of table space containers and the characteristics of the table.

### **iNonrecoverable**

Input. Set to `SQLU_NON_RECOVERABLE_LOAD` if the load transaction is to be marked as non-recoverable, and it will not be possible to recover it by a subsequent roll forward action. The rollforward utility will skip the transaction, and will mark the table into which data was being loaded as "invalid". The utility will also ignore any subsequent transactions against that table. After the roll forward is completed, such a table can only be dropped. With this option, table spaces are not put in backup pending state following the load operation, and a copy of the loaded data does not have to be made during the load operation. Set to `SQLU_RECOVERABLE_LOAD` if the load transaction is to be marked as recoverable.

### **iIndexingMode**

Input. Specifies the indexing mode. Valid values (defined in `sqlutil`) are:

#### **SQLU\_INX\_AUTOSELECT**

LOAD chooses between REBUILD and INCREMENTAL indexing modes.

#### **SQLU\_INX\_REBUILD**

Rebuild table indexes.

#### **SQLU\_INX\_INCREMENTAL**

Extend existing indexes.

**SQLU\_INX\_DEFERRED**

Do not update table indexes.

**iAccessLevel**

Input. Specifies the access level. Valid values are:

**SQLU\_ALLOW\_NO\_ACCESS**

Specifies that the load locks the table exclusively.

**SQLU\_ALLOW\_READ\_ACCESS**

Specifies that the original data in the table (the non-delta portion) should still be visible to readers while the load is in progress. This option is only valid for load appends, such as a load insert, and will be ignored for load replace.

**iLockWithForce**

Input. A boolean flag. If set to TRUE load will force other applications as necessary to ensure that it obtains table locks immediately. This option requires the same authority as the FORCE APPLICATIONS command (SYSADM or SYSCTRL).

SQLU\_ALLOW\_NO\_ACCESS loads may force conflicting applications at the start of the load operation. At the start of the load the utility may force applications that are attempting to either query or modify the table.

SQLU\_ALLOW\_READ\_ACCESS loads may force conflicting applications at the start or end of the load operation. At the start of the load the load utility may force applications that are attempting to modify the table. At the end of the load the load utility may force applications that are attempting to either query or modify the table.

**iCheckPending**

Input. Specifies to put the table into check pending state. If SQLU\_CHECK\_PENDING\_CASCADE\_IMMEDIATE is specified, check pending state will be immediately cascaded to all dependent and descendent tables. If SQLU\_CHECK\_PENDING\_CASCADE\_DEFERRED is specified, the cascade of check pending state to dependent tables will be deferred until the target table is checked for integrity violations. SQLU\_CHECK\_PENDING\_CASCADE\_DEFERRED is the default if the option is not specified.

**iRestartphase**

Input. Reserved. Valid value is a single space character ' '.

**iStatsOpt**

Input. Granularity of statistics to collect. Valid values are:

**SQLU\_STATS\_NONE**

No statistics to be gathered.

**SQLU\_STATS\_USE\_PROFILE**

Statistics are collected based on the profile defined for the current table. This profile must be created using the RUNSTATS command. If no profile exists for the current table, a warning is returned and no statistics are collected.

**iUseTablespaceLen**

Input. The length in bytes of *piUseTablespace*.

**oRowsRead**

Output. Number of records read during the load operation.

### **oRowsSkipped**

Output. Number of records skipped before the load operation begins.

### **oRowsLoaded**

Output. Number of rows loaded into the target table.

### **oRowsRejected**

Output. Number of records that could not be loaded.

### **oRowsDeleted**

Output. Number of duplicate rows deleted.

### **oRowsCommitted**

Output. The total number of processed records: the number of records loaded successfully and committed to the database, plus the number of skipped and rejected records.

### **piHostname**

Input. The hostname for the *iFileTransferCmd* parameter. If NULL, the hostname will default to "nohost".

### **piFileTransferCmd**

Input. File transfer command parameter. If not required, it must be set to NULL. See the Data Movement Guide for a full description of this parameter.

### **piPartFileLocation**

Input. In PARTITION\_ONLY, LOAD\_ONLY, and LOAD\_ONLY\_VERIFY\_PART modes, this parameter can be used to specify the location of the partitioned files. This location must exist on each partition specified by the *piOutputNodes* option.

For the SQL\_CURSOR file type, this parameter cannot be NULL and the location does not refer to a path, but to a fully qualified file name. This will be the fully qualified base file name of the partitioned files that are created on each output partition for PARTITION\_ONLY mode, or the location of the files to be read from each partition for LOAD\_ONLY mode. For PARTITION\_ONLY mode, multiple files may be created with the specified base name if there are LOB columns in the target table. For file types other than SQL\_CURSOR, if the value of this parameter is NULL, it will default to the current directory.

### **piOutputNodes**

Input. The list of Load output partitions. A NULL indicates that all nodes on which the target table is defined.

### **piPartitioningNodes**

Input. The list of partitioning nodes. A NULL indicates the default. Refer to the Load command in the Data Movement Guide and Reference for a description of how the default is determined.

### **piMode**

Input. Specifies the load mode for partitioned databases. Valid values (defined in db2ApiDf) are:

#### **DB2LOAD\_PARTITION\_AND\_LOAD**

Data is partitioned (perhaps in parallel) and loaded simultaneously on the corresponding database partitions.

#### **DB2LOAD\_PARTITION\_ONLY**

Data is partitioned (perhaps in parallel) and the output is written to files in a specified location on each loading partition. For file

types other than SQL\_CURSOR, the name of the output file on each partition will have the form filename.xxx, where filename is the name of the first input file specified by *piSourceList* and xxx is the partition number. For the SQL\_CURSOR file type, the name of the output file on each partition will be determined by the *piPartFileLocation* parameter. Refer to the *piPartFileLocation* parameter for information about how to specify the location of the partition file on each partition.

**Note:** This mode cannot be used for a CLI LOAD.

#### DB2LOAD\_LOAD\_ONLY

Data is assumed to be already partitioned; the partition process is skipped, and the data is loaded simultaneously on the corresponding database partitions. For file types other than SQL\_CURSOR, the input file name on each partition is expected to be of the form filename.xxx, where filename is the name of the first file specified by *piSourceList* and xxx is the 3-digit partition number. For the SQL\_CURSOR file type, the name of the input file on each partition will be determined by the *piPartFileLocation* parameter. Refer to the *piPartFileLocation* parameter for information about how to specify the location of the partition file on each partition.

**Note:** This mode cannot be used when loading a data file located on a remote client, nor can it be used for a CLI LOAD.

#### DB2LOAD\_LOAD\_ONLY\_VERIFY\_PART

Data is assumed to be already partitioned, but the data file does not contain a partition header. The partitioning process is skipped, and the data is loaded simultaneously on the corresponding database partitions. During the load operation, each row is checked to verify that it is on the correct partition. Rows containing partition violations are placed in a dumpfile if the dumpfile file type modifier is specified. Otherwise, the rows are discarded. If partition violations exist on a particular loading partition, a single warning will be written to the load message file for that partition. The input file name on each partition is expected to be of the form filename.xxx, where filename is the name of the first file specified by *piSourceList* and xxx is the 3-digit partition number.

**Note:** This mode cannot be used when loading a data file located on a remote client, nor can it be used for a CLI LOAD.

#### DB2LOAD\_ANALYZE

An optimal partitioning map with even distribution across all database partitions is generated.

#### **piMaxNumPartAgents**

Input. The maximum number of partitioning agents. A NULL value indicates the default, which is 25.

#### **piIsolatePartErrs**

Input. Indicates how the load operation will react to errors that occur on individual partitions. Valid values (defined in db2ApiDf) are:

#### DB2LOAD\_SETUP\_ERRS\_ONLY

In this mode, errors that occur on a partition during setup, such as problems accessing a partition or problems accessing a table space

or table on a partition, will cause the load operation to stop on the failing partitions but to continue on the remaining partitions. Errors that occur on a partition while data is being loaded will cause the entire operation to fail and rollback to the last point of consistency on each partition.

### **DB2LOAD\_LOAD\_ERRS\_ONLY**

In this mode, errors that occur on a partition during setup will cause the entire load operation to fail. When an error occurs while data is being loaded, the partitions with errors will be rolled back to their last point of consistency. The load operation will continue on the remaining partitions until a failure occurs or until all the data is loaded. On the partitions where all of the data was loaded, the data will not be visible following the load operation. Because of the errors in the other partitions the transaction will be aborted. Data on all of the partitions will remain invisible until a load restart operation is performed. This will make the newly loaded data visible on the partitions where the load operation completed and resume the load operation on partitions that experienced an error.

**Note:** This mode cannot be used when *iAccessLevel* is set to `SQLU_ALLOW_READ_ACCESS` and a copy target is also specified.

### **DB2LOAD\_SETUP\_AND\_LOAD\_ERRS**

In this mode, partition-level errors during setup or loading data cause processing to stop only on the affected partitions. As with the `DB2LOAD_LOAD_ERRS_ONLY` mode, when partition errors do occur while data is being loaded, the data on all partitions will remain invisible until a load restart operation is performed.

**Note:** This mode cannot be used when *iAccessLevel* is set to `SQLU_ALLOW_READ_ACCESS` and a copy target is also specified.

### **DB2LOAD\_NO\_ISOLATION**

Any error during the Load operation causes the transaction to be aborted.

If this parameter is `NULL`, it will default to `DB2LOAD_LOAD_ERRS_ONLY`, unless *iAccessLevel* is set to `SQLU_ALLOW_READ_ACCESS` and a copy target is also specified, in which case the default is `DB2LOAD_NO_ISOLATION`.

#### **piStatusInterval**

Input. Specifies the number of megabytes (MB) of data to load before generating a progress message. Valid values are whole numbers in the range of 1 to 4000. If `NULL` is specified, a default value of 100 will be used.

#### **piPortRange**

Input. The TCP port range for internal communication. If `NULL`, the port range used will be 6000-6063.

#### **piCheckTruncation**

Input. Causes Load to check for record truncation at Input/Output. Valid values are `TRUE` and `FALSE`. If `NULL`, the default is `FALSE`.

**piMapFileInput**

Input. Partition map input filename. If the mode is not ANALYZE, this parameter should be set to NULL. If the mode is ANALYZE, this parameter must be specified.

**piMapFileOutput**

Input. Partition map output filename. The rules for piMapFileInput apply here as well.

**piTrace**

Input. Specifies the number of records to trace when you need to review a dump of all the data conversion process and the output of hashing values. If NULL, the number of records defaults to 0.

**piNewline**

Input. Forces Load to check for newline characters at end of ASC data records if RECLLEN file type modifier is also specified. Possible values are TRUE and FALSE. If NULL, the value defaults to FALSE.

**piDistfile**

Input. Name of the partition distribution file. If a NULL is specified, the value defaults to "DISTFILE".

**piOmitHeader**

Input. Indicates that a partition map header should not be included in the partition file when using DB2LOAD\_PARTITION\_ONLY mode. Possible values are TRUE and FALSE. If NULL, the default is FALSE.

**piRunStatDBPartNum**

Specifies the database partition on which to collect statistics. The default value is the first database partition in the output partition list.

**iHostnameLen**

Input. The length in bytes of *piHostname*.

**iFileTransferLen**

Input. The length in bytes of *piFileTransferCmd*.

**iPartFileLocLen**

Input. The length in bytes of *piPartFileLocation*.

**iMapFileInputLen**

Input. The length in bytes of *piMapFileInput*.

**iMapFileOutputLen**

Input. The length in bytes of *piMapFileOutput*.

**iDistfileLen**

Input. The length in bytes of *piDistfile*.

**piNodeList**

Input. An array of node numbers.

**iNumNodes**

Input. The number of nodes in the *piNodeList* array. A 0 indicates the default, which is all nodes on which the target table is defined.

**iPortMin**

Input. Lower port number.

**iPortMax**

Input. Higher port number.

### **oRowsRdPartAgents**

Output. Total number of rows read by all partitioning agents.

### **oRowsRejPartAgents**

Output. Total number of rows rejected by all partitioning agents.

### **oRowsPartitioned**

Output. Total number of rows partitioned by all partitioning agents.

### **poAgentInfoList**

Output. During a load operation into a partitioned database, the following load processing entities may be involved: load agents, partitioning agents, pre-partitioning agents, file transfer command agents and load-to-file agents (these are described in the Data Movement Guide). The purpose of the *poAgentInfoList* output parameter is to return to the caller information about each load agent that participated in a load operation. Each entry in the list contains the following information:

- **oAgentType**. A tag indicating what kind of load agent the entry describes.
- **oNodeNum**. The number of the partition on which the agent executed.
- **oSqlcode**. The final sqlcode resulting from the agent's processing.
- **oTableState**. The final status of the table on the partition on which the agent executed (relevant only for load agents).

It is up to the caller of the API to allocate memory for this list prior to calling the API. The caller should also indicate the number of entries for which they allocated memory in the *iMaxAgentInfoEntries* parameter. If the caller sets *poAgentInfoList* to NULL or sets *iMaxAgentInfoEntries* to 0, then no information will be returned about the load agents.

### **iMaxAgentInfoEntries**

Input. The maximum number of agent information entries allocated by the user for *poAgentInfoList*. In general, setting this parameter to 3 times the number of partitions involved in the load operation should be sufficient.

### **oNumAgentInfoEntries**

Output. The actual number of agent information entries produced by the load operation. This number of entries will be returned to the user in the *poAgentInfoList* parameter as long as *iMaxAgentInfoEntries* is greater than or equal to *oNumAgentInfoEntries*. If *iMaxAgentInfoEntries* is less than *oNumAgentInfoEntries*, then the number of entries returned in *poAgentInfoList* is equal to *iMaxAgentInfoEntries*.

### **oSqlcode**

Output. The final sqlcode resulting from the agent's processing.

### **oTableState**

Output. The purpose of this output parameter is not to report every possible state of the table after the load operation. Rather, its purpose is to report only a small subset of possible tablestates in order to give the caller a general idea of what happened to the table during load processing. This value is relevant for load agents only. The possible values are:

#### **DB2LOADQUERY\_NORMAL**

Indicates that the load completed successfully on the partition and the table was taken out of the LOAD IN PROGRESS (or LOAD PENDING) state. In this case, the table still could be in CHECK PENDING state due to the need for further constraints processing, but this will not be reported as this is normal.

**DB2LOADQUERY\_UNCHANGED**

Indicates that the load job aborted processing due to an error but did not yet change the state of the table on the partition from whatever state it was in prior to calling db2Load. It is not necessary to perform a load restart or terminate operation on such partitions.

**DB2LOADQUERY\_LOADPENDING**

Indicates that the load job aborted during processing but left the table on the partition in the LOAD PENDING state, indicating that the load job on that partition must be either terminated or restarted.

**oNodeNum**

Output. The number of the partition on which the agent executed.

**oAgentType**

Output. The agent type. Valid values (defined in db2ApiDf) are :

**DB2LOAD\_LOAD\_AGENT**

**DB2LOAD\_PARTITIONING\_AGENT**

**DB2LOAD\_PRE\_PARTITIONING\_AGENT**

**DB2LOAD\_FILE\_TRANSFER\_AGENT**

**DB2LOAD\_LOAD\_TO\_FILE\_AGENT**

**Usage notes:**

Data is loaded in the sequence that appears in the input file. If a particular sequence is desired, the data should be sorted before a load is attempted.

The load utility builds indexes based on existing definitions. The exception tables are used to handle duplicates on unique keys. The utility does not enforce referential integrity, perform constraints checking, or update summary tables that are dependent on the tables being loaded. Tables that include referential or check constraints are placed in check pending state. Summary tables that are defined with REFRESH IMMEDIATE, and that are dependent on tables being loaded, are also placed in check pending state. Issue the SET INTEGRITY statement to take the tables out of check pending state. Load operations cannot be carried out on replicated summary tables.

For clustering indexes, the data should be sorted on the clustering index prior to loading. The data need not be sorted when loading into an multi-dimensionally clustered (MDC) table.

**DB2 Data Links Manager Considerations**

For each DATALINK column, there can be one column specification within parentheses. Each column specification consists of one or more of DL\_LINKTYPE, *prefix* and a DL\_URL\_SUFFIX specification. The *prefix* information can be either DL\_URL\_REPLACE\_PREFIX, or the DL\_URL\_DEFAULT\_PREFIX specification.

There can be as many DATALINK column specifications as the number of DATALINK columns defined in the table. The order of specifications follows the order of DATALINK columns as found within the insert-column list (if specified by INSERT INTO (insert-column, ...)), or within the table definition (if insert-column is not specified).

For example, if a table has columns C1, C2, C3, C4, and C5, and among them only columns C2 and C5 are of type DATALINK, and the insert-column list is (C1, C5, C3, C2), there should be two DATALINK column specifications. The first column specification will be for C5, and the second column specification will be for C2. If an insert-column list is not specified, the first column specification will be for C2, and the second column specification will be for C5.

If there are multiple DATALINK columns, and some columns do not need any particular specification, the column specification should have at least the parentheses to unambiguously identify the order of specifications. If there are no specifications for any of the columns, the entire list of empty parentheses can be dropped. Thus, in cases where the defaults are satisfactory, there need not be any DATALINK specification.

If data is being loaded into a table with a DATALINK column that is defined with FILE LINK CONTROL, perform the following steps before invoking the load utility. (If all the DATALINK columns are defined with NO LINK CONTROL, these steps are not necessary).

1. Ensure that the DB2 Data Links Manager is installed on the Data Links servers that will be referred to by the DATALINK column values.
2. Ensure that the database is registered with the DB2 Data Links Manager.
3. Copy to the appropriate Data Links servers, all files that will be inserted as DATALINK values.
4. Define the prefix name (or names) to the DB2 Data Links Managers on the Data Links servers.
5. Register the Data Links servers referred to by DATALINK data (to be loaded) in the DB2 Data Links Manager configuration file.

The connection between DB2 and the Data Links server may fail while running the load utility, causing the load operation to fail. If this occurs:


1. Start the Data Links server and the DB2 Data Links Manager.
2. Invoke a load restart operation.

Links that fail during the load operation are considered to be data integrity violations, and are handled in much the same way as unique index violations. Consequently, a special exception has been defined for loading tables that have one or more DATALINK columns.

### Representation of DATALINK Information in an Input File

The LINKTYPE (currently only URL is supported) is not specified as part of DATALINK information. The LINKTYPE is specified in the LOAD or the IMPORT command, and for input files of type PC/IXF, in the appropriate column descriptor records.

The syntax of DATALINK information for a URL LINKTYPE is as follows:



Note that both *urlname* and *comment* are optional. If neither is provided, the NULL value is assigned.

**urlname**

The URL name must conform to valid URL syntax.

**Notes:**

1. Currently "http", "file", and "unc" are permitted as a schema name.
2. The prefix (schema, host, and port) of the URL name is optional. If a prefix is not present, it is taken from the DL\_URL\_DEFAULT\_PREFIX or the DL\_URL\_REPLACE\_PREFIX specification of the load or the import utility. If none of these is specified, the prefix defaults to "file://localhost". Thus, in the case of local files, the file name with full path name can be entered as the URL name, without the need for a DATALINK column specification within the LOAD or the IMPORT command.
3. Prefixes, even if present in URL names, are overridden by a different prefix name on the DL\_URL\_REPLACE\_PREFIX specification during a load or import operation.
4. The "path" (after appending DL\_URL\_SUFFIX, if specified) is the full path name of the remote file in the remote server. Relative path names are not allowed. The http server default path-prefix is not taken into account.

**dl\_delimiter**

For the delimited ASCII (DEL) file format, a character specified via the `dldel` modifier, or defaulted to on the LOAD or the IMPORT command. For the non-delimited ASCII (ASC) file format, this should correspond to the character sequence `\;` (a backslash followed by a semicolon). Whitespace characters (blanks, tabs, and so on) are permitted before and after the value specified for this parameter.

**comment**

The comment portion of a DATALINK value. If specified for the delimited ASCII (DEL) file format, the *comment* text must be enclosed by the character string delimiter, which is double quotation marks (") by default. This character string delimiter can be overridden by the MODIFIED BY *filetype-mod* specification of the LOAD or the IMPORT command.

If no comment is specified, the comment defaults to a string of length zero.

Following are DATALINK data examples for the delimited ASCII (DEL) file format:

- `http://www.almaden.ibm.com:80/mrep/intro.mpeg; "Intro Movie"`

This is stored with the following parts:

- scheme = http
- server = www.almaden.ibm.com
- path = /mrep/intro.mpeg
- comment = "Intro Movie"

- `file://narang/u/narang; "InderPal's Home Page"`

This is stored with the following parts:

- scheme = file
- server = narang
- path = /u/narang
- comment = "InderPal's Home Page"

Following are DATALINK data examples for the non-delimited ASCII (ASC) file format:

## db2Load - Load

- `http://www.almaden.ibm.com:80/mrep/intro.mpeg\;`Intro Movie  
This is stored with the following parts:
  - `scheme = http`
  - `server = www.almaden.ibm.com`
  - `path = /mrep/intro.mpeg`
  - `comment = "Intro Movie"`
- `file://narang/u/narang\;`InderPal's Home Page  
This is stored with the following parts:
  - `scheme = file`
  - `server = narang`
  - `path = /u/narang`
  - `comment = "InderPal's Home Page"`

Following are DATALINK data examples in which the load or import specification for the column is assumed to be `DL_URL_REPLACE_PREFIX` ("`http://qso`"):

- `http://www.almaden.ibm.com/mrep/intro.mpeg`  
This is stored with the following parts:
  - `schema = http`
  - `server = qso`
  - `path = /mrep/intro.mpeg`
  - `comment = NULL string`
- `/u/me/myfile.ps`  
This is stored with the following parts:
  - `schema = http`
  - `server = qso`
  - `path = /u/me/myfile.ps`
  - `comment = NULL string`

### Related reference:

- "sqluvqdp - Quiesce Table Spaces for Table" in the *Administrative API Reference*
- "db2LoadQuery - Load Query" on page 145
- "SQLDCOL" in the *Administrative API Reference*
- "SQLU-MEDIA-LIST" in the *Administrative API Reference*
- "db2Export - Export" on page 12
- "db2Import - Import" on page 48
- "db2DatabaseQuiesce - Database Quiesce" in the *Administrative API Reference*
- "db2InstanceQuiesce - Instance Quiesce" in the *Administrative API Reference*
- "File type modifiers for load" on page 149
- "Delimiter restrictions for moving data" on page 217

### Related samples:

- "dtformat.sqc -- Load and import data format extensions (C)"
- "tbload.sqc -- How to load into a partitioned database (C)"
- "tbmove.sqc -- How to move table data (C)"
- "tbmove.sqC -- How to move table data (C++)"

---

## db2LoadQuery - Load Query

Checks the status of a load operation during processing.

### Authorization:

None

### Required connection:

Database

### API include file:

*db2ApiDf.h*

### C API syntax:

```
/* File: db2ApiDf.h */
/* API: db2LoadQuery */
/* ... */
SQL_API_RC SQL_API_FN
db2LoadQuery (
    db2UInt32 versionNumber,
    void *pParmStruct,
    struct sqlca *pSqlca);
```

```
typedef struct
{
    db2UInt32 iStringType;
    char *piString;
    db2UInt32 iShowLoadMessages;
    db2LoadQueryOutputStruct *poOutputStruct;
    char *piLocalMessageFile;
} db2LoadQueryStruct;
```

```
typedef struct
{
    db2UInt32 oRowsRead;
    db2UInt32 oRowsSkipped;
    db2UInt32 oRowsCommitted;
    db2UInt32 oRowsLoaded;
    db2UInt32 oRowsRejected;
    db2UInt32 oRowsDeleted;
    db2UInt32 oCurrentIndex;
    db2UInt32 oNumTotalIndexes;
    db2UInt32 oCurrentMPPNode;
    db2UInt32 oLoadRestarted;
    db2UInt32 oWhichPhase;
    db2UInt32 oWarningCount;
    db2UInt32 oTableState;
} db2LoadQueryOutputStruct;
/* ... */
```

### Generic API syntax:

```
/* File: db2ApiDf.h */
/* API: db2gLoadQuery */
/* ... */
SQL_API_RC SQL_API_FN
db2gLoadQuery (
    db2UInt32 versionNumber,
    void *pParmStruct,
    struct sqlca *pSqlca);
```

## db2LoadQuery - Load Query

```
typedef struct
{
    db2UInt32 iStringType;
    db2UInt32 iStringLen;
    char *piString;
    db2UInt32 iShowLoadMessages;
    db2LoadQueryOutputStruct *poOutputStruct;
    db2UInt32 iLocalMessageFileLen;
    char *piLocalMessageFile
} db2gLoadQueryStruct;

typedef struct
{
    db2UInt32 oRowsRead;
    db2UInt32 oRowsSkipped;
    db2UInt32 oRowsCommitted;
    db2UInt32 oRowsLoaded;
    db2UInt32 oRowsRejected;
    db2UInt32 oRowsDeleted;
    db2UInt32 oCurrentIndex;
    db2UInt32 oNumTotalIndexes;
    db2UInt32 oCurrentMPPNode;
    db2UInt32 oLoadRestarted;
    db2UInt32 oWhichPhase;
    db2UInt32 oWarningCount;
    db2UInt32 oTableState;
} db2LoadQueryOutputStruct;
/* ... */
```

### API parameters:

#### versionNumber

Input. Specifies the version and release level of the structure passed in as the second parameter, *pParmStruct*.

#### pParmStruct

Input. A pointer to the *db2LoadQueryStruct* structure.

#### pSqlca

Output. A pointer to the *sqlca* structure.

#### iStringType

Input. Specifies a type for *piString*. Valid values (defined in *db2ApiDf.h*) are:

##### DB2LOADQUERY\_TABLENAME

Specifies a table name for use by the *db2LoadQuery* API.

#### iStringLen

Input. Specifies the length in bytes of *piString*.

#### piString

Input. Specifies a temporary files path name or a table name, depending on the value of *iStringType*.

#### iShowLoadMessages

Input. Specifies the level of messages that are to be returned by the load utility. Valid values (defined in *db2ApiDf.h*) are:

##### DB2LOADQUERY\_SHOW\_ALL\_MSGS

Return all load messages.

##### DB2LOADQUERY\_SHOW\_NO\_MSGS

Return no load messages.

**DB2LOADQUERY\_SHOW\_NEW\_MSGS**

Return only messages that have been generated since the last call to this API.

**poOutputStruct**

Output. A pointer to the *db2LoadQueryOutputStruct* structure, which contains load summary information. Set to NULL if a summary is not required.

**iLocalMessageFileLen**

Input. Specifies the length in bytes of *piLocalMessageFile*.

**piLocalMessageFile**

Input. Specifies the name of a local file to be used for output messages.

**oRowsRead**

Output. Number of records read so far by the load utility.

**oRowsSkipped**

Output. Number of records skipped before the load operation began.

**oRowsCommitted**

Output. Number of rows committed to the target table so far.

**oRowsLoaded**

Output. Number of rows loaded into the target table so far.

**oRowsRejected**

Output. Number of rows rejected from the target table so far.

**oRowsDeleted**

Output. Number of rows deleted from the target table so far (during the delete phase).

**oCurrentIndex**

Output. Index currently being built (during the build phase).

**oCurrentMPPNode**

Output. Indicates which database partition server is being queried (for partitioned database environment mode only).

**oLoadRestarted**

Output. A flag whose value is TRUE if the load operation being queried is a load restart operation.

**oWhichPhase**

Output. Indicates the current phase of the load operation being queried. Valid values (defined in *db2ApiDf.h*) are:

**DB2LOADQUERY\_LOAD\_PHASE**

Load phase.

**DB2LOADQUERY\_BUILD\_PHASE**

Build phase.

**DB2LOADQUERY\_DELETE\_PHASE**

Delete phase.

**oNumTotalIndexes**

Output. Total number of indexes to be built (during the build phase).

**oWarningCount**

Output. Total number of warnings returned so far.

## db2LoadQuery - Load Query

### oTableState

Output. The table states. Valid values (as defined in db2ApiDf) are:

#### **DB2LOADQUERY\_NORMAL**

No table states affect the table.

#### **DB2LOADQUERY\_CHECK\_PENDING**

The table has constraints and the constraints have yet to be verified. Use the SET INTEGRITY command to take the table out of the DB2LOADQUERY\_CHECK\_PENDING state. The load utility puts a table into the DB2LOADQUERY\_CHECK\_PENDING state when it begins a load on a table with constraints.

#### **DB2LOADQUERY\_LOAD\_IN\_PROGRESS**

There is a load actively in progress on this table.

#### **DB2LOADQUERY\_LOAD\_PENDING**

A load has been active on this table but has been aborted before the load could commit. Issue a load terminate, a load restart, or a load replace to bring the table out of the DB2LOADQUERY\_LOAD\_PENDING state.

#### **DB2LOADQUERY\_READ\_ACCESS**

The table data is available for read access queries. Loads using the DB2LOADQUERY\_READ\_ACCESS option put the table into Read Access Only state.

#### **DB2LOADQUERY\_NOTAVAILABLE**

The table is unavailable. The table may only be dropped or it may be restored from a backup. Rollforward through a non-recoverable load will put a table into the unavailable state.

#### **DB2LOADQUERY\_NO\_LOAD\_RESTART**

The table is in a partially loaded state that will not allow a load restart. The table will also be in the Load Pending state. Issue a load terminate or a load replace to bring the table out of the No Load Restartable state. The table can be placed in the DB2LOADQUERY\_NO\_LOAD\_RESTART state during a rollforward operation. This can occur if you rollforward to a point in time that is prior to the end of a load operation, or if you roll forward through an aborted load operation but do not roll forward to the end of the load terminate or load restart operation.

#### **DB2LOADQUERY\_TYPE1\_INDEXES**

The table currently uses type-1 indexes. The indexes can be converted to type-2 using the CONVERT option when using the REORG utility on the indexes.

### Usage notes:

This API reads the status of the load operation on the table specified by *piString*, and writes the status to the file specified by *pLocalMsgFileName*.

### Related concepts:

- “Monitoring a partitioned database load using the LOAD QUERY command” on page 184

### Related reference:

- “SQLCA” in the *Administrative API Reference*

2  
2  
2  
2

**Related samples:**

- “loadqry.sqb -- Query the current status of a load (MF COBOL)”
- “tblog.sqc -- How to load into a partitioned database (C)”
- “tbmove.sqc -- How to move table data (C)”
- “tbmove.sqC -- How to move table data (C++)”

**File type modifiers for load**

Table 10. Valid file type modifiers for load: All file formats

Modifier	Description
anyorder	This modifier is used in conjunction with the <i>cpu_parallelism</i> parameter. Specifies that the preservation of source data order is not required, yielding significant additional performance benefit on SMP systems. If the value of <i>cpu_parallelism</i> is 1, this option is ignored. This option is not supported if SAVECOUNT > 0, since crash recovery after a consistency point requires that data be loaded in sequence.
generatedignore	This modifier informs the load utility that data for all generated columns is present in the data file but should be ignored. This results in all generated column values being generated by the utility. This modifier cannot be used with either the generatedmissing or the generatedoverride modifier.
generatedmissing	If this modifier is specified, the utility assumes that the input data file contains no data for the generated column (not even NULLs). This results in all generated column values being generated by the utility. This modifier cannot be used with either the generatedignore or the generatedoverride modifier.
generatedoverride	<p>This modifier instructs the load utility to accept user-supplied data for all generated columns in the table (contrary to the normal rules for these types of columns). This is useful when migrating data from another database system, or when loading a table from data that was recovered using the RECOVER DROPPED TABLE option on the ROLLFORWARD DATABASE command. When this modifier is used, any rows with no data or NULL data for a non-nullable generated column will be rejected (SQL3116W).</p> <p><b>Note:</b> When this modifier is used, the table will be placed in CHECK PENDING state. To take the table out of CHECK PENDING state without verifying the user-supplied values, issue the following command after the load operation:</p> <pre>SET INTEGRITY FOR &lt; table-name &gt; GENERATED COLUMN IMMEDIATED UNCHECKED</pre> <p>To take the table out of CHECK PENDING state and force verification of the user-supplied values, issue the following command after the load operation:</p> <pre>SET INTEGRITY FOR &lt; table-name &gt; IMMEDIATE CHECKED.</pre> <p>This modifier cannot be used with either the generatedmissing or the generatedignore modifier.</p>
identityignore	This modifier informs the load utility that data for the identity column is present in the data file but should be ignored. This results in all identity values being generated by the utility. The behavior will be the same for both GENERATED ALWAYS and GENERATED BY DEFAULT identity columns. This means that for GENERATED ALWAYS columns, no rows will be rejected. This modifier cannot be used with either the identitymissing or the identityoverride modifier.
identitymissing	If this modifier is specified, the utility assumes that the input data file contains no data for the identity column (not even NULLs), and will therefore generate a value for each row. The behavior will be the same for both GENERATED ALWAYS and GENERATED BY DEFAULT identity columns. This modifier cannot be used with either the identityignore or the identityoverride modifier.

## db2LoadQuery - Load Query

Table 10. Valid file type modifiers for load: All file formats (continued)

Modifier	Description
identityoverride	<p>This modifier should be used only when an identity column defined as GENERATED ALWAYS is present in the table to be loaded. It instructs the utility to accept explicit, non-NULL data for such a column (contrary to the normal rules for these types of identity columns). This is useful when migrating data from another database system when the table must be defined as GENERATED ALWAYS, or when loading a table from data that was recovered using the DROPPED TABLE RECOVERY option on the ROLLFORWARD DATABASE command. When this modifier is used, any rows with no data or NULL data for the identity column will be rejected (SQL3116W). This modifier cannot be used with either the identitymissing or the identityignore modifier.</p> <p><b>Note:</b> The load utility will not attempt to maintain or verify the uniqueness of values in the table's identity column when this option is used.</p>
indexfreespace= <i>x</i>	<p><i>x</i> is an integer between 0 and 99 inclusive. The value is interpreted as the percentage of each index page that is to be left as free space when load rebuilds the index. Load with INDEXING MODE INCREMENTAL ignores this option. The first entry in a page is added without restriction; subsequent entries are added the percent free space threshold can be maintained. The default value is the one used at CREATE INDEX time.</p> <p>This value takes precedence over the PCTFREE value specified in the CREATE INDEX statement; the registry variable DB2 INDEX FREE takes precedence over indexfreespace. The indexfreespace option affects index leaf pages only.</p>
lobsinfile	<p><i>lob-path</i> specifies the path to the files containing LOB data. The ASC, DEL, or IXF load input files contain the names of the files having LOB data in the LOB column.</p> <p>This option is not supported in conjunction with the CURSOR filetype.</p> <p>The LOBS FROM clause specifies where the LOB files are located when the "lobsinfile" modifier is used. The LOBS FROM clause means nothing outside the context of the "lobsinfile" modifier. The LOBS FROM clause conveys to the LOAD utility the list of paths to search for the LOB files while loading the data.</p> <p>Each path contains at least one file that contains at least one LOB pointed to by a Lob Location Specifier (LLS) in the data file. The LLS is a string representation of the location of a LOB in a file stored in the LOB file path. The format of an LLS is <i>filename.ext.nnn.mmm/</i>, where <i>filename.ext</i> is the name of the file that contains the LOB, <i>nnn</i> is the offset in bytes of the LOB within the file, and <i>mmm</i> is the length of the LOB in bytes. For example, if the string <i>db2exp.001.123.456/</i> is stored in the data file, the LOB is located at offset 123 in the file <i>db2exp.001</i>, and is 456 bytes long.</p> <p>To indicate a null LOB, enter the size as -1. If the size is specified as 0, it is treated as a 0 length LOB. For null LOBS with length of -1, the offset and the file name are ignored. For example, the LLS of a null LOB might be <i>db2exp.001.7.-1/</i>.</p>
noheader	<p>Skips the header verification code (applicable only to load operations into tables that reside in a single-partition database partition group).</p> <p>The AutoLoader utility writes a header to each file contributing data to a table in a multiple-partition database partition group. If the default MPP load (mode PARTITION_AND_LOAD) is used against a table residing in a single-partition database partition group, the file is not expected to have a header. Thus the noheader modifier is not needed. If the LOAD_ONLY mode is used, the file is expected to have a header. The only circumstance in which you should need to use the noheader modifier is if you wanted to perform LOAD_ONLY operation using a file that does not have a header.</p>
norowwarnings	<p>Suppresses all warnings about rejected rows.</p>

Table 10. Valid file type modifiers for load: All file formats (continued)

Modifier	Description
pagefreespace= <i>x</i>	<p><i>x</i> is an integer between 0 and 100 inclusive. The value is interpreted as the percentage of each data page that is to be left as free space. If the specified value is invalid because of the minimum row size, (for example, a row that is at least 3 000 bytes long, and an <i>x</i> value of 50), the row will be placed on a new page. If a value of 100 is specified, each row will reside on a new page.</p> <p><b>Note:</b> The PCTFREE value of a table determines the amount of free space designated per page. If a pagefreespace value on the load operation or a PCTFREE value on a table have not been set, the utility will fill up as much space as possible on each page. The value set by pagefreespace overrides the PCTFREE value specified for the table.</p>
subtableconvert	Valid only when loading into a single sub-table. Typical usage is to export data from a regular table, and then to invoke a load operation (using this modifier) to convert the data into a single sub-table.
totalfreespace= <i>x</i>	<p><i>x</i> is an integer greater than or equal to 0 . The value is interpreted as the percentage of the total pages in the table that is to be appended to the end of the table as free space. For example, if <i>x</i> is 20, and the table has 100 data pages after the data has been loaded, 20 additional empty pages will be appended. The total number of data pages for the table will be 120. The data pages total does not factor in the number of index pages in the table. This option does not affect the index object.</p> <p><b>Note:</b> If two loads are done with this option specified, the second load will not reuse the extra space appended to the end by the first load.</p>
usedefaults	<p>If a source column for a target table column has been specified, but it contains no data for one or more row instances, default values are loaded. Examples of missing data are:</p> <ul style="list-style-type: none"> <li>• For DEL files: ",," is specified for the column</li> <li>• For DEL/ASC/WSF files: A row that does not have enough columns, or is not long enough for the original specification.</li> </ul> <p>Without this option, if a source column contains no data for a row instance, one of the following occurs:</p> <ul style="list-style-type: none"> <li>• If the column is nullable, a NULL is loaded</li> <li>• If the column is not nullable, the utility rejects the row.</li> </ul>

Table 11. Valid file type modifiers for load: ASCII file formats (ASC/DEL)

Modifier	Description
codepage= <i>x</i>	<p><i>x</i> is an ASCII character string. The value is interpreted as the code page of the data in the input data set. Converts character data (and numeric data specified in characters) from this code page to the database code page during the load operation.</p> <p>The following rules apply:</p> <ul style="list-style-type: none"> <li>• For pure DBCS (graphic), mixed DBCS, and EUC, delimiters are restricted to the range of x00 to x3F, inclusive.</li> <li>• For DEL data specified in an EBCDIC code page, the delimiters may not coincide with the shift-in and shift-out DBCS characters.</li> <li>• nullindchar must specify symbols included in the standard ASCII set between code points x20 and x7F, inclusive. This refers to ASCII symbols and code points. EBCDIC data can use the corresponding symbols, even though the code points will be different.</li> </ul> <p>This option is not supported in conjunction with the CURSOR filetype.</p>

## db2LoadQuery - Load Query

Table 11. Valid file type modifiers for load: ASCII file formats (ASC/DEL) (continued)

Modifier	Description
dateformat="x"	<p>x is the format of the date in the source file.<sup>1</sup> Valid date elements are:</p> <p>YYYY - Year (four digits ranging from 0000 - 9999)  M - Month (one or two digits ranging from 1 - 12)  MM - Month (two digits ranging from 1 - 12;  mutually exclusive with M)  D - Day (one or two digits ranging from 1 - 31)  DD - Day (two digits ranging from 1 - 31;  mutually exclusive with D)  DDD - Day of the year (three digits ranging  from 001 - 366; mutually exclusive  with other day or month elements)</p> <p>A default value of 1 is assigned for each element that is not specified. Some examples of date formats are:</p> <p>"D-M-YYYY"  "MM.DD.YYYY"  "YYYYDDD"</p>
dumpfile = x	<p>x is the fully qualified (according to the server database partition) name of an exception file to which rejected rows are written. A maximum of 32 KB of data is written per record. Following is an example that shows how to specify a dump file:</p> <pre>db2 load from data of del modified by dumpfile = /u/user/filename insert into table_name</pre> <p>The file will be created and owned by the instance owner. To override the default file permissions, use the dumpfileaccessall file type modifier.</p> <p><b>Notes:</b></p> <ol style="list-style-type: none"> <li>1. In a partitioned database environment, the path should be local to the loading database partition, so that concurrently running load operations do not attempt to write to the same file.</li> <li>2. The contents of the file are written to disk in an asynchronous buffered mode. In the event of a failed or an interrupted load operation, the number of records committed to disk cannot be known with certainty, and consistency cannot be guaranteed after a LOAD RESTART. The file can only be assumed to be complete for a load operation that starts and completes in a single pass.</li> <li>3. This modifier does not support file names with multiple file extensions. For example, <pre>dumpfile = /home/svtdbm6/DUMP.FILE</pre> is acceptable to the load utility, but <pre>dumpfile = /home/svtdbm6/DUMP.LOAD.FILE</pre> is not.</li> </ol>
dumpfileaccessall = x	<p>Grants read access to 'OTHERS' when a dump file is created.</p> <p>This file type modifier is only valid when:</p> <ol style="list-style-type: none"> <li>1. it is used in conjunction with dumpfile file type modifier</li> <li>2. the user has SELECT privilege on the load target table</li> <li>3. it is issued on a DB2 server database partition that resides on a UNIX-based operating system</li> </ol>

Table 11. Valid file type modifiers for load: ASCII file formats (ASC/DEL) (continued)

Modifier	Description
fastparse	<p>Reduced syntax checking is done on user-supplied column values, and performance is enhanced. Tables loaded under this option are guaranteed to be architecturally correct, and the utility is guaranteed to perform sufficient data checking to prevent a segmentation violation or trap. Data that is in correct form will be loaded correctly.</p> <p>For example, if a value of 123qwr4 were to be encountered as a field entry for an integer column in an ASC file, the load utility would ordinarily flag a syntax error, since the value does not represent a valid number. With fastparse, a syntax error is not detected, and an arbitrary number is loaded into the integer field. Care must be taken to use this modifier with clean data only. Performance improvements using this option with ASCII data can be quite substantial.</p> <p>This option is not supported in conjunction with the CURSOR or IXF file types.</p>
implieddecimal	<p>The location of an implied decimal point is determined by the column definition; it is no longer assumed to be at the end of the value. For example, the value 12345 is loaded into a DECIMAL(8,2) column as 123.45, <i>not</i> 12345.00.</p> <p>This modifier cannot be used with the packeddecimal modifier.</p>
timeformat="x"	<p>x is the format of the time in the source file.<sup>1</sup> Valid time elements are:</p> <ul style="list-style-type: none"> <li>H - Hour (one or two digits ranging from 0 - 12 for a 12 hour system, and 0 - 24 for a 24 hour system)</li> <li>HH - Hour (two digits ranging from 0 - 12 for a 12 hour system, and 0 - 24 for a 24 hour system; mutually exclusive with H)</li> <li>M - Minute (one or two digits ranging from 0 - 59)</li> <li>MM - Minute (two digits ranging from 0 - 59; mutually exclusive with M)</li> <li>S - Second (one or two digits ranging from 0 - 59)</li> <li>SS - Second (two digits ranging from 0 - 59; mutually exclusive with S)</li> <li>SSSSS - Second of the day after midnight (5 digits ranging from 00000 - 86399; mutually exclusive with other time elements)</li> <li>TT - Meridian indicator (AM or PM)</li> </ul> <p>A default value of 0 is assigned for each element that is not specified. Some examples of time formats are:</p> <pre>"HH:MM:SS" "HH.MM TT" "SSSSS"</pre>

4

## db2LoadQuery - Load Query

Table 11. Valid file type modifiers for load: ASCII file formats (ASC/DEL) (continued)

Modifier	Description
timestampformat="x"	<p>x is the format of the time stamp in the source file.<sup>1</sup> Valid time stamp elements are:</p> <p>YYYY - Year (four digits ranging from 0000 - 9999)</p> <p>M - Month (one or two digits ranging from 1 - 12)</p> <p>MM - Month (two digits ranging from 01 - 12; mutually exclusive with M and MMM)</p> <p>MMM - Month (three-letter case-insensitive abbreviation for the month name; mutually exclusive with M and MM)</p> <p>D - Day (one or two digits ranging from 1 - 31)</p> <p>DD - Day (two digits ranging from 1 - 31; mutually exclusive with D)</p> <p>DDD - Day of the year (three digits ranging from 001 - 366; mutually exclusive with other day or month elements)</p> <p>H - Hour (one or two digits ranging from 0 - 12 for a 12 hour system, and 0 - 24 for a 24 hour system)</p> <p>HH - Hour (two digits ranging from 0 - 12 for a 12 hour system, and 0 - 24 for a 24 hour system; mutually exclusive with H)</p> <p>M - Minute (one or two digits ranging from 0 - 59)</p> <p>MM - Minute (two digits ranging from 0 - 59; mutually exclusive with M, minute)</p> <p>S - Second (one or two digits ranging from 0 - 59)</p> <p>SS - Second (two digits ranging from 0 - 59; mutually exclusive with S)</p> <p>SSSSS - Second of the day after midnight (5 digits ranging from 00000 - 86399; mutually exclusive with other time elements)</p> <p>UUUUUU - Microsecond (6 digits ranging from 000000 - 999999; mutually exclusive with all other microsecond elements)</p> <p>UUUUU - Microsecond (5 digits ranging from 00000 - 99999, maps to range from 000000 - 999990; mutually exclusive with all other microsecond elements)</p> <p>UUUU - Microsecond (4 digits ranging from 0000 - 9999, maps to range from 000000 - 999900; mutually exclusive with all other microsecond elements)</p> <p>UUU - Microsecond (3 digits ranging from 000 - 999, maps to range from 000000 - 999000; mutually exclusive with all other microsecond elements)</p> <p>UU - Microsecond (2 digits ranging from 00 - 99, maps to range from 000000 - 990000; mutually exclusive with all other microsecond elements)</p> <p>U - Microsecond (1 digit ranging from 0 - 9, maps to range from 000000 - 900000; mutually exclusive with all other microsecond elements)</p> <p>TT - Meridian indicator (AM or PM)</p> <p>A default value of 1 is assigned for unspecified YYYY, M, MM, D, DD, or DDD elements. A default value of 'Jan' is assigned to an unspecified MMM element. A default value of 0 is assigned for all other unspecified elements. Following is an example of a time stamp format:</p> <p>"YYYY/MM/DD HH:MM:SS.UUUUUU"</p> <p>The valid values for the MMM element include: 'jan', 'feb', 'mar', 'apr', 'may', 'jun', 'jul', 'aug', 'sep', 'oct', 'nov' and 'dec'. These values are case insensitive.</p> <p>The following example illustrates how to import data containing user defined date and time formats into a table called schedule:</p> <pre>db2 import from delfile2 of del modified by timestampformat="yyyy.mm.dd hh:mm tt" insert into schedule</pre>
noeofchar	The optional end-of-file character x'1A' is not recognized as the end of file. Processing continues as if it were a normal character.

Table 11. Valid file type modifiers for load: ASCII file formats (ASC/DEL) (continued)

Modifier	Description
usegraphiccodepage	<p>If usegraphiccodepage is given, the assumption is made that data being loaded into graphic or double-byte character large object (DBCLOB) data field(s) is in the graphic code page. The rest of the data is assumed to be in the character code page. The graphic codepage is associated with the character code page. LOAD determines the character code page through either the codepage modifier, if it is specified, or through the code page of the database if the codepage modifier is not specified.</p> <p>This modifier should be used in conjunction with the delimited data file generated by drop table recovery only if the table being recovered has graphic data.</p> <p><b>Restrictions</b></p> <p>The usegraphiccodepage modifier MUST NOT be specified with DEL or ASC files created by the EXPORT utility, as these files contain data encoded in only one code page. The usegraphiccodepage modifier is also ignored by the double-byte character large objects (DBCLOBs) in files.</p>

Table 12. Valid file type modifiers for load: ASC file formats (Non-delimited ASCII)

Modifier	Description
binarynumerics	<p>Numeric (but not DECIMAL) data must be in binary form, not the character representation. This avoids costly conversions.</p> <p>This option is supported only with positional ASC, using fixed length records specified by the reclen option. The noeofchar option is assumed.</p> <p>The following rules apply:</p> <ul style="list-style-type: none"> <li>• No conversion between data types is performed, with the exception of BIGINT, INTEGER, and SMALLINT.</li> <li>• Data lengths must match their target column definitions.</li> <li>• FLOATs must be in IEEE Floating Point format.</li> <li>• Binary data in the load source file is assumed to be big-endian, regardless of the platform on which the load operation is running.</li> </ul> <p><b>Note:</b> NULLs cannot be present in the data for columns affected by this modifier. Blanks (normally interpreted as NULL) are interpreted as a binary value when this modifier is used.</p>
nochecklengths	<p>If nochecklengths is specified, an attempt is made to load each row, even if the source data has a column definition that exceeds the size of the target table column. Such rows can be successfully loaded if code page conversion causes the source data to shrink; for example, 4-byte EUC data in the source could shrink to 2-byte DBCS data in the target, and require half the space. This option is particularly useful if it is known that the source data will fit in all cases despite mismatched column definitions.</p>
nullindchar=x	<p>x is a single character. Changes the character denoting a NULL value to x. The default value of x is Y.<sup>2</sup></p> <p>This modifier is case sensitive for EBCDIC data files, except when the character is an English letter. For example, if the NULL indicator character is specified to be the letter N, then n is also recognized as a NULL indicator.</p>

## db2LoadQuery - Load Query

Table 12. Valid file type modifiers for load: ASC file formats (Non-delimited ASCII) (continued)

Modifier	Description
packeddecimal	<p>Loads packed-decimal data directly, since the <code>binarynumerics</code> modifier does not include the <code>DECIMAL</code> field type.</p> <p>This option is supported only with positional ASC, using fixed length records specified by the <code>reclen</code> option. The <code>noeofchar</code> option is assumed.</p> <p>Supported values for the sign nibble are:</p> <ul style="list-style-type: none"> <li>+ = 0xC 0xA 0xE 0xF</li> <li>- = 0xD 0xB</li> </ul> <p>NULLs cannot be present in the data for columns affected by this modifier. Blanks (normally interpreted as NULL) are interpreted as a binary value when this modifier is used.</p> <p>Regardless of the server platform, the byte order of binary data in the load source file is assumed to be big-endian; that is, when using this modifier on Windows operating systems, the byte order must not be reversed.</p> <p>This modifier cannot be used with the <code>implieddecimal</code> modifier.</p>
reclen= <i>x</i>	<p><i>x</i> is an integer with a maximum value of 32 767. <i>x</i> characters are read for each row, and a new-line character is not used to indicate the end of the row.</p>
striptblanks	<p>Truncates any trailing blank spaces when loading data into a variable-length field. If this option is not specified, blank spaces are kept.</p> <p>This option cannot be specified together with <code>striptnulls</code>. These are mutually exclusive options.</p> <p><b>Note:</b> This option replaces the obsolete <code>t</code> option, which is supported for back-level compatibility only.</p>
striptnulls	<p>Truncates any trailing NULLs (0x00 characters) when loading data into a variable-length field. If this option is not specified, NULLs are kept.</p> <p>This option cannot be specified together with <code>striptblanks</code>. These are mutually exclusive options.</p> <p><b>Note:</b> This option replaces the obsolete <code>padwithzero</code> option, which is supported for back-level compatibility only.</p>
zoneddecimal	<p>Loads zoned decimal data, since the <code>BINARYNUMERICS</code> modifier does not include the <code>DECIMAL</code> field type. This option is supported only with positional ASC, using fixed length records specified by the <code>RECLEN</code> option. The <code>NOEOFCHAR</code> option is assumed.</p> <p>Half-byte sign values can be one of the following:</p> <ul style="list-style-type: none"> <li>+ = 0xC 0xA 0xE 0xF</li> <li>- = 0xD 0xB</li> </ul> <p>Supported values for digits are 0x0 to 0x9.</p> <p>Supported values for zones are 0x3 and 0xF.</p>

Table 13. Valid file type modifiers for load: DEL file formats (Delimited ASCII)

Modifier	Description
chardelx	<p><i>x</i> is a single character string delimiter. The default value is a double quotation mark ("). The specified character is used in place of double quotation marks to enclose a character string.<sup>23</sup> If you wish to explicitly specify the double quotation mark(") as the character string delimiter, you should specify it as follows:</p> <pre>modified by chardel""</pre> <p>The single quotation mark (') can also be specified as a character string delimiter as follows:</p> <pre>modified by chardel''</pre>
coldelx	<i>x</i> is a single character column delimiter. The default value is a comma (.). The specified character is used in place of a comma to signal the end of a column. <sup>23</sup>
datesiso	Date format. Causes all date data values to be loaded in ISO format.
decplusblank	Plus sign character. Causes positive decimal values to be prefixed with a blank space instead of a plus sign (+). The default action is to prefix positive decimal values with a plus sign.
decptr	<i>x</i> is a single character substitute for the period as a decimal point character. The default value is a period (.). The specified character is used in place of a period as a decimal point character. <sup>23</sup>
delprioritychar	<p>The current default priority for delimiters is: record delimiter, character delimiter, column delimiter. This modifier protects existing applications that depend on the older priority by reverting the delimiter priorities to: character delimiter, record delimiter, column delimiter. Syntax:</p> <pre>db2 load ... modified by delprioritychar ...</pre> <p>For example, given the following DEL data file:</p> <pre>"Smith, Joshua",4000,34.98&lt;row delimiter&gt; "Vincent,&lt;row delimiter&gt;, is a manager", ... ... 4005,44.37&lt;row delimiter&gt;</pre> <p>With the delprioritychar modifier specified, there will be only two rows in this data file. The second &lt;row delimiter&gt; will be interpreted as part of the first data column of the second row, while the first and the third &lt;row delimiter&gt; are interpreted as actual record delimiters. If this modifier is <i>not</i> specified, there will be three rows in this data file, each delimited by a &lt;row delimiter&gt;.</p>
dlldelx	<p><i>x</i> is a single character DATALINK delimiter. The default value is a semicolon (;). The specified character is used in place of a semicolon as the inter-field separator for a DATALINK value. It is needed because a DATALINK value may have more than one sub-value. <sup>234</sup></p> <p><b>Note:</b> <i>x</i> must not be the same character specified as the row, column, or character string delimiter.</p>
keepblanks	<p>Preserves the leading and trailing blanks in each field of type CHAR, VARCHAR, LONG VARCHAR, or CLOB. Without this option, all leading and trailing blanks that are not inside character delimiters are removed, and a NULL is inserted into the table for all blank fields.</p> <p>The following example illustrates how to load data into a table called TABLE1, while preserving all leading and trailing spaces in the data file:</p> <pre>db2 load from delfile3 of del modified by keepblanks insert into table1</pre>

## db2LoadQuery - Load Query

Table 13. Valid file type modifiers for load: DEL file formats (Delimited ASCII) (continued)

Modifier	Description
nochardel	The load utility will assume all bytes found between the column delimiters to be part of the column's data. Character delimiters will be parsed as part of column data. This option should not be specified if the data was exported using DB2 (unless nochardel was specified at export time). It is provided to support vendor data files that do not have character delimiters. Improper usage may result in data loss or corruption.  This option cannot be specified with charde1x, delprioritychar or nodoublede1. These are mutually exclusive options.
nodoublede1	Suppresses recognition of double character delimiters.

Table 14. Valid file type modifiers for load: IXF file format

Modifier	Description
forcein	Directs the utility to accept data despite code page mismatches, and to suppress translation between code pages.  Fixed length target fields are checked to verify that they are large enough for the data. If nochecklengths is specified, no checking is done, and an attempt is made to load each row.
nochecklengths	If nochecklengths is specified, an attempt is made to load each row, even if the source data has a column definition that exceeds the size of the target table column. Such rows can be successfully loaded if code page conversion causes the source data to shrink; for example, 4-byte EUC data in the source could shrink to 2-byte DBCS data in the target, and require half the space. This option is particularly useful if it is known that the source data will fit in all cases despite mismatched column definitions.

### Notes:

1. Double quotation marks around the date format string are mandatory. Field separators cannot contain any of the following: a-z, A-Z, and 0-9. The field separator should not be the same as the character delimiter or field delimiter in the DEL file format. A field separator is optional if the start and end positions of an element are unambiguous. Ambiguity can exist if (depending on the modifier) elements such as D, H, M, or S are used, because of the variable length of the entries.

For time stamp formats, care must be taken to avoid ambiguity between the month and the minute descriptors, since they both use the letter M. A month field must be adjacent to other date fields. A minute field must be adjacent to other time fields. Following are some ambiguous time stamp formats:

```
"M" (could be a month, or a minute)
"M:M" (Which is which?)
"M:YYYY:M" (Both are interpreted as month.)
"S:M:YYYY" (adjacent to both a time value and a date value)
```

In ambiguous cases, the utility will report an error message, and the operation will fail.

Following are some unambiguous time stamp formats:

```
"M:YYYY" (Month)
"S:M" (Minute)
"M:YYYY:S:M" (Month...Minute)
"M:H:YYYY:M:D" (Minute...Month)
```

Some characters, such as double quotation marks and back slashes, must be preceded by an escape character (for example, \).

2. The character must be specified in the code page of the source data.  
The character code point (instead of the character symbol), can be specified using the syntax xJJ or 0xJJ, where JJ is the hexadecimal representation of the code point. For example, to specify the # character as a column delimiter, use one of the following:
  - ... modified by coldel# ...
  - ... modified by coldel0x23 ...
  - ... modified by coldelX23 ...
3. Delimiter restrictions for moving data lists restrictions that apply to the characters that can be used as delimiter overrides.
4. Even if the DATALINK delimiter character is a valid character within the URL syntax, it will lose its special meaning within the scope of the load operation.
5. The load utility does not issue a warning if an attempt is made to use unsupported file types with the MODIFIED BY option. If this is attempted, the load operation fails, and an error code is returned.

Table 15. LOAD behavior when using codepage and usegraphiccodepage

codepage=N	usegraphiccodepage	LOAD behavior
Absent	Absent	All data in the file is assumed to be in the database code page, not the application code page, even if the CLIENT option is specified.
Present	Absent	All data in the file is assumed to be in code page N. <b>Warning:</b> Graphic data will be corrupted when loaded into the database if N is a single-byte code page.
Absent	Present	Character data in the file is assumed to be in the database code page, even if the CLIENT option is specified. Graphic data is assumed to be in the code page of the database graphic data, even if the CLIENT option is specified.  If the database code page is single-byte, then all data is assumed to be in the database code page. <b>Warning:</b> Graphic data will be corrupted when loaded into a single-byte database.
Present	Present	Character data is assumed to be in code page N. Graphic data is assumed to be in the graphic code page of N.  If N is a single-byte or double-byte code page, then all data is assumed to be in code page N. <b>Warning:</b> Graphic data will be corrupted when loaded into the database if N is a single-byte code page.

**Related reference:**

- “LOAD” on page 100
- “db2Load - Load” on page 123
- “Delimiter restrictions for moving data” on page 217

---

## Load exception table

The exception table is a user-created table that reflects the definition of the table being loaded, and includes some additional columns. It is specified by the FOR EXCEPTION clause on the LOAD command. An exception table might not contain an identity column or any other type of generated column. If an identity column is present in the primary table, the corresponding column in the exception table should only contain the column's type, length, and nullability attributes. The exception table is used to store copies of rows that violate unique index rules; the utility will not check for constraints or foreign key violations other than violations of uniqueness. DATALINK exceptions are also captured in the exception table.

A load exception table can be assigned to the table space where the table being loaded resides, or to another table space. In either case, the load exception table should be assigned to the same database partition group and have the same partitioning key as the table being loaded.

A unique key is a key for which no two values are equal. The mechanism used to enforce this constraint is called a unique index. A primary key is a special case of a unique key. A table cannot have more than one primary key.

**Note:** Any rows rejected because of invalid data before the building of an index are not inserted into the exception table.

Rows are appended to existing information in the exception table; this can include invalid rows from previous load operations. If you want only the invalid rows from the current load operation, you must remove the existing rows before invoking the utility.

The exception table used with the load utility is identical to the exception tables used by the SET INTEGRITY statement.

An exception table should be used when loading data which has a unique index and the possibility of duplicate records. If an exception table is not specified, and duplicate records are found, the load operation continues, and only a warning message is issued about the deleted duplicate records. The records themselves are not logged.

After the load operation completes, information in the exception table can be used to correct data that is in error. The corrected data can then be inserted into the table.

**Related reference:**

- "Exception tables" in the *SQL Reference, Volume 1*

---

## Load dump file

| Specifying the *dumpfile* modifier tells the load utility the name and the location of  
| the exception file to which rejected rows are written. When running in a  
| partitioned database environment, rows can be rejected either by the Partitioning  
| Subagents or by the Loading Subagents. Because of this, the dumpfile name is  
| given an extension that identifies the subagent type, as well as the partition  
| number where the exceptions were generated. For example, if you specified the  
| following dumpfile value:

```
dumpfile = "/u/username/dumpit"
```

Then rows that were rejected by the Load Subagent on partition five will be stored in a file named `/u/username/dumpit.load.005`, rows that were rejected by the Load Subagent on partition two will be stored in a file named `/u/username/dumpit.load.002`, and rows that were rejected by the Partitioning Subagent on partition two will be stored in a file named `/u/username/dumpit.part.002`, and so on.

For rows rejected by the Load Subagent, if the row is less than 32 768 bytes in length, the record is copied to the dump file in its entirety; if it is longer, a row fragment (including the final bytes of the record) is written to the file.

For rows rejected by the Partitioning Subagent, the entire row is copied to the dump file regardless of the record size.

**Related reference:**

- “LOAD” on page 100

---

## Load temporary files

DB2® creates temporary binary files during load processing. These files are used for load crash recovery, load terminate operations, warning and error messages, and runtime control data. The temporary files are removed when the load operation completes without error.

The temporary files are written to a path that can be specified through the *temp-pathname* parameter of the LOAD command, or in the *piTempFilesPath* parameter of the **db2Load** API. The default path is a subdirectory of the database directory.

The temporary files path resides on the server machine and is accessed by the DB2 instance exclusively. Therefore, it is imperative that any path name qualification given to the *temp-pathname* parameter reflects the directory structure of the server, not the client, and that the DB2 instance owner has read and write permission on the path.

**Note:** In an MPP system, the temporary files path should reside on a local disk, not on an NFS mount. If the path is on an NFS mount, there will be significant performance degradation during the load operation.

**Attention:** The temporary files written to this path must not be tampered with under any circumstances. Doing so will cause the load operation to malfunction, and will place your database in jeopardy.

**Related reference:**

- “LOAD” on page 100
- “db2Load - Load” on page 123

---

## Load utility log records

The utility manager produces log records associated with a number of DB2® utilities, including the load utility. The following log records mark the beginning or end of a specific activity during a load operation:

- Load Start. This log record is associated with the beginning of a load operation.
- Load Delete Start. This log record is associated with the beginning of the delete phase in a load operation. The delete phase is started only if there are duplicate primary key values. During the delete phase, each delete operation on a table record, or an index key, is logged.
- Load Delete End. This log record is associated with the end of the delete phase in a load operation. This delete phase will be repeated during the rollforward recovery of a successful load operation.
- Load Pending List. This log record is written when a load transaction commits and is used instead of a normal transaction commit log record.

The following list outlines the log records that the load utility will create depending on the size of the input data:

- Two log records will be created for every table space extent allocated or deleted by the utility in a DMS table space.
- One log record will be created for every chunk of identity values consumed.
- Log records will be created for every data row or index key deleted during the delete phase of a load operation.
- Log records will be created that maintain the integrity of the index tree when performing a load operation with the ALLOW READ ACCESS and INDEXING MODE INCREMENTAL options specified. The number of records logged is considerably less than a fully logged insertion into the index.

### Related reference:

- “LOAD” on page 100
- “db2Load - Load” on page 123

---

## Table locking, table states and table space states

In most cases, the load utility uses table level locking to restrict access to tables. The load utility does not quiesce the table spaces involved in the load operation, and uses table space states only for load operations with the COPY NO option specified. The level of locking depends on whether or not the load operation allows read access. A load operation in ALLOW NO ACCESS mode will use an exclusive lock (Z-lock) on the table for the duration of the load. An load operation in ALLOW READ ACCESS mode acquires and maintains a share lock (S-lock) for the duration of the load operation, and upgrades the lock to an exclusive lock (Z-lock) when data is being committed.

Before a load operation in ALLOW READ ACCESS mode begins, the load utility will wait for all applications that began before the load operation to release locks on the target table. Since locks are not persistent, they are supplemented by table states that will remain even if a load operation is aborted. These states can be checked by using the LOAD QUERY command. By using the LOCK WITH FORCE option, the load utility will force applications holding conflicting locks off the table that it is trying to load into.

## Locking Behavior For Load Operations in ALLOW READ ACCESS Mode

At the beginning of a load operation, the load utility acquires a share lock (S-lock) on the table. It holds this lock until the data is being committed. The share lock allows applications with compatible locks to access the table during the load operation. For example, applications that use read only queries will be able to access the table, while applications that try to insert data into the table will be denied. When the load utility acquires the share lock on the table, it will wait for all applications that hold locks on the table prior to the start of the load operation to release them, even if they have compatible locks. Since the load utility upgrades the share lock to an exclusive (Z-lock) when the data is being committed, there can be some delay in commit time while the load utility waits for applications with conflicting locks to finish.

**Note:** The load operation will not timeout while it waits for the applications to release their locks on the table.

### LOCK WITH FORCE Option

2 The LOCK WITH FORCE option can be used to force off applications holding  
2 conflicting locks on the target table so that the load operation can proceed.  
2 Applications holding conflicting locks on the system catalog tables will not be  
2 forced off by load. If an application is forced off the system by the load utility, it  
2 will lose its database connection and an error will be returned (SQL1224N).

For a load operation in ALLOW NO ACCESS mode, all applications holding table locks that exist at the start of the load operation will be forced.

For a load operation in ALLOW READ ACCESS mode applications holding the following locks will be forced:

- Table locks that conflict with a table share lock (for example, import or insert).
- All table locks that exist at the commit phase of the load operation.

When the COPY NO option is specified for a load operation on a recoverable database, all objects in the target table space will be locked in share mode before the table space is placed in backup pending state. This will occur regardless of the access mode. If the LOCK WITH FORCE option is specified, all applications holding locks on objects in the table space that conflict with a share lock will be forced off.

### Table States

| In addition to locks, the load utility uses table states to control access to tables. A  
| table state can be checked by using the LOAD QUERY command. The states  
| returned by the LOAD QUERY command are as follows:

#### Normal

No table states affect the table.

#### Check Pending

The table has constraints which have not yet been verified. Use the SET INTEGRITY statement to take the table out of check pending state. The load utility places a table in the check pending state when it begins a load operation on a table with constraints.

#### Load in Progress

There is a load operation in progress on this table.

### **Load Pending**

A load operation has been active on this table but has been aborted before the data could be committed. Issue a LOAD TERMINATE, LOAD RESTART, or LOAD REPLACE command to bring the table out of this state.

### **Read Access Only**

The table data is available for read access queries. Load operations using the ALLOW READ ACCESS option place the table in read access only state.

### **Unavailable**

The table is unavailable. The table can only be dropped or restored from a backup. Rolling forward through a non-recoverable load operation will place a table in the unavailable state.

### **Not Load Restartable**

The table is in a partially loaded state that will not allow a load restart operation. The table will also be in load pending state. Issue a LOAD TERMINATE or a LOAD REPLACE command to bring the table out of the not load restartable state. A table is placed in not load restartable state when a rollforward operation is performed after a failed load operation that has not been successfully restarted or terminated, or when a restore operation is performed from an online backup that was taken while the table was in load in progress or load pending state. In either case, the information required for a load restart operation is unreliable, and the not load restartable state prevents a load restart operation from taking place.

### **Type-1 Indexes**

The table currently uses type-1 indexes. The indexes can be converted to type-2 using the CONVERT option when using the REORG utility on the indexes.

### **Unknown**

The LOAD QUERY command is unable to determine the table state.

A table can be in several states at the same time. For example, if data is loaded into a table with constraints and the ALLOW READ ACCESS option is specified, table state would be:

```
Tablestate:  
  Check Pending  
  Load in Progress  
  Read Access Only
```

After the load operation but before issuing the SET INTEGRITY statement, the table state would be:

```
Tablestate:  
  Check Pending  
  Read Access Only
```

After the SET INTEGRITY statement has been issued the table state would be:

```
Tablestate:  
  Normal
```

### **Table Space States when COPY NO is Specified**

If a load operation with the COPY NO option is executed in a recoverable database, the table spaces associated with the load operation are placed in the backup table space state and the load in progress table space state. This takes place

at the beginning of the load operation. The load operation can be delayed at this point while locks are acquired on the tables within the table space.

When a table space is in backup pending state, it is still available for read access. The table space can only be taken out of backup pending state by taking a backup of the table space. Even if the load operation is aborted, the table space will remain in backup pending state because the table space state is changed at the beginning of the load operation, and cannot be rolled back if it fails. The load in progress table space state prevents online backups of a load operation with the COPY NO option specified while data is being loaded. The load in progress state is removed when the load operation is completed or aborts.

During a rollforward operation through a LOAD command with the COPY NO option specified, the associated table spaces are placed in restore pending state. To remove the table spaces from restore pending state, a restore operation must be performed. A rollforward operation will only place a table space in the restore pending state if the load operation completed successfully.

**Related concepts:**

- “Pending states after a load operation” on page 165

---

## Character set and national language support

The DB2<sup>®</sup> UDB data movement utilities offer the following National Language Support (NLS):

- The import and the export utilities provide automatic code page conversion from a client code page to the server code page.
- For the load utility, data can be converted from any code page to the server code page by using the codepage modifier with DEL and ASC files.
- For all utilities, IXF data is automatically converted from its original code page (as stored in the IXF file) to the server code page.

Unequal code page situations, involving expansion or contraction of the character data, can sometimes occur. For example, Japanese or Traditional-Chinese Extended UNIX<sup>®</sup> Code (EUC) and double-byte character sets (DBCS) might encode different lengths for the same character. Normally, comparison of input data length to target column length is performed before reading in any data. If the input length is greater than the target length, NULLs are inserted into that column if it is nullable. Otherwise, the request is rejected. If the `nochecklengths` modifier is specified, no initial comparison is performed, and an attempt is made to load the data. If the data is too long after translation is complete, the row is rejected. Otherwise, the data is loaded.

**Related reference:**

- “LOAD” on page 100

---

## Pending states after a load operation

The load utility uses *table* states to preserve database consistency during a load operation. These states can be checked by using the LOAD QUERY command.

The load and build phases of the load process place the target table in the load in progress table state. The load utility also places table spaces in the load in progress

state when the COPY NO option is specified on a recoverable database. The table spaces remain in this state for the duration of the load operation and are returned to normal state if the transaction is committed or rolled back.

If the NO ACCESS option has been specified, the table cannot be accessed while the load is in progress. If the ALLOW READ ACCESS option has been specified, the data in the table that existed prior to the invocation of the load command will be available in read only mode during the load operation. If the ALLOW READ ACCESS option is specified and the load operation fails, the data that existed in the table prior to the load operation will continue to be available in read only mode after the failure.

To remove the load in progress table state (if the load operation has failed, or was interrupted), do one of the following:

- Restart the load operation. First, address the cause of the failure; for example, if the load utility ran out of disk space, add containers to the table space before attempting a load restart operation.
- Terminate the load operation.
- Invoke a LOAD REPLACE operation against the same table on which a load operation has failed.
- Recover table spaces for the loading table by using the RESTORE DATABASE command with the most recent table space or database backup, and then carry out further recovery actions.

Table spaces are placed in backup pending state if the load process completes, and:

- The database configuration parameter *logretain* is set to recovery, or *userexit* is enabled, and
- The load option COPY YES is not specified, and
- The load option NONRECOVERABLE is not specified.

The fourth possible state associated with the load process (check pending state) pertains to referential and check constraints, DATALINKS constraints, generated column constraints, materialized query computation, or staging table propagation. For example, if an existing table is a parent table containing a primary key referenced by a foreign key in a dependent table, replacing data in the parent table places both tables (not the table space) in check pending state. To validate a table for referential integrity and check constraints, issue the SET INTEGRITY statement after the load process completes, if the table has been left in check pending state.

**Related concepts:**

- “Checking for integrity violations” on page 91
- “Table locking, table states and table space states” on page 162

**Related reference:**

- “LIST TABLESPACES Command” in the *Command Reference*


---

## Optimizing load performance

The performance of the load utility depends on the nature and the quantity of the data, the number of indexes, and the load options specified.

Unique indexes reduce load performance if duplicates are encountered. In most cases, it is still more efficient to create indexes during the load operation than to

invoke the CREATE INDEX statement for each index after the load operation completes (see Figure 5).



*Figure 5. Increasing Load Performance through Concurrent Indexing and Statistics Collection.* Tables are normally built in three steps: data loading, index building, and statistics collection. This causes multiple data I/O during the load operation, during index creation (there can be several indexes for each table), and during statistics collection (which causes I/O on the table data and on all of the indexes). A much faster alternative is to let the load utility complete all of these tasks in one pass through the data.

When tuning index creation performance, the amount of memory dedicated to the sorting of index keys during a load operation is controlled by the *sortheap* database configuration parameter. For example, to direct the load utility to use 4000 pages of main memory per index for key sorting, set the *sortheap* database configuration parameter to be 4000 pages, disconnect all applications from the database, and then issue the LOAD command. If an index is so large that it cannot be sorted in memory, a sort spill occurs. That is, the data is divided among several "sort runs" and stored in a temporary table space that will be merged later. If there is no way to avoid a sort spill by increasing the size of the *sortheap* parameter, it is important that the buffer pool for temporary table spaces be large enough to minimize the amount of disk I/O that spilling causes. Furthermore, to achieve I/O parallelism during the merging of sort runs, it is recommended that temporary table spaces be declared with multiple containers, each residing on a different disk device.

Load performance can be improved by installing high performance sorting libraries from third party vendors to create indexes during the load operation. An example of a third party sort product is SyncSort. Use the **DB2SORT** environment variable (registry value) to specify the location of the sorting library that is to be loaded at run time.

Use of the SET INTEGRITY statement might lengthen the total time needed to load a table and make it usable again. If all the load operations are performed in INSERT mode, the SET INTEGRITY statement will check the table for constraints violations incrementally (by checking only the appended portion of the table). If a table cannot be checked for constraints violations incrementally, the entire table is checked, and it might be some time before the table is usable again.

Similarly, if a load operation is performed on the underlying tables of a materialized query table, use of the REFRESH TABLE statement might lengthen the time needed to make both the underlying tables and the materialized query table fully usable again. If several sequential load operations are performed in INSERT mode into the underlying tables of a REFRESH IMMEDIATE materialized query table, the SET INTEGRITY statement will incrementally refresh the materialized query table in most cases. If the system determines that a full refresh is required, the materialized query table definition query will be recomputed, and it might be some time before the table is usable again.

The load utility performs equally well in INSERT mode and in REPLACE mode.

The utility attempts to deliver the best performance possible by determining optimal values for DISK\_PARALLELISM, CPU\_PARALLELISM, and DATA\_BUFFER, if these parameters have not been specified by the user. Optimization is done based on the size and the free space available in the utility heap. Consider allowing the load utility to choose values for these parameters before attempting to tune them for your particular needs.

Following is information about the performance implications of various options available through the load utility:

#### **ANYORDER**

Specify this file type modifier to suspend the preservation of order in the data being loaded, and improve performance. If the data to be loaded is presorted, anyorder might corrupt the presorted order, and the benefits of presorting will be lost for subsequent queries.

#### **BINARY NUMERICS and PACKED DECIMAL**

Use these file type modifiers to improve performance when loading positional numeric ASC data into fixed-length records.

#### **COPY YES or NO**

Use this parameter to specify whether a copy of the input data is to be made during a load operation. COPY YES reduces load performance, because all of the loading data is copied during the load operation (forward recovery must be enabled); the increased I/O activity might increase the load time on an I/O-bound system. Specifying multiple devices or directories (on different disks) can offset some of the performance penalty resulting from this operation. COPY NO might reduce overall performance, because if forward recovery is enabled, the table space is placed in backup pending state, and the database, or selected table spaces, must be backed up before the table can be accessed.

#### **CPU\_PARALLELISM**

Use this parameter to exploit intra-partition parallelism (if this is part of your machine's capability), and significantly improve load performance. The parameter specifies the number of processes or threads used by the load utility to parse, convert, and format data records. The maximum number allowed is 30. If there is insufficient memory to support the specified value, the utility adjusts the value. If this parameter is not specified, the load utility selects a default value that is based on the number of CPUs on the system.

Record order in the source data is preserved (see Figure 6 on page 169) regardless of the value of this parameter.

If tables include either LOB or LONG VARCHAR data, CPU\_PARALLELISM is set to one. Parallelism is not supported in this case.

Although use of this parameter is not restricted to symmetric multiprocessor (SMP) hardware, you might not obtain any discernible performance benefit from using it in non-SMP environments.



Figure 6. Record Order in the Source Data is Preserved When Intra-partition Parallelism is Exploited During a Load Operation

### DATA BUFFER

The DATA BUFFER parameter specifies the total amount of memory allocated to the load utility as a buffer. It is recommended that this buffer be several *extents* in size. An extent is the unit of movement for data within DB2®, and the extent size can be one or more 4KB pages. The DATA BUFFER parameter is useful when working with large objects (LOBs); it reduces I/O waiting time. The data buffer is allocated from the utility heap. Depending on the amount of storage available on your system, you should consider allocating more memory for use by the DB2 utilities. The database configuration parameter *util\_heap\_sz* can be modified accordingly. The default value for the Utility Heap Size configuration parameter is 5 000 4KB pages. Because load is only one of several utilities that use memory from the utility heap, it is recommended that no more than fifty percent of the pages defined by this parameter be available for the load utility, and that the utility heap be defined large enough.

### DISK\_PARALLELISM

The DISK\_PARALLELISM parameter specifies the number of processes or threads used by the load utility to write data records to disk. Use this parameter to exploit available containers when loading data, and significantly improve load performance. The maximum number allowed is the greater of four times the CPU\_PARALLELISM value (actually used by the load utility), or 50. By default, DISK\_PARALLELISM is equal to the sum of the table space containers on all table spaces containing objects for the table being loaded, except where this value exceeds the maximum number allowed.

### FASTPARSE

Use the fastparse file type modifier to reduce the data checking that is performed on user-supplied column values, and enhance performance. This option should only be used when the data being loaded is known to be valid. It can improve performance by about 10 or 20 percent.

### NONRECOVERABLE

Use this parameter if you do not need to be able to recover load transactions against a table. Load performance is enhanced, because no additional activity beyond the movement of data into the table is required, and the load operation completes without leaving the table spaces in backup pending state.

**Note:** When these load transactions are encountered during subsequent restore and rollforward recovery operations, the table is not updated, and is marked "invalid". Further actions against this table are ignored. After the rollforward operation is complete, the table can either be dropped or a LOAD TERMINATE command can be issued to bring it back online.

## NOROWWARNINGS

Use the `norowwarnings` file type modifier to suppress the recording of warnings about rejected rows, and enhance performance, if you anticipate a large number of warnings.

## ALLOW READ ACCESS

This option allows users to query a table while a load operation is in progress. The user will only be able to view data that existed in the table prior to the load operation. If the `INDEXING MODE INCREMENTAL` option is also specified, and the load operation fails, the subsequent load terminate operation might have to correct inconsistencies in the index. This requires an index scan which involves considerable I/O. If the `ALLOW READ ACCESS` option is also specified for the load terminate operation, the buffer pool will be used for I/O.

## SAVECOUNT

Use this parameter to set an interval for the establishment of consistency points during a load operation. The synchronization of activities performed to establish a consistency point takes time. If done too frequently, there will be a noticeable reduction in load performance. If a very large number of rows is to be loaded, it is recommended that a large `SAVECOUNT` value be specified (for example, a value of ten million in the case of a load operation involving 100 million records).

A `LOAD RESTART` operation will automatically continue from the last consistency point.

## STATISTICS YES

Use this parameter to collect data distribution and index statistics more efficiently than through invocation of the `runstats` utility following completion of the load operation, even though performance of the load operation itself will decrease (particularly when `DETAILED INDEXES ALL` is specified).

For optimal performance, applications require the best data distribution and index statistics possible. Once the statistics are updated, applications can use new access paths to the table data based on the latest statistics. New access paths to a table can be created by rebinding the application packages using the `DB2 BIND` command.

When loading data into large tables, it is recommended that a larger value for the `stat_heap_sz` (Statistics Heap Size) database configuration parameter be specified.

## USE <tablespaceName>

This parameter allows an index to be rebuilt in a system temporary table space and copied back to the index table space during the index copy phase of a load operation. When a load operation in `ALLOW READ ACCESS` mode fully rebuilds the indexes, the new indexes are built as a *shadow*. The original indexes are replaced by the new indexes at the end of the load operation.

By default, the *shadow* index is built in the same table space as the original index. This might cause resource problems as both the original and the *shadow* index will reside in the same table space simultaneously. If the *shadow* index is built in the same table space as the original index, the original index will be instantaneously replaced by the *shadow*. However, if the *shadow* index is built in a system temporary table space, the load operation will require an index copy phase which will copy the index from a system temporary table space to the index table space. There will be

considerable I/O involved in the copy. If either of the table spaces is a DMS table space, the I/O on the system temporary table space might not be sequential. The values specified by the DISK\_PARALLELISM option will be respected during the index copy phase.

#### **WARNINGCOUNT**

Use this parameter to specify the number of warnings that can be returned by the utility before a load operation is forced to terminate. If you are expecting only a few warnings or no warnings, set the WARNINGCOUNT parameter to approximately the number you are expecting, or to twenty if you are expecting no warnings. The load operation will stop after the WARNINGCOUNT number is reached. This gives you the opportunity to correct data (or to drop and then recreate the table being loaded) before attempting to complete the load operation. Although not having a direct effect on the performance of the load operation, the establishment of a WARNINGCOUNT threshold prevents you from having to wait until the entire load operation completes before determining that there is a problem.

#### **Related concepts:**

- “Multidimensional clustering considerations” on page 96
- “DB2 registry and environment variables” in the *Administration Guide: Performance*

#### **Related reference:**

- “util\_heap\_sz - Utility heap size configuration parameter” in the *Administration Guide: Performance*
- “stat\_heap\_sz - Statistics heap size configuration parameter” in the *Administration Guide: Performance*
- “SET INTEGRITY statement” in the *SQL Reference, Volume 2*
- “BIND Command” in the *Command Reference*
- “UPDATE DATABASE CONFIGURATION Command” in the *Command Reference*

---

## **Load - CLP Examples**

### **Example 1**

TABLE1 has 5 columns:

- COL1 VARCHAR 20 NOT NULL WITH DEFAULT
- COL2 SMALLINT
- COL3 CHAR 4
- COL4 CHAR 2 NOT NULL WITH DEFAULT
- COL5 CHAR 2 NOT NULL

ASCFE1 has 6 elements:

- ELE1 positions 01 to 20
- ELE2 positions 21 to 22
- ELE3 positions 23 to 23
- ELE4 positions 24 to 27
- ELE5 positions 28 to 31
- ELE6 positions 32 to 32
- ELE7 positions 33 to 40

Data Records:

```
1...5...10...15...20...25...30...35...40
Test data 1          XXN 123abcdN
Test data 2 and 3   QQY   XXN
Test data 4,5 and 6 WWN6789   Y
```

The following command loads the table from the file:

```
db2 load from ascfile1 of asc modified by striptblanks reflen=40
method L (1 20, 21 22, 24 27, 28 31)
null indicators (0,0,23,32)
insert into table1 (col1, col5, col2, col3)
```

#### Notes:

1. The specification of `striptblanks` in the `MODIFIED BY` parameter forces the truncation of blanks in `VARCHAR` columns (`COL1`, for example, which is 11, 17 and 19 bytes long, in rows 1, 2 and 3, respectively).
2. The specification of `reflen=40` in the `MODIFIED BY` parameter indicates that there is no new-line character at the end of each input record, and that each record is 40 bytes long. The last 8 bytes are not used to load the table.
3. Since `COL4` is not provided in the input file, it will be inserted into `TABLE1` with its default value (it is defined `NOT NULL WITH DEFAULT`).
4. Positions 23 and 32 are used to indicate whether `COL2` and `COL3` of `TABLE1` will be loaded `NULL` for a given row. If there is a `Y` in the column's null indicator position for a given record, the column will be `NULL`. If there is an `N`, the data values in the column's data positions of the input record (as defined in `L(.....)`) are used as the source of column data for the row. In this example, neither column in row 1 is `NULL`; `COL2` in row 2 is `NULL`; and `COL3` in row 3 is `NULL`.
5. In this example, the `NULL INDICATORS` for `COL1` and `COL5` are specified as 0 (zero), indicating that the data is not nullable.
6. The `NULL INDICATOR` for a given column can be anywhere in the input record, but the position must be specified, and the `Y` or `N` values must be supplied.

#### Example 2 (Using Dump Files)

Table `FRIENDS` is defined as:

```
table friends "( c1 INT NOT NULL, c2 INT, c3 CHAR(8) )"
```

If an attempt is made to load the following data records into this table,

```
23, 24, bobby
, 45, john
4,, mary
```

the second row is rejected because the first `INT` is `NULL`, and the column definition specifies `NOT NULL`. Columns which contain initial characters that are not consistent with the `DEL` format will generate an error, and the record will be rejected. Such records can be written to a dump file.

`DEL` data appearing in a column outside of character delimiters is ignored, but does generate a warning. For example:

```
22,34,"bob"
24,55,"sam" sdf
```

The utility will load "sam" in the third column of the table, and the characters "sdf" will be flagged in a warning. The record is not rejected. Another example:

22 3, 34,"bob"

The utility will load 22,34,"bob", and generate a warning that some data in column one following the 22 was ignored. The record is not rejected.

### Example 3 (Loading DATALINK Data)

The following command loads the table MOVIE TABLE from the input file del file1, which has data in the DEL format:

```
db2 load from del file1 of del
modified by d1del|
insert into movietable (actorname, description, url_making_of,
url_movie) datalink specification (dl_url_default_prefix
"http://narang"), (dl_url_replace_prefix "http://bomdel"
dl_url_suffix ".mpeg") for exception excptab
```

#### Notes:

1. The table has four columns:

actorname	VARCHAR(n)
description	VARCHAR(m)
url_making_of	DATALINK (with LINKTYPE URL)
url_movie	DATALINK (with LINKTYPE URL)

2. The DATALINK data in the input file has the vertical bar (|) character as the sub-field delimiter.
3. If any column value for url\_making\_of does not have the prefix character sequence, "http://narang" is used.
4. Each non-NULL column value for url\_movie will get "http://bomdel" as its prefix. Existing values are replaced.
5. Each non-NULL column value for url\_movie will get ".mpeg" appended to the path. For example, if a column value of url\_movie is "http://server1/x/y/z", it will be stored as "http://bomdel/x/y/z.mpeg"; if the value is "/x/y/z", it will be stored as "http://bomdel/x/y/z.mpeg".
6. If any unique index or DATALINK exception occurs while loading the table, the affected records are deleted from the table and put into the exception table excptab.

### Example 4 (Loading a Table with an Identity Column)

TABLE1 has 4 columns:

- C1 VARCHAR(30)
- C2 INT GENERATED BY DEFAULT AS IDENTITY
- C3 DECIMAL(7,2)
- C4 CHAR(1)

TABLE2 is the same as TABLE1, except that C2 is a GENERATED ALWAYS identity column.

Data records in DATAFILE1 (DEL format):

```
"Liszt"
"Hummel",,187.43, H
"Grieg",100, 66.34, G
"Satie",101, 818.23, I
```

Data records in DATAFILE2 (DEL format):

```
"Liszt", 74.49, A
"Hummel", 0.01, H
"Grieg", 66.34, G
"Satie", 818.23, I
```

**Notes:**

1. The following command generates identity values for rows 1 and 2, since no identity values are supplied in DATAFILE1 for those rows. Rows 3 and 4, however, are assigned the user-supplied identity values of 100 and 101, respectively.

```
db2 load from datafile1.del of del replace into table1
```

2. To load DATAFILE1 into TABLE1 so that identity values are generated for all rows, issue one of the following commands:

```
db2 load from datafile1.del of del method P(1, 3, 4)
replace into table1 (c1, c3, c4)
db2load from datafile1.del of del modified by identityignore
replace into table1
```

3. To load DATAFILE2 into TABLE1 so that identity values are generated for each row, issue one of the following commands:

```
db2 load from datafile2.del of del replace into table1 (c1, c3, c4)
db2 load from datafile2.del of del modified by identitymissing
replace into table1
```

4. To load DATAFILE1 into TABLE2 so that the identity values of 100 and 101 are assigned to rows 3 and 4, issue the following command:

```
db2 load from datafile1.del of del modified by identityoverride
replace into table2
```

In this case, rows 1 and 2 will be rejected, because the utility has been instructed to override system-generated identity values in favor of user-supplied values. If user-supplied values are not present, however, the row must be rejected, because identity columns are implicitly not NULL.

5. If DATAFILE1 is loaded into TABLE2 without using any of the identity-related file type modifiers, rows 1 and 2 will be loaded, but rows 3 and 4 will be rejected, because they supply their own non-NULL values, and the identity column is GENERATED ALWAYS.

**Example 5 (Loading from CURSOR)**

MY.TABLE1 has 3 columns:

- ONE INT
- TWO CHAR(10)
- THREE DATE

MY.TABLE2 has 3 columns:

- ONE INT
- TWO CHAR(10)
- THREE DATE

Cursor MYCURSOR is defined as follows:

```
declare mycursor cursor for select * from my.table1
```

The following command loads all the data from MY.TABLE1 into MY.TABLE2:

```
load from mycursor of cursor method P(1,2,3) insert into
my.table2(one,two,three)
```

**Notes:**

1. Only one cursor name can be specified in a single LOAD command. That is, load from mycurs1, mycurs2 of cursor... is not allowed.
2. P and N are the only valid METHOD values for loading from a cursor.
3. In this example, METHOD P and the insert column list (one,two,three) could have been omitted since they represent default values.
4. MY.TABLE1 can be a table, view, alias, or nickname.

**Related concepts:**

- “Load Overview” on page 74

**Related reference:**

- “LOAD QUERY” on page 121
- “Example partitioned database load sessions” on page 192
- “LOAD” on page 100



---

## Chapter 4. Loading data in a partitioned database environment

This chapter describes loading data in a partitioned database environment.

The following topics are covered:

- “Partitioned database load - overview”
- “Using load in a partitioned database environment” on page 179
- “Monitoring a partitioned database load using the LOAD QUERY command” on page 184
- “Restarting or terminating a load operation in a partitioned database environment” on page 186
- “Partitioned database load configuration options” on page 187
- “Example partitioned database load sessions” on page 192
- “Migration and back-level compatibility” on page 195
- “Loading data in a partitioned database environment - hints and tips” on page 197

---

### Partitioned database load - overview

In a partitioned database, large amounts of data are located across many partitions. Partitioning keys are used to determine on which database partition each portion of the data resides. The data must be *partitioned* before it can be loaded at the correct database partition. When loading tables in a partitioned database environment, the load utility can:

- Partition input data in parallel.
- Load data simultaneously on corresponding database partitions.
- Transfer data from one system to another system.

Partitioned database load operations take place in 2 phases: A setup phase, where partition resources such as table locks are acquired, and a load phase where the data is loaded into the partitions. You can use the ISOLATE\_PART\_ERRS option of the LOAD command to select how errors will be handled during either of these phases, and how errors on one or more of the partitions will affect the load operation on the partitions that are not experiencing errors.

When loading data into a partitioned database you can use one of the following modes:

- PARTITION\_AND\_LOAD. Data is partitioned (perhaps in parallel) and loaded simultaneously on the corresponding database partitions.
- PARTITION\_ONLY. Data is partitioned (perhaps in parallel) and the output is written to files in a specified location on each loading partition. Each file includes a partition header that specifies how the data was partitioned, and that the file can be loaded into the database using the LOAD\_ONLY mode.
- LOAD\_ONLY. Data is assumed to be already partitioned; the partition process is skipped, and the data is loaded simultaneously on the corresponding database partitions.

- **LOAD\_ONLY\_VERIFY\_PART.** Data is assumed to be already partitioned, but the data file does not contain a partition header. The partitioning process is skipped, and the data is loaded simultaneously on the corresponding database partitions. During the load operation, each row is checked to verify that it is on the correct partition. Rows containing partition violations are placed in a dumpfile if the *dumpfile* file type modifier is specified. Otherwise, the rows are discarded. If partition violations exist on a particular loading partition, a single warning will be written to the load message file for that partition.
- **ANALYZE.** An optimal partitioning map with even distribution across all database partitions is generated.

### Concepts and Terminology

The following terminology will be used when discussing the behavior and operation of the load utility in a partitioned database environment:

- The *coordinator partition* is the database partition to which the user connects to perform the load operation. In the **PARTITION\_AND\_LOAD**, **PARTITION\_ONLY**, and **ANALYZE** modes, it is assumed that the data file resides on this partition unless the **CLIENT** option of the load command is specified. Specifying the **CLIENT** option of the load command indicates that the data to be loaded resides on a remotely connected client.
- In the **PARTITION\_AND\_LOAD**, **PARTITION\_ONLY**, and **ANALYZE** modes, the *pre-partitioning agent* reads the user data and distributes it in round-robin fashion to the *partitioning agents* which will partition the data. This process is always performed on the coordinator partition. A maximum of one partitioning agent is allowed per partition for any load operation.
- In the **PARTITION\_AND\_LOAD**, **LOAD\_ONLY** and **LOAD\_ONLY\_VERIFY\_PART** modes, *load agents* run on each output partition and coordinate the loading of data to that partition.
- *Load to file agents* run on each output partition during a **PARTITION\_ONLY** load operation. They receive data from partitioning agents and write it to a file on their partition.
- A *file transfer command agent* runs on the coordinator partition and is responsible for executing a file transfer command.




Figure 7. *Partitioned Database Load Overview*. The source data is read by the pre-partitioning agent, approximately half of the data is sent to each of two partitioning agents which partition the data and send it to one of three database partitions. The load agent at each partition loads the data.

**Related concepts:**

- “Loading data in a partitioned database environment - hints and tips” on page 197
- “Monitoring a partitioned database load using the LOAD QUERY command” on page 184
- “Restarting or terminating a load operation in a partitioned database environment” on page 186

**Related reference:**

- “Partitioned database load configuration options” on page 187

## Using load in a partitioned database environment

**Prerequisites:**

Before loading a table in a partitioned database environment:

1. Ensure that the *svcsname* database manager configuration parameter and the **DB2COMM** profile registry variable are set correctly. This is important because the load utility uses TCP/IP to transfer data from the pre-partitioning agent to the partitioning agents, and from the partitioning agents to the loading partitions.
2. Before invoking the load utility, you must be connected to (or be able to implicitly connect to) the database into which the data will be loaded. Since the load utility will issue a COMMIT statement, you should complete all transactions and release any locks by issuing either a COMMIT or a ROLLBACK statement before beginning the load operation. If the PARTITION\_AND\_LOAD, PARTITION\_ONLY, or ANALYZE mode is being used, the data file that is being loaded must reside on this partition unless:
  - a. the CLIENT option has been specified, in which case the data must reside on the client machine;
  - b. the input source type is CURSOR, in which case there is no input file.

3. You might want to run the Design Advisor to determine the best partition for each table. For more information, see The Design Advisor.

### Restrictions:

The following restrictions apply when using the load utility to load data in a partitioned database environment:

- The location of the input files to the load operation cannot be a tape device.
- The ROWCOUNT option is not supported unless the ANALYZE mode is being used.
- If the target table has an identity column that is needed for partitioning and the *identityoverride* modifier is not specified, or if you are using multiple database partitions to partition and then load the data, the use of a SAVECOUNT greater than zero on the LOAD command is not supported.
- If an identity column forms part of the partitioning key, only PARTITION\_AND\_LOAD mode will be supported.
- The LOAD\_ONLY and LOAD\_ONLY\_VERIFY\_PART modes cannot be used with the CLIENT option of the LOAD command.
- The LOAD\_ONLY\_VERIFY\_PART mode cannot be used with the CURSOR input source type.
- The partition error isolation modes LOAD\_ERRS\_ONLY and SETUP\_AND\_LOAD\_ERRS cannot be used with the ALLOW READ ACCESS and COPY YES options of the LOAD command.
- Multiple load operations can load data into the same table concurrently if the partitions specified by the OUTPUT\_DBPARTNUMS and PARTITIONING\_DBPARTNUMS options do not overlap. For example, if a table is defined on partitions 0 through 3, one load operation can load data into partitions 0 and 1 while a second load operation can load data into partitions 2 and 3.
- Only Non-delimited ASCII (ASC) and Delimited ASCII (DEL) files can be partitioned. PC/IXF files cannot be partitioned. To load a PC/IXF file into a multiple partition table, you can first load it into a single-partition table, and then perform a load operation using the CURSOR file type to move the data into a multiple partition table. You can also load a PC/IXF file into a multiple partition table using load in LOAD\_ONLY\_VERIFY\_PART mode.

### Procedure:

The following examples illustrate how to use the LOAD command to initiate various types of load operations. The database used in the following examples has five partitions: 0, 1, 2, 3 and 4. Each partition has a local directory /udb/data/. Two tables, TABLE1 and TABLE2, are defined on partitions 0, 1, 3 and 4. When loading from a client, the user has access to a remote client that is not one of the database partitions.

### Loading from a Server Partition


#### Partition and Load Example

In this scenario you are connected to a partition that may or may not be a partition where TABLE1 is defined. The data file load.del resides in the current working directory of this partition. To load the data from load.del into all of the partitions where TABLE1 is defined, issue the following command: `LOAD FROM LOAD.DEL OF DEL REPLACE INTO TABLE1`

**Note:** In this example, default values will be used for all of the partitioned database configuration parameters: The MODE parameter will default to PARTITION\_AND\_LOAD, the OUTPUT\_DBPARTNUMS options will default to all nodes on which TABLE1 is defined, and the PARTITIONING\_DBPARTNUMS will default to the set of nodes selected according to the LOAD command rules for choosing partitioning nodes when none are specified.

To perform a load operation using nodes 3 and 4 as partitioning nodes, issue the following command:

```
LOAD FROM LOAD.DEL of DEL REPLACE INTO TABLE1
PARTITIONED DB CONFIG PARTITIONING_DBPARTNUMS (3,4)
```



*Figure 8. .* This diagram illustrates the behavior that will result when the above command is issued. Data is loaded into partitions 3 and 4.

### Partition Only Example


In this scenario you are connected to a partition that may or may not be a partition where TABLE1 is defined. The data file load.del resides in the current working directory of this partition. To partition (but not load) load.del to all the database partitions on which TABLE1 is defined, using partitions 3 and 4 as partitioning nodes, issue the following command:

```
LOAD FROM LOAD.DEL of DEL REPLACE INTO TABLE1
PARTITIONED DB CONFIG MODE PARTITION_ONLY
PART_FILE_LOCATION /udb/data
PARTITIONING_DBPARTNUMS (3,4)
```

This will result in a file `load.del.xxx` being stored in the `/udb/data` directory on each partition, where `xxx` is a three-digit representation of the partition number.

To partition the `load.del` file to partitions 1 and 3, using only 1 partitioning agent running on partition 0 (which is the default for `PARTITIONING_DBPARTNUMS`), issue the following command:

```
LOAD FROM LOAD.DEL OF DEL REPLACE INTO TABLE1
PARTITIONED DB CONFIG MODE PARTITION_ONLY
PART_FILE_LOCATION /udb/data
OUTPUT_DBPARTNUMS (1,3)
```



*Figure 9.* This diagram illustrates the behavior that will result when the above command is issued. Data is loaded into partitions 1 and 3, using 1 partitioning agent running on partition 0.

### Load Only Example

If you have already performed a load operation in the `PARTITION_ONLY` mode and want to load the partitioned files in the `/udb/data` directory of each loading partition to all the partitions on which `TABLE1` is defined, issue the following command:

```
LOAD FROM LOAD.DEL OF DEL REPLACE INTO TABLE1
PARTITIONED DB CONFIG MODE LOAD_ONLY
PART_FILE_LOCATION /udb/data
```




Figure 10. . This diagram illustrates the behavior that will result when the above command is issued. Partitioned data is loaded to all partitions where TABLE1 is defined.

To load into partition 4 only, issue the following command:

```
LOAD FROM LOAD.DEL OF DEL REPLACE INTO TABLE1
PARTITIONED DB CONFIG MODE LOAD_ONLY
PART_FILE_LOCATION /udb/data
OUTPUT_DBPARTNUMS (4)
```

### Loading Pre-partitioned Files Without Partition Map Headers

The LOAD command can be used to load data files without partition headers directly into several database partitions. If the data files exist in the /udb/data directory on each partition where TABLE1 is defined and have the name load.del.xxx, where xxx is the partition number, the files can be loaded by issuing the following command:

```
LOAD FROM LOAD.DEL OF DEL modified by dumpfile=rejected.rows
REPLACE INTO TABLE1
PARTITIONED DB CONFIG MODE LOAD_ONLY_VERIFY_PART
PART_FILE_LOCATION /udb/data
```

To load the data into partition 1 only, issue the following command:

```
LOAD FROM LOAD.DEL OF DEL modified by dumpfile=rejected.rows
REPLACE INTO TABLE1
PARTITIONED DB CONFIG MODE LOAD_ONLY_VERIFY_PART
PART_FILE_LOCATION /udb/data
OUTPUT_DBPARTNUMS (1)
```

**Note:** Rows that do not belong on the partition from which they were loaded will be rejected and put into the dumpfile, if one has been specified.

### Loading from a Remote Client to a Partitioned Database

To load data into a partitioned database from a file that is on a remote client, you must specify the CLIENT option of the LOAD command to indicate that the data file is not on a server partition. For example:

```
LOAD CLIENT FROM LOAD.DEL OF DEL REPLACE INTO TABLE1
```

**Note:** You cannot use the LOAD\_ONLY or LOAD\_ONLY\_VERIFY\_PART modes with the CLIENT option.

### Loading from a Cursor

As in single partition databases, you can load from a cursor into a multi-partition database. In this example, for the PARTITION\_ONLY and LOAD\_ONLY modes, the PART\_FILE\_LOCATION option must specify a fully qualified file name. This name will be the fully qualified base file name of the partitioned files that are created or loaded on each output partition. Multiple files may be created with the specified base name if there are LOB columns in the target table.

To partition all the rows in the answer set of the statement SELECT \* FROM TABLE1 to a file on each partition named /udb/data/select.out.xxx (where xxx is the node number), for future loading into TABLE2, issue the following commands from the DB2 Command Line Processor:

```
DECLARE C1 CURSOR FOR SELECT * FROM TABLE1

LOAD FROM C1 OF CURSOR REPLACE INTO TABLE2
      PARTITIONED DB CONFIG MODE PARTITION_ONLY
      PART_FILE_LOCATION /udb/data/select.out
```

The data files produced by the above operation can then be loaded by issuing the following LOAD command:

```
LOAD FROM C1 OF CURSOR REPLACE INTO TABLE2
      PARTITIONED CB CONFIG MODE LOAD_ONLY
      PART_FILE_LOCATION /udb/data/select.out
```

### Related concepts:

- “The Design Advisor” in the *Administration Guide: Performance*
- “Moving data using the cursor file type” on page 226

### Related reference:

- “db2Load - Load” on page 123

---

## Monitoring a partitioned database load using the LOAD QUERY command

### Message Files Produced During a Partitioned Database Load

During a load operation, message files are created by some of the load processes on the partitions where they are being executed. These files store all information, warning and error messages produced during the execution of the process. The load processes that produce message files that can be viewed by the user are the load agent, pre-partitioning agent and partitioning agent.

Users can connect to individual partitions during a load operation and issue the LOAD QUERY command against the target table. When issued from the CLP, this command will display the contents of all the message files that currently reside on that partition for the table that is specified in the LOAD QUERY command.

For example, table TABLE1 is defined on partitions 0 through 3 in database WSDb. A user is connected to partition 0 and issues the following LOAD command:

```
load from load.del of del replace into table1 partitioned db config
partitioning_dbpartnums (1)
```

This command will initiate a load operation that includes load agents running on partitions 0, 1, 2 and 3; a partitioning agent running on partition 1; and a pre-partitioning agent running on partition 0.

Partition 0 will contain one message file for the pre-partitioning agent and one for the load agent on that partition. To view the contents of these files at the same time, start a new session and issue the following commands from the CLP:

```
set client connect_node 0
connect to wsdb
load query table table1
```

Partition 1 will contain one file for the load agent and one for the partitioning agent. To view the contents of these files, start a new session and issue the following commands from the CLP:

```
set client connect_node 1
connect to wsdb
load query table table1
```

**Note:** The messages generated by the STATUS\_INTERVAL load configuration option will appear in the pre-partitioning agent message file. To view these message during a load operation, you must connect to the coordinator partition and issue the LOAD QUERY command.

### Saving the Contents of Message Files

If a load operation is initiated through the load API (**db2Load**), the messages option (piLocalMsgFileName) must be specified and the message files will be brought from the server to the client and stored for the user to view.

For partitioned database load operations initiated from the CLP, the message files will not be displayed to the console or retained. To save or view the contents of these files after a partitioned database load has completed, the MESSAGES option of the LOAD command must be specified. If this option is used, once the load operation has completed the message files on each partition will be transferred to the client machine and stored in files using the base name indicated by the MESSAGES option. For partitioned database load operations, the name of the file corresponding to the load process that produced it is listed below:

Process Type	File Name
Load Agent	<message-file-name>.LOAD.<partition-number>
Partitioning Agent	<message-file-name>.PART.<partition-number>
Pre-partitioning Agent	<message-file-name>.PREP.<partition-number>

For example, if the MESSAGES option specifies /wsdb/messages/load, the load agent message file for partition 2 will be /wsdb/messages/load.LOAD.002.

**Note:** It is strongly recommended that the MESSAGES option be used for partitioned database load operations initiated from the CLP.

**Related reference:**

- “db2LoadQuery - Load Query” on page 145

---

## Restarting or terminating a load operation in a partitioned database environment

The load process in a partitioned database environment consists of two stages: the setup stage where partition-level resources such as table locks on output partitions are acquired, and the load stage where data is formatted and loaded into tables on the partitions. The four partition error isolation modes (LOAD\_ERRS\_ONLY, SETUP\_ERRS\_ONLY, SETUP\_AND\_LOAD\_ERRS, and NO\_ISOLATION) affect the behavior of load restart and terminate operations when there are errors during one or both of these stages. In general, if a failure occurs during the setup stage, restart and terminate operations are not necessary. However, a failure during the load stage will require a LOAD RESTART or a LOAD TERMINATE on all partitions involved in the load operation.

### Failures During the Setup Stage

When a load operation fails on at least one partition during the setup stage and the setup stage errors are not being isolated (that is, the error isolation mode is either LOAD\_ERRS\_ONLY or NO\_ISOLATION), the entire load operation will be aborted and the state of the table on each partition will be rolled back to the state it was in prior to the load operation. In this case, there is no need to issue a LOAD RESTART or LOAD TERMINATE command.

When a load operation fails on at least one partition during the initial setup stage and setup stage errors are being isolated (that is, the error isolation mode is either SETUP\_ERRS\_ONLY or SETUP\_AND\_LOAD\_ERRS), the load operation will continue on the partitions where the setup stage was successful, but the table on each of the failing partitions is rolled back to the state it was in prior to the load operation. In this case, there is no need to perform a load restart or terminate operation, unless there is also a failure during the load stage.

To complete the load process on the partitions where the load operation failed during the setup stage, issue a LOAD REPLACE or LOAD INSERT command and use the OUTPUT\_DBPARTNUMS option to specify only the partition numbers of the partitions that failed during the original load operation.

For example, table TABLE1 is defined on partitions 0 through 3 in database WSDB. The following command is issued:

```
load from load.del of del replace into table1 partitioned db config
  isolate_part_errs setup_and_load_errs
```

During the set up stage of the load operation there is a failure on partitions 1 and 3. Since setup stage errors are being isolated, the load operation will complete successfully and data will be loaded on partitions 0 and 2. To complete the load operation by loading data on partitions 1 and 3, issue the following command:

```
load from load.del of del replace into table1 partitioned db config
  output_dbpartnums (1, 3)
```

### Failures During the Load Stage

If a load operation fails on at least one partition during the load stage of a partitioned database load operation, a LOAD RESTART or LOAD TERMINATE command must be issued on all partitions involved in the load operation whether or not they encountered an error while loading data. This is necessary because loading data in a partitioned database environment is done through a single transaction. If a load restart operation is initiated, loading will continue where it left off on all partitions.

For example, table TABLE1 is defined on partitions 0 through 3 in database WSDB. The following command is issued:

```
load from load1.del of del replace into table1 partitioned db config
isolate_part_errs no_isolation
```

During the load stage of the load operation there is a failure on partitions 1 and 3. To resume the load operation, the LOAD RESTART command must specify the same set of output partitions as the original command since the load operation must be restarted on all partitions:

```
load from load.del of del restart into table1 partitioned db config
isolate_part_errs no_isolation
```

**Note:** For load restart operations, the options specified in the LOAD RESTART command will be honored, so it is important that they are identical to the ones specified in the original LOAD command.

If a LOAD TERMINATE command is used when a partitioned database load operation fails during the load stage, all work done in the previous load operation will be lost and the table on each partition will be returned to the state it was in prior to the initial load operation.

For example, table TABLE1 is defined on partitions 0 through 3 in database WSDB. The following command is issued:

```
load from load.del of del replace into table1 partitioned db config
isolate_part_errs no_isolation
```

If a failure occurs during the load stage, the load operation can be terminated by issuing a LOAD TERMINATE command that specifies the same output parameters as the original command:

```
load from load.del of del terminate into table1 partitioned db config
isolate_part_errs no_isolation
```

**Related concepts:**

- “Restarting an interrupted load operation” on page 97
- “Partitioned database load - overview” on page 177

---

## Partitioned database load configuration options

### HOSTNAME X

This option is only relevant when used with the FILE\_TRANSFER\_CMD option. X is the name of the remote machine where the data file resides. This can be a z/OS host or another workstation. If this option is not specified, and the FILE\_TRANSFER\_CMD option is specified, the hostname *nohost* will be used.

### FILE\_TRANSFER\_CMD X

Specifies a file executable, batch file, or script that will be called before data is loaded onto any partitions. The value specified must be a fully

qualified path. The full path, including the execution file name, must not exceed 254 characters. The command will be invoked with the following syntax:

```
<COMMAND> <logpath> <hostname> <basepipename> <nummedia>  
<source media list>
```

Where:

**<COMMAND>**

Is the command specified by the FILE:TRANSFER:CMD modifier.

**<logpath>**

Is the log path for the file from which the data is being loaded. Diagnostic or temporary data can be written to this path.

**<hostname>**

Is the value of the HOSTNAME option.

**<basepipename>**

Is the base name for named pipes that the load operation will create and expect to receive data from. One pipe is created for every source file on the LOAD command. Each of these files ends with .xxx, where xxx is the index of the source file for the LOAD command. For example, if there are 2 source files for the LOAD command, and the <basepipename> is pipe123, two named pipes would be created: pipe123.000 and pipe123.001. The <COMMAND> file will populate these named pipes with user data.

**<nummedia>**

Specifies the number of media arguments which follow.

**<source media list>**

Is the list of source files specified in the LOAD command. Each source file must be placed inside double quotation marks.

**PART\_FILE\_LOCATION X**

In the PARTITION\_ONLY, LOAD\_ONLY, and LOAD\_ONLY\_VERIFY\_PART modes, this parameter can be used to specify the location of the partitioned files. This location must exist on each partition specified by the OUTPUT\_DBPARTNUMS option. If the location specified is a relative path name, the path will be appended to the current directory to create the location for the partitioned files.

For the CURSOR file type, this option must be specified, and the location must refer to a fully qualified file name. This name will be the fully qualified base file name of the partitioned files that are created on each output partition in the PARTITION\_ONLY mode, or the location of the files to be read from for each partition in the LOAD\_ONLY mode. When using the PARTITION\_ONLY mode, multiple files can be created with the specified base name if the target table contains LOB columns.

For file types other than CURSOR, if this option is not specified, the current directory will be used for the partitioned files.

**OUTPUT\_DBPARTNUMS X**

X represents a list of partition numbers. The partition numbers represent the database partitions on which the load operation is to be performed. The partition numbers must be a subset of the database partitions on which the table is defined. The default is that all database partitions will



PART\_FILE\_LOCATION option for details on how to specify the location of the partition file for each partition.

**Notes:**

1. This mode cannot be used for a CLI load operation, or when the CLIENT option of LOAD command is specified.
  2. If the table contains an identity column that is needed for partitioning, then this mode is not supported, unless the *identityoverride* modifier is specified.
- LOAD\_ONLY\_VERIFY\_PART. Data is assumed to be already partitioned, but the data file does not contain a partition header. The partitioning process is skipped, and the data is loaded simultaneously on the corresponding database partitions. During the load operation, each row is checked to verify that it is on the correct partition. Rows containing partition violations are placed in a dumpfile if the *dumpfile* file type modifier is specified. Otherwise, the rows are discarded. If partition violations exist on a particular loading partition, a single warning will be written to the load message file for that partition. The format of the input file name for each partition should be *filename.xxx*, where *filename* is the name of the file specified in the LOAD command and *xxx* is the 3-digit partition number. See the PART\_FILE\_LOCATION option for details on how to specify the location of the partition file for each partition.

**Notes:**

1. This mode cannot be used for a CLI load operation, or when the CLIENT option of LOAD command is specified.
  2. If the table contains an identity column that is needed for partitioning, then this mode is not supported, unless the *identityoverride* modifier is specified.
- ANALYZE. An optimal partitioning map with even distribution across all database partitions is generated.

**MAX\_NUM\_PART\_AGENTS X**

Specifies the maximum numbers of partitioning agents to be used in a load session. The default 25.

**ISOLATE\_PART\_ERRS X**

Indicates how the load operation will react to errors that occur on individual partitions. The default is LOAD\_ERRS\_ONLY, unless both the ALLOW READ ACCESS and COPY YES options of the LOAD command are specified, in which case the default is NO\_ISOLATION. Valid values are:

- SETUP\_ERRS\_ONLY. Errors that occur on a partition during setup, such as problems accessing a partition, or problems accessing a table space or table on a partition, will cause the load operation to stop on the failing partitions but to continue on the remaining partitions. Errors that occur on a partition while data is being loaded will cause the entire operation to fail and roll back to the last point of consistency on each partition.
- LOAD\_ERRS\_ONLY. Errors that occur on a partition during setup will cause the entire load operation to fail. When an error occurs while data is being loaded the partitions with errors will be rolled back to their last point of consistency. The load operation will continue on the remaining partitions until a failure occurs or until all the data is loaded. On the partitions where all of the data was loaded, the data will not be visible following the load operation. Because of the errors in the other partitions

the transaction will be aborted. Data on all of the partitions will remain invisible until a load restart operation is performed. This will make the newly loaded data visible on the partitions where load operation completed and resume the load operation on partitions that experienced an error.

**Note:** This mode cannot be used when both the ALLOW READ ACCESS and the COPY YES options of the LOAD command are specified.

- **SETUP\_AND\_LOAD\_ERRS.** In this mode, partition-level errors during setup or loading data cause processing to stop only on the affected partitions. As with the LOAD\_ERRS\_ONLY mode, when partition errors do occur while data is being loaded, the data on all partitions will remain invisible until a load restart operation is performed.

**Note:** This mode cannot be used when both the ALLOW READ ACCESS and the COPY YES options of the LOAD command are specified.

- **NO\_ISOLATION.** Any error during the load operation causes the transaction to fail.

#### **STATUS\_INTERVAL X**

X represents how often you will be notified of the volume of data that has been read. The unit of measurement is megabytes (MB). The default is 100 MB. Valid values are whole numbers from 1 to 4000.

#### **PORT\_RANGE X**

X represents the range of TCP ports used to create sockets for internal communications. The default range is from 6000 to 6063. If defined at the time of invocation, the value of the DB2ATLD\_PORTS DB2 registry variable will replace the value of the PORT\_RANGE load configuration option. For the DB2ATLD\_PORTS registry variable, the range should be provided in the following format:

<lower-port-number>:<higher-port-number>

From the CLP, the format is:

( lower-port-number, higher-port-number )

#### **CHECK\_TRUNCATION**

Specifies that the program should check for truncation of data records at input/output. The default behavior is that data will not be checked for truncation at input/output.

#### **MAP\_FILE\_INPUT X**

X specifies the input file name for the partitioning map. This parameter must be specified if the partitioning map is customized, as it points to the file containing the customized partitioning map. A customized partitioning map can be created by using the **db2gpmap** program to extract the map from the database system catalog table, or by using the ANALYZE mode of the LOAD command to generate an optimal map. The map generated by using the ANALYZE mode must be moved to each database partition in your database before the load operation can proceed.

#### **MAP\_FILE\_OUTPUT X**

X represents the output filename for the partitioning map. This parameter should be used when the ANALYZE mode is specified. An optimal partitioning map with even distribution across all database partitions is

generated. If this modifier is not specified and the ANALYZE mode is specified, the program exits with an error.

#### TRACE X

Specifies the number of records to trace when you require a review of a dump of the data conversion process and the output of the hashing values. The default is 0.

#### NEWLINE

Used when the input data file is an ASC file with each record delimited by a new line character and the RecLen parameter of the LOAD command is specified. When this option is specified, each record will be checked for a new line character. The record length, as specified in the RecLen parameter, will also be checked.

#### DISTFILE X

If this option is specified, the LOAD utility will generate a partition distribution file with the given name. The partition distribution file contains 4096 integers: one for each entry in the target table's partition map. Each integer in the file represents the number of rows in the input files being loaded that hashed to the corresponding partition map entry. This information can help you identify skew in your data and also help you decide whether a new partition map should be generated for the table using the ANALYZE mode of the utility. If this option is not specified, the default behaviour of the Load utility is to not generate the distribution file.

**Note:** When this option is specified, a maximum of one partitioning agent will be used for the load operation. If multiple partitioning agents are explicitly requested by the user, only one will be used.

#### OMIT\_HEADER

Specifies that a partition map header should not be included in the partition file. If not specified, a header will be generated.

#### RUN\_STAT\_DBPARTNUM X

If the STATISTICS YES parameter has been specified in the LOAD command, statistics will be collected only on one database partition. This parameter specifies on which database partition to collect statistics. If the value is -1 or not specified at all, statistics will be collected on the first database partition in output partition list.

#### Related tasks:

- "Using load in a partitioned database environment" on page 179

#### Related reference:

- "REDISTRIBUTE DATABASE PARTITION GROUP Command" in the *Command Reference*
- "LOAD" on page 100

---

## Example partitioned database load sessions

In the following examples, the database has 4 partitions numbered 0 through 4. Database WSDB is defined on all of the partitions, and table TABLE1 resides in the default node group which is also defined on all of the partitions.

### Example 1

To load data into TABLE1 from the user data file load.del which resides on partition 0, connect to partition 0 and then issue the following command:

```
load from load.del of del replace into table1
```

If the load operation is successful, the output will be as follows:

Agent Type	Node	SQL Code	Result
LOAD	000	+00000000	Success.
LOAD	001	+00000000	Success.
LOAD	002	+00000000	Success.
LOAD	003	+00000000	Success.
PARTITION	001	+00000000	Success.
PRE_PARTITION	000	+00000000	Success.
RESULTS:	4 of 4 LOADs completed successfully.		

```
Summary of Partitioning Agents:
Rows Read           = 100000
Rows Rejected       = 0
Rows Partitioned    = 100000
```

```
Summary of LOAD Agents:
Number of rows read   = 100000
Number of rows skipped = 0
Number of rows loaded = 100000
Number of rows rejected = 0
Number of rows deleted = 0
Number of rows committed = 100000
```

The output indicates that there was one load agent on each partition and each ran successfully. It also shows that there was one pre-partitioning agent running on the coordinator partition and one partitioning agent running on partition 1. These processes completed successfully with a normal SQL return code of 0. The statistical summary shows that the pre-partitioning agent read 100,000 rows, the partitioning agent partitioned 100,000 rows, and the sum of all rows loaded by the load agents is 100,000.

## Example 2

In the following example, data is loaded into TABLE1 in the PARTITION\_ONLY mode. The partitioned output files will be stored on each of the output partitions in the directory /udb/data:

```
load from load.del of del replace into table1 partitioned db config mode
partition_only part_file_location /udb/data
```

The output from the load command will be as follows:

Agent Type	Node	SQL Code	Result
LOAD_TO_FILE	000	+00000000	Success.
LOAD_TO_FILE	001	+00000000	Success.
LOAD_TO_FILE	002	+00000000	Success.
LOAD_TO_FILE	003	+00000000	Success.

PARTITION	001	+00000000	Success.
PRE_PARTITION	000	+00000000	Success.

Summary of Partitioning Agents:  
 Rows Read = 100000  
 Rows Rejected = 0  
 Rows Partitioned = 100000

The output indicates that there was a load-to-file agent running on each output node, and these agents ran successfully. There was a pre-partitioning agent on the coordinator partition, and a partitioning agent running on node 1. The statistical summary indicates that 100,000 rows were successfully read by the pre-partitioning agent and 100,000 rows were successfully partitioned by the partitioning agent. Since no rows were loaded into the table, no summary of the number of rows loaded appears.

### Example 3

To load the files that were generated during the PARTITION\_ONLY load operation above, issue the following command:

```
load from load.del of del replace into table1 partitioned db config mode
load_only part_file_location /udb/data
```

The output from the load command will be as follows::

Agent Type	Node	SQL Code	Result
LOAD	000	+00000000	Success.
LOAD	001	+00000000	Success.
LOAD	002	+00000000	Success.
LOAD	003	+00000000	Success.
RESULTS:	4 of 4 LOADs completed successfully.		

Summary of LOAD Agents:  
 Number of rows read = 100000  
 Number of rows skipped = 0  
 Number of rows loaded = 100000  
 Number of rows rejected = 0  
 Number of rows deleted = 0  
 Number of rows committed = 100000

The output indicates that the load agents on each output partition ran successfully and that the sum of the number of rows loaded by all load agents is 100,000. No summary of rows partitioned is indicated since partitioning was not performed.

### Example 4 - Failed Load Operation

If the following LOAD command is issued:

```
load from load.del of del replace into table1
```

and one of the loading partitions runs out of space in the table space during the load operation, the following output will be returned:

```
SQL0289N Unable to allocate new pages in table space "DMS4KT".
SQLSTATE=57011
```

Agent Type	Node	SQL Code	Result
LOAD	000	+00000000	Success.
LOAD	001	-00000289	Error. May require RESTART.
LOAD	002	+00000000	Success.
LOAD	003	+00000000	Success.
PARTITION	001	+00000000	Success.
PRE_PARTITION	000	+00000000	Success.
RESULTS:	3 of 4 LOADs completed successfully.		

Summary of Partitioning Agents:

```
Rows Read           = 0
Rows Rejected       = 0
Rows Partitioned    = 0
```

Summary of LOAD Agents:

```
Number of rows read      = 0
Number of rows skipped   = 0
Number of rows loaded    = 0
Number of rows rejected  = 0
Number of rows deleted   = 0
Number of rows committed = 0
```

The output indicates that the load operation returned error SQL0289. The partition summary indicates that partition 1 ran out of space. Since the default error isolation mode is NO\_ISOLATION, the load operation will be aborted on all partitions and a load restart or load terminate operation must be invoked. If additional space is added to the containers of the table space on partition 1, the load operation can be restarted as follows:

```
load from load.del of del restart into table1
```

**Related tasks:**

- “Using load in a partitioned database environment” on page 179

**Related reference:**

- “LOAD” on page 100

---

## Migration and back-level compatibility

### Using the LOAD Command in a Partitioned Database Environment

In Version 8 changes have been made to the LOAD command that will replace the functionality of the `db2atld` utility. As a result, you will notice some differences in the terminology being used.

The `db2atld` utility referred to a *splitter* and a *split file* (the output of the splitter). The equivalent when using the LOAD command is the *partitioning agent* and the *partition file*. Also, when using the LOAD command we refer to the data file being *partitioned not split*. The load modes and configuration options are named to reflect this change. For example, where the AutoLoader had the SPLIT\_ONLY mode and

the SPLIT\_NODES option, the LOAD command now has the PARTITION\_ONLY mode and the PARTITIONING\_DBPARTNUMS option.

The equivalent of the FORCE option of the AutoLoader is the ISOLATE\_PART\_ERRS load configuration option. This option allows users to specify four types of partition error isolation. One of them (SETUP\_AND\_LOAD\_ERRS) is similar to the error isolation offered by the FORCE YES option.

### Using db2atld

The **db2atld** utility is still available and it accepts a configuration file with the same syntax it did prior to Version 8. Consider the following when using **db2atld**:

1. **db2atld** will now only establish one connection when loading into multi-partition databases. Prior to Version 8, the **db2atld** established one connection per output partition.
2. **db2atld** will use the same, single transaction model as the load utility when used in a partitioned database environment.
3. The LOAD\_ONLY\_VERIFY\_PART mode and any other new features provided in the enhanced load utility are not available when initiating a partitioned database load via the **db2atld** executable.
4. All previously supported AutoLoader configuration parameters are recognized.
5. Information displayed on the console by **db2atld** is now slightly different. For example, in SPLIT\_AND\_LOAD mode the partitioning statistics and loading statistics are now always displayed. Previously, they were only displayed when there was a discrepancy between the statistics. Further, status interval information is not dumped to the console during the load operation but is instead dumped to the pre-partitioning agent message file, which is called "<messagefile>.PREP.<nodenum>." Status information regarding the spawning of the splitter processes and loading processes is no longer available.
6. It is no longer necessary to launch the **db2atld** executable from a path that is cross mounted.
7. When loading data in a partitioned database environment, the maximum number of input sources is 999.
8. Prior to Version 8, when the LOAD\_ONLY mode of the **db2atld** utility was used, the names of the split file for each partition could have the extension .00xxx or .xxx, where xxx is the partition number. In Version 8 or later, the .00xxx extension is no longer supported. You can only specify a 3-digit extension (.xxx).

### Reverting to pre-Version 8 Load behavior Using the DB2®\_PARTITIONEDLOAD\_DEFAULT registry variable

Prior to Version 8, you could load a single partition of a multi-partition database using the load utility as long as the input data file contained partition header information that was valid for the partition being loaded. This header was usually created in the SPLIT\_ONLY mode of the AutoLoader or through the **db2split** utility. The partition header would be verified by the load utility before the remaining data was loaded. For tables residing in a single partition database partition group in a EEE environment, a data file with no partition header information could be loaded as long as the noheader file type modifier was specified.

The behavior of the LOAD command has since changed. In a partitioned database environment, when no partitioned database load configuration options are specified, it is now assumed that the load operation will take place on all partitions on which the table is defined. The input file does not require a partition header, and the MODE option defaults to PARTITION\_AND\_LOAD. To load a single partition, the OUTPUT\_DBPARTNUMS option must be specified.

It is possible to maintain the pre-Version 8 behavior of the LOAD command in a partitioned database environment. This would allow you to load a file with a valid partition header into a single database partition without specifying any extra partitioned database configuration options. You can do this by setting the value of the DB2\_PARTITIONEDLOAD\_DEFAULT registry variable to NO. You may want to use this option if you want to avoid modifying existing scripts that issue the LOAD command against single database partitions. For example, to load a partitioned file into partition 3 of a table that resides in a 4 partition nodegroup, issue the following command:

```
db2set DB2_PARTITIONEDLOAD_DEFAULT=NO
```

Then issue the following commands from the DB2 Command Line Processor:

```
CONNECT RESET

SET CLIENT CONNECT_NODE 3

CONNECT TO DB MYDB

LOAD FROM LOAD.DEL OF DEL REPLACE INTO TABLE1
```

**Related reference:**

- “LOAD” on page 100

---

## Loading data in a partitioned database environment - hints and tips

Following is some information to consider before loading a table in a partitioned database environment:

- Familiarize yourself with the partitioned load configuration options by using the utility with small amounts of data.
- If the input data is already sorted, or in some chosen order, and you wish to maintain that order during the loading process, only one database partition should be used for partitioning. Parallel partitioning cannot guarantee that the data will be loaded in the same order it was received. The load utility will choose a single partitioning agent by default if the anyorder modifier is not specified on the LOAD command.
- If large objects (LOBs) are being loaded from separate files (that is, if you are using the lobinfile modifier through the load utility), all directories containing the LOB files must be read-accessible to all the database partitions where loading is taking place. The LOAD *lob-path* parameter must be fully qualified when working with LOBs.
- You can force a partitioned database job to continue even if the load operation detects (at startup time) that some loading partitions or associated table spaces or tables are offline, by setting the ISOLATE\_PART\_ERRS option to SETUP\_ERRS\_ONLY or SETUP\_AND\_LOAD\_ERRS.
- Use the STATUS\_INTERVAL partitioned load configuration option to monitor the progress of a partitioned database load job. The load operation produces messages at specified intervals indicating how many megabytes of data have

been read by the pre-partitioning agent. These messages are dumped to the pre-partitioning agent message file. To view the contents of this file during the load operation, connect to the coordinator partition and issue a LOAD QUERY command against the target table.

- Better performance can be expected if the partitioning nodes (as defined by the PARTITIONING\_DBPARTNUMS option) are different from the loading partitions (as defined by the OUTPUT\_DBPARTNUMS option), since there is less contention for CPU cycles. When loading data into a partitioned database, the load utility itself should be invoked on a database partition that is not participating in either the partitioning or the loading operation.
- Specifying the MESSAGES parameter in the LOAD command will save the messages files from the pre-partitioning, partitioning, and load agents for reference at the end of the load operation. To view the contents of these files during a load operation, connect to the desired partition and issue a LOAD QUERY command against the target table.
- The load utility chooses only one output database partition on which to collect statistics. The RUN\_STAT\_DBPARTNUM partitioned load database configuration option can be used to specify that partition.
- Before loading data in a partitioned database environment, you might want to run the Design Advisor to determine the best partition for each table. For more information, see The Design Advisor.

### Troubleshooting

If the load utility is hanging, you can:

- Use the STATUS\_INTERVAL parameter to monitor the progress of a partitioned database load operation. The status interval information is dumped to the pre-partitioning agent message file on the coordinator partition.
- Check the partitioning agent messages file to see the status of the partitioning agent processes on each partitioning database partition. If the load is proceeding with no errors, and the TRACE option has been set, there should be trace messages for a number of records in these message files.
- Check the load messages file to see if there are any load error messages.

**Note:** You must specify the MESSAGES option of the LOAD command in order for these files to exist.

- Interrupt the current load operation if you find errors suggesting that one of the load processes encountered errors.

### Related reference:

- “LOAD QUERY” on page 121
- “LOAD” on page 100

---

## Chapter 5. Moving DB2 Data Links Manager Data

This chapter describes how to use the DB2 export, import, and load utilities to move DB2 Data Links Manager data.

For information about the file formats that you can use with these utilities, see “Export/Import/Load Utility File Formats” on page 243.


The following topics are covered:

- “Moving DB2 Data Links Manager Data Using Export - Concepts”
- “Using export to move DB2 Data Links Manager data” on page 201
- “Using import to move DB2 Data Links Manager data” on page 202
- “Using load to move DB2 Data Links Manager data” on page 203.

---

### Moving DB2 Data Links Manager Data Using Export - Concepts

Since table data resides in the database, and the files referred to by DATALINK columns reside on Data Links servers, the export utility must move both the database data, and the data files on the corresponding Data Links servers. To do this, the export utility produces one control file per Data Links server. The name of the control file is the same as the name of the Data Links server. The control files are created in a new directory that has the name `d1fm/YYYYMMDD/HHMMSS`, where `YYYYMMDD` represents *YearMonthDay*, and `HHMMSS` represents *HourMinuteSecond*. This directory is created under the same directory in which the export data file is created. A control file lists the names of the corresponding DB2 Data Links Manager files that are referenced by the DATALINK columns of the rows that are exported.



*Figure 11. Moving DB2 Data Links Manager Data.* Since table data resides in the database, and the files referred to by DATALINK columns reside on Data Links servers, the export, import, and load utilities must move both the database data, and the data files on the corresponding Data Links servers.

On Windows<sup>®</sup> operating systems, the export utility produces only one control file for all Data Links servers. The name of this control file is `ctrlfile.lst`. It is created in a new directory that has the name `d1fm/YYYYMMDD/HHMMSS`. This directory is created under the same directory in which the export data file is created. The control file lists the URLs of all DB2 Data Links Manager files that are referenced by the DATALINK columns of the rows that are exported.

DATALINK values that have the NO LINK CONTROL property are not placed in the control file.

The control files must be transported to their respective Data Links servers. On Windows operating systems, the single control file must be transported to all referenced Data Links servers. The **dlfm\_export** utility should be run at each Data Links server, specifying the control file name. This utility produces an archive of the files listed in the control file for that Data Links server. Set the **DLFM\_FS\_ENVIRONMENT** registry variable appropriately before running the **dlfm\_export** utility.

The export utility executes as an SQL application. The rows and columns that satisfy the conditions of the SELECT statement are extracted from the database. For DATALINK columns, the SELECT statement should not specify any scalar functions.

The export utility generates the following files:

- The export data file. A DATALINK column value in this file has the same format as that used by the import and the load utilities. If the DATALINK column value is NULL, it is treated in the same way as are other NULL columns.
- Control files for each Data Links server. The control file lists the complete path and the names of all the files that are to be exported from that Data Links server. On Windows operating systems, there is only one control file for all Data Links servers referenced by DATALINK column values.

Use the **dlfm\_export** utility to export files from one or more Data Links servers as follows:

```
dlfm_export control-file-name archive-file-name
```

where *control-file-name* is the name of the control file generated by running the export utility on the DB2<sup>®</sup> client, and *archive-file-name* is the name of the archive file that will be generated. The default *archive-file-name* is `export.tar`, located in the current working directory.

A complementary utility called **dlfm\_import** is provided to retrieve and restore files from the archive that **dlfm\_export** generates. This utility must be used whether the archived files are being restored on the same, or a different, Data Links server.

Use the **dlfm\_import** utility to retrieve files from the archive as follows:

```
dlfm_import archive-file-name [LISTFILES]
```

where *archive-file-name* is the name of the archive file that will be used to restore the files. The default *archive-file-name* is `export.tar`. LISTFILES is an optional keyword that, when specified, causes the utility to return a list of the files contained within the archive. Run the **dlfm\_import** utility with root authority at each Data Links server, because you may want to restore the archived files on a different Data Links server, which may not have the same directory structure and user IDs as the Data Links server on which the **dlfm\_export** utility was run. Set the **DLFM\_FS\_ENVIRONMENT** registry variable appropriately before running the **dlfm\_import** utility.

**Note:** When running the **dlfm\_import** utility on a Data Links server other than the one on which the **dlfm\_export** utility was run, the files will be restored in the correct paths. The files will be owned by root in case some of the user

IDs do not exist on the importing machine. Before inserting these files into a database, ensure that all files have the correct permissions and belong to the correct user IDs.

The following table shows how to export the DB2 data and the files that are referenced by the database called SystemA to the database called SystemB. SystemA uses the Data Links servers DLFM1 and DLFM2. SystemB uses the Data Links servers DLFMX and DLFMY. The files on DLFM1 will be exported to DLFMX, and the files on DLFM2 will be exported to DLFMY.

Database SystemA with Data Links Servers DLFM1 and DLFM2			Step
DB2 data on File	File1 with file names for DLFM1	File2 with file names for DLFM2	1) Run the <code>dlfm_export</code> command (as root) on both Data Links servers. This will produce an archive on both Data Links servers.
Database SystemB with Data Links Servers DLFMX and DLFMY			
	On DLFMX, restore from archive	On DLFMY, restore from archive	2) Run <code>dlfm_import</code> (as root) on both Data Links servers.
			3) Run the <code>IMPORT</code> command on SystemB, using the parameter <code>DL_URL_REPLACE_PREFIX</code> to specify the appropriate Data Links server for each exported file.
When you run the <code>IMPORT</code> command on SystemB, the SystemA data and all files referenced by <code>DATALINK</code> columns are imported.			

**Related tasks:**

- “Using Export” on page 3
- “Using export to move DB2 Data Links Manager data” on page 201

**Related reference:**

- “db2Export - Export” on page 12

---

## Using export to move DB2 Data Links Manager data

**Procedure:**

To ensure that a consistent copy of the table and the corresponding files that are referenced by the `DATALINK` columns are copied, perform the following steps:

1. Ensure that no update transactions are in progress when the export operation is running by issuing the following command:
 

```
db2 quiesce tablespaces for table tablename share
```
2. Invoke the export utility.
3. Run the `dlfm_export` utility with root authority at each Data Links server; this will successfully archive files to which the Data Links File Manager administrator may not have access. The utility does not capture the ACLs

information of the files that are archived. As input to **dlfm\_export**, specify the name of the control file that was generated by the export utility.

4. Make the table available for updates by issuing the following command:

```
db2 quiesce tablespaces for table tablename reset
```

**Related concepts:**

- “Export Overview” on page 1
- “Moving DB2 Data Links Manager Data Using Export - Concepts” on page 199


**Related tasks:**

- “Using import to move DB2 Data Links Manager data” on page 202
- “Using load to move DB2 Data Links Manager data” on page 203

---

## Using import to move DB2 Data Links Manager data

Since table data resides in the database, and the files referred to by DATALINK columns reside on Data Links servers, the import utility must move both the database data, and the data files on the corresponding Data Links servers.



*Figure 12. Moving DB2 Data Links Manager Data.* Since table data resides in the database, and the files referred to by DATALINK columns reside on Data Links servers, the export, import, and load utilities must move both the database data, and the data files on the corresponding Data Links servers.

**Procedure:**

Before running the import utility against the target database:

1. Copy the files that will be referenced to the appropriate Data Links servers. The **dlfm\_import** utility can be used to extract files from an archive that is generated by the **dlfm\_export** utility.
2. Define the prefix name (or names) to the Data Links File Managers on the Data Links servers. (You may want to perform other administrative tasks, such as registering the database.)
3. Update the Data Links server information in the URLs (of the DATALINK columns) from the exported data for the SQL table, if required. (If the Data Links servers of the original configuration are the same as those at the target location, the Data Links server names need not be updated).
4. Define the Data Links servers at the target configuration in the DB2 Data Links Manager configuration file.

When the import utility runs against the target database, files referred to by DATALINK column data are linked on the appropriate Data Links servers.

**Related concepts:**

- “Import Overview” on page 25

**Related tasks:**

- “Using export to move DB2 Data Links Manager data” on page 201
- “Using load to move DB2 Data Links Manager data” on page 203

---

## Using load to move DB2 Data Links Manager data

**Procedure:**

If you are loading data into a table with a DATALINK column that is defined with FILE LINK CONTROL, perform the following steps before invoking the load utility. (If all the DATALINK columns are defined with NO LINK CONTROL, these steps are not necessary.)

1. Ensure that DB2 Data Links Manager is installed on the Data Links servers that will be referred to by the DATALINK column values.
2. Ensure that the database is registered with the DB2 Data Links Manager.
3. Copy to the appropriate Data Links servers all files that will be inserted as DATALINK values.
4. Define the prefix name (or names) to the DB2 Data Links Managers on the Data Links servers.
5. Register the Data Links servers referred to by DATALINK data (to be loaded) in the DB2 Data Links Manager configuration file.

Links that fail during the load operation are considered to be data integrity violations, and are handled in much the same way as unique index violations. Consequently, a special exception has been defined for loading tables that have one or more DATALINK columns.

Following are load utility features that are not supported when loading tables with DATALINK columns:

- CPU\_PARALLELISM (the value is forced to 1)
- LOAD REPLACE
- LOAD TERMINATE
- LOAD COPY

**Related reference:**

- “LOAD” on page 100



---

## Chapter 6. Moving Data Between Systems

This chapter describes how to use the DB2 export, import, and load utilities to transfer data across platforms, and to and from iSeries host databases. DB2 DataPropagator, another method for moving data between databases in an enterprise, is also described. The chapter also introduces the Data Warehouse Center (DWC), which you can use to move data from operational databases to a warehouse database.

The following topics are covered:

- “Moving data across platforms - file format considerations”
- “Moving Data With DB2 Connect” on page 206
- “db2move - Database Movement Tool” on page 209
- “db2relocatedb - Relocate Database” on page 213
- “Moving data between typed tables” on page 218
- “Using replication to move data” on page 222
- “Using the Data Warehouse Center to Move Data” on page 224.
- “Moving data using the cursor file type” on page 226.

---

### Moving data across platforms - file format considerations

Compatibility is important when exporting, importing, or loading data across platforms. The following sections describe PC/IXF, delimited ASCII (DEL), and WSF file format considerations when moving data between different operating systems.

#### PC/IXF File Format

PC/IXF is the recommended file format for transferring data across platforms. PC/IXF files allow the load utility or the import utility to process (normally machine dependent) numeric data in a machine-independent fashion. For example, numeric data is stored and handled differently by Intel and other hardware architectures.

To provide compatibility of PC/IXF files among all products in the DB2<sup>®</sup> family, the export utility creates files with numeric data in Intel format, and the import utility expects it in this format.

Depending on the hardware platform, DB2 products convert numeric values between Intel and non-Intel formats (using byte reversal) during both export and import operations.

UNIX<sup>®</sup> based implementations of DB2 do not create multiple-part PC/IXF files during export. However, they will allow you to import a multiple-part PC/IXF file that was created by DB2. When importing this type of file, all parts should be in the same directory, otherwise an error is returned.

Single-part PC/IXF files created by UNIX based implementations of the DB2 export utility can be imported by DB2 for Windows<sup>®</sup>.

## Delimited ASCII (DEL) File Format

DEL files have differences based on the operating system on which they were created. The differences are:

- Row separator characters
  - UNIX based text files use a line feed (LF) character.
  - Non-UNIX based text files use a carriage return/line feed (CRLF) sequence.
- End-of-file character
  - UNIX based text files do not have an end-of-file character.
  - Non-UNIX based text files have an end-of-file character (X'1A').

Since DEL export files are text files, they can be transferred from one operating system to another. File transfer programs can handle operating system-dependant differences if you transfer the files in text mode; the conversion of row separator and end-of-file characters is not performed in binary mode.

**Note:** If character data fields contain row separator characters, these will also be converted during file transfer. This conversion causes unexpected changes to the data and, for this reason, it is recommended that you do not use DEL export files to move data across platforms. Use the PC/IXF file format instead.

## WSF File Format

Numeric™ data in WSF format files is stored using Intel machine format. This format allows Lotus® WSF files to be transferred and used in different Lotus operating environments (for example, in Intel based and UNIX based systems).

As a result of this consistency in internal formats, exported WSF files from DB2 products can be used by Lotus 1-2-3® or Symphony running on a different platform. DB2 products can also import WSF files that were created on different platforms.

Transfer WSF files between operating systems in binary (not text) mode.

**Note:** Do not use the WSF file format to transfer data between DB2 databases on different platforms, because a loss of data can occur. Use the PC/IXF file format instead.

### Related reference:

- “Export/Import/Load Utility File Formats” on page 243

---

## Moving Data With DB2 Connect

If you are working in a complex environment in which you need to move data between a host database system and a workstation, you can use DB2 Connect, the gateway for data transfer between the host and the workstation (see Figure 13 on page 207).




Figure 13. Import/Export through DB2 Connect

The DB2 export and import utilities allow you to move data from a host or iSeries server database to a file on the DB2 Connect workstation, and the reverse. You can then use the data with any other application or relational database management system that supports this export or import format. For example, you can export data from a host or iSeries server database into a PC/IXF file, and then import it into a DB2 for Windows database.

You can perform export and import operations from a database client or from the DB2 Connect workstation.

**Notes:**

1. The data to be exported or imported must comply with the size and data type restrictions that are applicable to both databases.
2. To improve import performance, you can use compound SQL. Specify the compound file type modifier in the import utility to group a specified number of SQL statements into a block. This may reduce network overhead and improve response time.

**Restrictions:**

With DB2 Connect, export and import operations must meet the following conditions:

- The file type must be PC/IXF.
- A target table with attributes that are compatible with the data must be created on the target server before you can import to it. The **db2look** utility can be used to get the attributes of the source table. Import through DB2 Connect cannot create a table, because INSERT is the only supported option.

If any of these conditions is not met, the operation fails, and an error message is returned.

**Note:** Index definitions are not stored on export or used on import.

If you export or import mixed data (columns containing both single-byte and double-byte data), consider the following:

- On systems that store data in EBCDIC (MVS, OS/390, OS/400, VM, and VSE), shift-out and shift-in characters mark the start and the end of double-byte data. When you define column lengths for your database tables, be sure to allow enough room for these characters.
- Variable-length character columns are recommended, unless the column data has a consistent pattern.

### **Moving Data from a workstation to a host server:**

To move data to a host or AS/400 and iSeries server database:

1. Export the data from a DB2 table to a PC/IXF file.
2. Using the INSERT option, import the PC/IXF file into a compatible table in the host server database.

To move data from a host server database to a workstation:

1. Export the data from the host server database table to a PC/IXF file.
2. Import the PC/IXF file into a DB2 table.

### **Example**

The following example illustrates how to move data from a workstation to a host or AS/400 and iSeries server database.

1. Export the data into an external IXF format by issuing the following command:  

```
db2 export to staff.ixf of ixf select * from userid.staff
```
2. Issue the following command to establish a DRDA connection to the target DB2 UDB server:  

```
db2 connect to cbc664 user admin using xxx
```
3. If it doesn't already exist, create the target table on target DB2 UDB server\_  

```
CREATE TABLE mydb.staff (ID SMALLINT NOT NULL, NAME VARCHAR(9),
DEPT SMALLINT, JOB CHAR(5), YEARS SMALLINT, SALARY DECIMAL(7,2),
COMM DECIMAL(7,2))
```
4. To import the data issue the following command:  

```
db2 import from staff.ixf of ixf insert into mydb.staff
```

Each row of data will be read from the file in IXF format, and an SQL INSERT statement will be issued to insert the row into table mydb.staff. Single rows will continue to be inserted until all of the data has been moved to the target table.

| Detailed information is available in the following IBM Redbook: Moving Data  
| Across the DB2 Family. This Redbook can be found at the following URL:  
| <http://www.redbooks.ibm.com/redbooks/SG246905.html>.

### **Related concepts:**

- "Moving data across platforms - file format considerations" on page 205

### **Related reference:**

- "EXPORT" on page 8
- "IMPORT" on page 35

## db2move - Database Movement Tool


This tool facilitates the movement of large numbers of tables between DB2 databases located on workstations. The tool queries the system catalog tables for a particular database and compiles a list of all user tables. It then exports these tables in PC/IXF format. The PC/IXF files can be imported or loaded to another local DB2 database on the same system, or can be transferred to another workstation platform and imported or loaded to a DB2 database on that platform.

**Note:** Tables with structured type columns are not moved when this tool is used.

### Authorization:

This tool calls the DB2 export, import, and load APIs, depending on the action requested by the user. Therefore, the requesting user ID must have the correct authorization required by those APIs, or the request will fail.

### Command syntax:



### Command parameters:

#### dbname

Name of the database.

**action** Must be one of: EXPORT, IMPORT, or LOAD.

**-tc** table-creators. The default is all creators.

This is an EXPORT action only. If specified, only those tables created by the creators listed with this option are exported. If not specified, the default is to use all creators. When specifying multiple creators, they must be separated by commas; no blanks are allowed between creator IDs. The maximum number of creators that can be specified is 10. This option can be used with the “-tn” table-names option to select the tables for export.

An asterisk (\*) can be used as a wildcard character that can be placed anywhere in the string.

**-tn** table-names. The default is all user tables.

This is an EXPORT action only. If specified, only those tables whose names match exactly those in the specified string are exported. If not specified, the default is to use all user tables. When specifying multiple table names, they must be separated by commas; no blanks are allowed between table names. The maximum number of table names that can be specified is 10.

## db2move - Database Movement Tool

This option can be used with the “-tc” table-creators option to select the tables for export. **db2move** will only export those tables whose names match the specified table names and whose creators match the specified table creators.

An asterisk (\*) can be used as a wildcard character that can be placed anywhere in the string.

**-sn** schema-names. The default is all schemas.

If specified, only those tables whose schema names match exactly will be exported. If the asterisk wildcard character (\*) is used in the schema names, it will be changed to a percent sign (%) and the table name (with percent sign) will be used in the LIKE predicate of the WHERE clause. If not specified, the default is to use all schemas. If multiple schema names are specified, they must be separated by commas; no blanks are allowed between schema names. The maximum number of schema names that can be specified is 10. If used with the -tn or -tc option, **db2move** will export only those tables whose schemas match the specified schema names and whose creators match the specified creators.

**Note:** Schema names of less than 8 character are padded to 8 characters in length. For example, a schema name ‘fred’ has to be specified “-sn fr\*d\*” instead of “-sn fr\*d” when using an asterisk.

2 **-ts** tablespace-names. The default is all table spaces.

2 This is an EXPORT action only. If this option is specified, only those tables  
2 that reside in the specified table space will be exported. If the asterisk  
2 wildcard character (\*) is used in the table space name, it will be changed to  
2 a percent sign (%) and the table name (with percent sign) will be used in  
2 the LIKE predicate in the WHERE clause. If the -ts option is not specified,  
2 the default is to use all table spaces. If multiple table space names are  
2 specified, they must be separated by commas; no blanks are allowed  
2 between table space names. The maximum number of table space names  
2 that can be specified is 10.

2 **Note:** Table space names less than 8 characters are padded to 8 characters  
2 in length. For example, a table space name ‘mytb’ has to be specified  
2 “-ts my\*b\*” instead of “-sn my\*b” when using the asterisk.

2 **-tf** filename

2 This is an EXPORT action only. If specified, only the tables listed in the  
2 given file will be exported. The tables should be listed one per line, and  
2 each table should be fully qualified. Here is an example of the contents of  
2 a file:

```
2 "SCHEMA1"."TABLE NAME1"  
2 "SCHEMA NAME77"."TABLE155"
```

**-io** import-option. The default is REPLACE\_CREATE.

Valid options are: INSERT, INSERT\_UPDATE, REPLACE, CREATE, and REPLACE\_CREATE.

**-lo** load-option. The default is INSERT.

Valid options are: INSERT and REPLACE.

**-l** lobpaths. The default is the current directory.

This option specifies the absolute path names where LOB files are created (as part of EXPORT) or searched for (as part of IMPORT or LOAD). When specifying multiple LOB paths, each must be separated by commas; no blanks are allowed between LOB paths. If the first path runs out of space (during EXPORT), or the files are not found in the path (during IMPORT or LOAD), the second path will be used, and so on.

If the action is EXPORT, and LOB paths are specified, all files in the LOB path directories are deleted, the directories are removed, and new directories are created. If not specified, the current directory is used for the LOB path.

**-u** userid. The default is the logged on user ID.

Both user ID and password are optional. However, if one is specified, the other must be specified. If the command is run on a client connecting to a remote server, user ID and password should be specified.

**-p** password. The default is the logged on password.

Both user ID and password are optional. However, if one is specified, the other must be specified. If the command is run on a client connecting to a remote server, user ID and password should be specified.

**-aw** Allow Warnings. When '-aw' is not specified, tables that experience warnings during export are not included in the db2move.lst file (although that table's .ixf file and .msg file are still generated). In some scenarios (such as data truncation) the user may wish to allow such tables to be included in the db2move.lst file. Specifying this option allows tables which receive warnings during export to be included in the .lst file.

### Examples:

- db2move sample export

This will export all tables in the SAMPLE database; default values are used for all options.

- db2move sample export -tc userid1,us\*rid2 -tn tname1,\*tname2

This will export all tables created by "userid1" or user IDs LIKE "us%rid2", and with the name "tname1" or table names LIKE "%tname2".

- db2move sample import -l D:\LOBPATH1,C:\LOBPATH2

This example is applicable to the Windows operating system only. The command will import all tables in the SAMPLE database; LOB paths "D:\LOBPATH1" and "C:\LOBPATH2" are to be searched for LOB files.

- db2move sample load -l /home/userid/lobpath,/tmp

This example is applicable to UNIX based systems only. The command will load all tables in the SAMPLE database; both the /home/userid/lobpath subdirectory and the tmp subdirectory are to be searched for LOB files.

- db2move sample import -io replace -u userid -p password

This will import all tables in the SAMPLE database in REPLACE mode; the specified user ID and password will be used.

### Usage notes:

This tool exports, imports, or loads user-created tables. If a database is to be duplicated from one operating system to another operating system, **db2move** facilitates the movement of the tables. It is also necessary to move all other objects associated with the tables, such as aliases, views, triggers, user-defined functions,

## db2move - Database Movement Tool

| and so on. If the import utility with the REPLACE\_CREATE option is used to  
| create the tables on the target database, then the limitations outlined in Using  
| import to recreate an exported table are imposed. If unexpected errors are  
| encountered during the **db2move** import phase when the REPLACE\_CREATE  
| option is used, examine the appropriate tabnnn.msg message file and consider that  
| the errors may be the result of the limitations on table creation.

When export, import, or load APIs are called by **db2move**, the FileTypeMod parameter is set to lobsinfile. That is, LOB data is kept in separate files from PC/IXF files. There are 26 000 file names available for LOB files.

The LOAD action must be run locally on the machine where the database and the data file reside. When the load API is called by **db2move**, the CopyTargetList parameter is set to NULL; that is, no copying is done. If *logretain* is on, the load operation cannot be rolled forward later. The table space where the loaded tables reside is placed in backup pending state, and is not accessible. A full database backup, or a table space backup, is required to take the table space out of backup pending state.

**Note:** 'db2move import' performance may be improved by altering default buffer pool, IBMDEFAULTBP; and by updating the configuration parameters *sortheap*, *util\_heap\_sz*, *logfilsz*, and *logprimary*.

### Files Required/Generated When Using EXPORT:

- Input: None.
- Output:
  - EXPORT.out** The summarized result of the EXPORT action.
  - db2move.lst** The list of original table names, their corresponding PC/IXF file names (tabnnn.ixf), and message file names (tabnnn.msg). This list, the exported PC/IXF files, and LOB files (tabnnnc.yyy) are used as input to the **db2move** IMPORT or LOAD action.
  - tabnnn.ixf** The exported PC/IXF file of a specific table.
  - tabnnn.msg** The export message file of the corresponding table.
  - tabnnnc.yyy** The exported LOB files of a specific table.  
"nnn" is the table number. "c" is a letter of the alphabet. "yyy" is a number ranging from 001 to 999.  
These files are created only if the table being exported contains LOB data. If created, these LOB files are placed in the "lobpath" directories. There are a total of 26 000 possible names for the LOB files.
  - system.msg** The message file containing system messages for creating or deleting file or directory commands. This is only used if the action is EXPORT, and a LOB path is specified.

### Files Required/Generated When Using IMPORT:

- Input:
  - db2move.lst** An output file from the EXPORT action.
  - tabnnn.ixf** An output file from the EXPORT action.
  - tabnnnc.yyy** An output file from the EXPORT action.

- Output:

- IMPORT.out** The summarized result of the IMPORT action.
- tabnnn.msg** The import message file of the corresponding table.

**Files Required/Generated When Using LOAD:**

- Input:

- db2move.lst** An output file from the EXPORT action.
- tabnnn.ixf** An output file from the EXPORT action.
- tabnnnc.yyy** An output file from the EXPORT action.

- Output:

- LOAD.out** The summarized result of the LOAD action.
- tabnnn.msg** The LOAD message file of the corresponding table.

**Related reference:**

- “db2look - DB2 Statistics and DDL Extraction Tool Command” in the *Command Reference*

## db2relocatedb - Relocate Database

Renames a database, or relocates a database or part of a database (for example, the container and the log directory) as specified in the configuration file provided by the user. This tool makes the necessary changes to the DB2 instance and database support files.

**Authorization:**

None

**Command syntax:**

►► db2relocatedb -f configFilename ◀◀

**Command parameters:**

**-f configFilename**

Specifies the name of the file containing configuration information necessary for relocating the database. This can be a relative or absolute filename. The format of the configuration file is:

```
DB_NAME=oldName,newName
DB_PATH=oldPath,newPath
INSTANCE=oldInst,newInst
NODENUM=nodeNumber
LOG_DIR=oldDirPath,newDirPath
CONT_PATH=oldContPath1,newContPath1
CONT_PATH=oldContPath2,newContPath2
...
```

**Where:**

**DB\_NAME**

Specifies the name of the database being relocated. If the database name is being changed, both the old name and the new name must be specified. This is a required field.

## db2relocatedb - Relocate Database

### DB\_PATH

Specifies the path of the database being relocated. This is the path where the database was originally created. If the database path is changing, both the old path and new path must be specified. This is a required field.

### INSTANCE

Specifies the instance where the database exists. If the database is being moved to a new instance, both the old instance and new instance must be specified. This is a required field.

### NODENUM

Specifies the node number for the database node being changed. The default is 0.

### LOG\_DIR

Specifies a change in the location of the log path. If the log path is being changed, then both the old path and new path must be specified. This specification is optional if the log path resides under the database path, in which case the path is updated automatically.

### CONT\_PATH

Specifies a change in the location of table space containers. Both the old and new container path must be specified. Multiple CONT\_PATH lines can be provided if there are multiple container path changes to be made. This specification is optional if the container paths reside under the database path, in which case the paths are updated automatically. If you are making changes to more than one container where the same old path is being replaced by a common new path, a single CONT\_PATH entry can be used. In such a case, an asterisk (\*) could be used both in the old and new paths as a wildcard.

**Note:** Blank lines or lines beginning with a comment character (#) will be ignored.

### Usage notes:

If the instance that a database belongs to is changing, the following must be done before running this command to ensure that changes to the instance and database support files will be made:

- If a database is being moved to another instance, create the new instance.
- Copy the files/devices belonging to the databases being copied onto the system where the new instance resides. The path names must be changed as necessary. However, if there are already databases in the directory where the database files are moved to, you can mistakenly overwrite the existing sqlbdir file, thereby removing the references to the existing databases. In this scenario, the **db2relocatedb** utility cannot be used. Instead of **db2relocatedb**, an alternative is a redirected restore.
- Change the permission of the files/devices that were copied so that they are owned by the instance owner.

If the instance is changing, the tool must be run by the new instance owner.

In a partitioned database environment, this tool must be run against every partition that requires changes. A separate configuration file must be supplied for each partition, that includes the NODENUM value of the partition being changed.

For example, if the name of a database is being changed, every partition will be affected and the **db2relocatedb** command must be run with a separate configuration file on each partition. If containers belonging to a single database partition are being moved, the **db2relocatedb** command only needs to be run once on that partition.

### Examples:

#### Example 1

To change the name of the database TESTDB to PRODDB in the instance db2inst1 that resides on the path /home/db2inst1, create the following configuration file:

```
DB_NAME=TESTDB,PRODDB
DB_PATH=/home/db2inst1
INSTANCE=db2inst1
NODENUM=0
```

Save the configuration file as relocate.cfg and use the following command to make the changes to the database files:

```
db2relocatedb -f relocate.cfg
```

#### Example 2

To move the database DATAB1 from the instance jsmith on the path /dbpath to the instance prodinst do the following:

1. Move the files in the directory /dbpath/jsmith to /dbpath/prodinst.
2. Use the following configuration file with the **db2relocatedb** command to make the changes to the database files:

```
DB_NAME=DATAB1
DB_PATH=/dbpath
INSTANCE=jsmith,prodinst
NODENUM=0
```

#### Example 3

The database PRODDB exists in the instance inst1 on the path /databases/PRODDB. The location of two table space containers needs to be changed as follows:

- SMS container /data/SMS1 needs to be moved to /DATA/NewSMS1.
- DMS container /data/DMS1 needs to be moved to /DATA/DMS1.

After the physical directories and files have been moved to the new locations, the following configuration file can be used with the **db2relocatedb** command to make changes to the database files so that they recognize the new locations:

```
DB_NAME=PRODDB
DB_PATH=/databases/PRODDB
INSTANCE=inst1
NODENUM=0
CONT_PATH=/data/SMS1,/DATA/NewSMS1
CONT_PATH=/data/DMS1,/DATA/DMS1
```

#### Example 4

The database TESTDB exists in the instance db2inst1 and was created on the path /databases/TESTDB. Table spaces were then created with the following containers:

## db2relocatedb - Relocate Database

```
| TS1
| TS2_Cont0
| TS2_Cont1
| /databases/TESTDB/TS3_Cont0
| /databases/TESTDB/TS4_Cont0
| /Data/TS5_Cont0
| /dev/rTS5_Cont1
```

| TESTDB is to be moved to a new system. The instance on the new system will be newinst and the location of the database will be /DB2.

| When moving the database, all of the files that exist in the /databases/TESTDB/db2inst1 directory must be moved to the /DB2/newinst directory. This means that the first 5 containers will be relocated as part of this move. (The first 3 are relative to the database directory and the next 2 are relative to the database path.) Since these containers are located within the database directory or database path, they do not need to be listed in the configuration file. If the 2 remaining containers are to be moved to different locations on the new system, they must be listed in the configuration file.

| After the physical directories and files have been moved to their new locations, the following configuration file can be used with **db2relocatedb** to make changes to the database files so that they recognize the new locations:

```
| DB_NAME=TESTDB
| DB_PATH=/databases/TESTDB,/DB2
| INSTANCE=db2inst1,newinst
| NODENUM=0
| CONT_PATH=/Data/TS5_Cont0,/DB2/TESTDB/TS5_Cont0
| CONT_PATH=/dev/rTS5_Cont1,/dev/rTESTDB_TS5_Cont1
```

### Example 5

| The database TESTDB has two partitions on database partition servers 10 and 20. The instance is servinst and the database path is /home/servinst on both database partition servers. The name of the database is being changed to SERVDB and the database path is being changed to /databases on both database partition servers. In addition, the log directory is being changed on database partition server 20 from /testdb\_logdir to /servdb\_logdir.

| Since changes are being made to both database partitions, a configuration file must be created for each database partition and **db2relocatedb** must be run on each database partition server with the corresponding configuration file.

| On database partition server 10, the following configuration file will be used:

```
| DB_NAME=TESTDB,SERVDB
| DB_PATH=/home/servinst,/databases
| INSTANCE=servinst
| NODE_NUM=10
```

| On database partition server 20, the following configuration file will be used:

```
| DB_NAME=TESTDB,SERVDB
| DB_PATH=/home/servinst,/databases
| INSTANCE=servinst
| NODE_NUM=20
| LOG_DIR=/testdb_logdir,/servdb_logdir
```

### Example 6

The database MAINDB exists in the instance maininst on the path /home/maininst. The location of four table space containers needs to be changed as follows:

```

/maininst_files/allconts/C0 needs to be moved to /MAINDB/C0
/maininst_files/allconts/C1 needs to be moved to /MAINDB/C1
/maininst_files/allconts/C2 needs to be moved to /MAINDB/C2
/maininst_files/allconts/C3 needs to be moved to /MAINDB/C3

```

After the physical directories and files are moved to the new locations, the following configuration file can be used with the **db2relocatedb** command to make changes to the database files so that they recognize the new locations.

**Note:** A similar change is being made to all of the containers; that is, /maininst\_files/allconts/ is being replaced by /MAINDB/ so that a single entry with the wildcard character can be used:

```

DB_NAME=MAINDB
DB_PATH=/home/maininst
INSTANCE=maininst
NODE_NUM=0
CONT_PATH=/maininst_files/allconts/*, /MAINDB/*

```

**Related reference:**

- “db2inidb - Initialize a Mirrored Database Command” in the *Command Reference*

---

## Delimiter restrictions for moving data

### Delimiter restrictions:

It is the user’s responsibility to ensure that the chosen delimiter character is not part of the data to be moved. If it is, unexpected errors may occur. The following restrictions apply to column, string, DATALINK, and decimal point delimiters when moving data:

- Delimiters are mutually exclusive.
- A delimiter cannot be binary zero, a line-feed character, a carriage-return, or a blank space.
- The default decimal point (.) cannot be a string delimiter.
- The following characters are specified differently by an ASCII-family code page and an EBCDIC-family code page:
  - The Shift-In (0x0F) and the Shift-Out (0x0E) character cannot be delimiters for an EBCDIC MBCS data file.
  - Delimiters for MBCS, EUC, or DBCS code pages cannot be greater than 0x40, except the default decimal point for EBCDIC MBCS data, which is 0x4b.
  - Default delimiters for data files in ASCII code pages or EBCDIC MBCS code pages are:
    - " (0x22, double quotation mark; string delimiter)
    - , (0x2c, comma; column delimiter)
  - Default delimiters for data files in EBCDIC SBCS code pages are:
    - " (0x7F, double quotation mark; string delimiter)
    - , (0x6B, comma; column delimiter)
  - The default decimal point for ASCII data files is 0x2e (period).
  - The default decimal point for EBCDIC data files is 0x4B (period).

## db2relocatedb - Relocate Database

- If the code page of the server is different from the code page of the client, it is recommended that the hex representation of non-default delimiters be specified. For example,

```
db2 load from ... modified by charde10x0C colde1X1e ...
```

The following information about support for double character delimiter recognition in DEL files applies to the export, import, and load utilities:

- Character delimiters are permitted within the character-based fields of a DEL file. This applies to fields of type CHAR, VARCHAR, LONG VARCHAR, or CLOB (except when `lobsinfile` is specified). Any pair of character delimiters found between the enclosing character delimiters is imported or loaded into the database. For example,

```
"What a "nice" day!"
```

will be imported as:

```
What a "nice" day!
```

In the case of export, the rule applies in reverse. For example,

```
I am 6" tall.
```

will be exported to a DEL file as:

```
"I am 6"" tall."
```

- In a DBCS environment, the pipe (|) character delimiter is not supported.

---

## Moving data between typed tables

The DB2<sup>®</sup> export and import utilities can be used to move data out of, and into, typed tables. Typed tables may be in a hierarchy. Data movement across hierarchies can include:

- Movement from one hierarchy to an identical hierarchy.
- Movement from one hierarchy to a sub-section of a larger hierarchy.
- Movement from a sub-section of a large hierarchy to a separate hierarchy.

The `IMPORT CREATE` option allows you to create both the table hierarchy and the type hierarchy.

Identification of types in a hierarchy is database dependent. This means that in different databases, the same type has a different identifier. Therefore, when moving data between these databases, a mapping of the same types must be done to ensure that the data is moved correctly.

Before each typed row is written out during an export operation, an identifier is translated into an index value. This index value can be any number from one to the number of relevant types in the hierarchy. Index values are generated by numbering each type when moving through the hierarchy in a specific order. This order is called the *traverse order*. It is the order of proceeding top-to-bottom, left-to-right through all of the supertables and subtables in the hierarchy. The traverse order is important when moving data between table hierarchies, because it determines where the data is moved in relation to other data.

One method is to proceed from the top of the hierarchy (or the root table), down the hierarchy (subtables) to the bottom subtable, then back up to its supertable, down to the next "right-most" subtable(s), then back up to next higher supertable, down to its subtables, and so on.

The following figure shows a hierarchy with four valid traverse orders:

- Person, Employee, Manager, Architect, Student.
- Person, Student, Employee, Manager, Architect (this traverse order is marked with the dotted line).
- Person, Employee, Architect, Manager, Student.
- Person, Student, Employee, Architect, Manager.




Figure 14.

**Related concepts:**

- “Export Overview” on page 1
- “Import Overview” on page 25

## Moving Data Between Typed Tables - Details

### Traverse Order

There is a default traverse order, in which all relevant types refer to all reachable types in the hierarchy from a given starting point in the hierarchy. The default order includes all tables in the hierarchy, and each table is ordered by the scheme used in the OUTER order predicate. There is also a user-specified traverse order, in which the user defines (in a traverse order list) the relevant types to be used. The same traverse order must be used when invoking the export utility and the import utility.

If you are specifying the traverse order, remember that the subtables must be traversed in PRE-ORDER fashion (that is, each branch in the hierarchy must be traversed to the bottom before a new branch is started).

### Default Traverse Order

The default traverse order behaves differently when used with different file formats. Assume identical table hierarchy and type relationships in the following:

Exporting data to the PC/IXF file format creates a record of all relevant types, their definitions, and relevant tables. Export also completes the mapping of an index

value to each table. During import, this mapping is used to ensure accurate movement of the data to the target database. When working with the PC/IXF file format, you should use the default traverse order.

With the ASC, DEL, or WSF file format, the order in which the typed rows and the typed tables were created could be different, even though the source and target hierarchies might be structurally identical. This results in time differences that the default traverse order will identify when proceeding through the hierarchies. The creation time of each type determines the order taken through the hierarchy at both the source and the target when using the default traverse order. Ensure that the creation order of each type in both the source and the target hierarchies is identical, and that there is structural identity between the source and the target. If these conditions cannot be met, select a user-specified traverse order.

### **User-Specified Traverse Order**

If you want to control the traverse order through the hierarchies, ensure that the same traverse order is used for both the export and the import utilities. Given:

- An identical definition of subtables in both the source and the target databases
- An identical hierarchical relationship among the subtables in both the source and target databases
- An identical traverse order

the import utility guarantees the accurate movement of data to the target database.

Although you determine the starting point and the path down the hierarchy when defining the traverse order, each branch must be traversed to the end before the next branch in the hierarchy can be started. The export and import utilities look for violations of this condition within the specified traverse order.

#### **Related reference:**

- “Delimited ASCII (DEL) File Format” on page 244
- “Non-delimited ASCII (ASC) File Format” on page 249
- “PC Version of IXF File Format” on page 252
- “Worksheet File Format (WSF)” on page 290

## **Selection During Data Movement**

The movement of data from one hierarchical structure of typed tables to another is done through a specific traverse order and the creation of an intermediate flat file. The export utility (in conjunction with the traverse order) controls what is placed in that file. You only need to specify the target table name and the WHERE clause. The export utility uses these selection criteria to create an appropriate intermediate file.

The import utility controls what is placed in the target database. You can specify an attributes list at the end of each subtable name to restrict the attributes that are moved to the target database. If no attributes list is used, all of the columns in each subtable are moved.

The import utility controls the size and the placement of the hierarchy being moved through the CREATE, INTO table-name, UNDER, and AS ROOT TABLE parameters.

#### **Related reference:**

- “IMPORT” on page 35

## Examples of Moving Data Between Typed Tables

Examples in this section are based on the following hierarchical structure:




Figure 15.

### Example 1

To export an entire hierarchy and then recreate it through an import operation:

```

DB2® CONNECT TO Source_db
DB2 EXPORT TO entire_hierarchy.ixf OF IXF HIERARCHY STARTING Person
DB2 CONNECT TO Target_db
DB2 IMPORT FROM entire_hierarchy.ixf OF IXF CREATE INTO
HIERARCHY STARTING Person AS ROOT TABLE
  
```

Each type in the hierarchy is created if it does not exist. If these types already exist, they must have the same definition in the target database as in the source database. An SQL error (SQL20013N) is returned if they are not the same. Since new hierarchy is being created, none of the subtables defined in the data file being moved to the target database (Target\_db) can exist. Each of the tables in the source database hierarchy is created. Data from the source database is imported into the correct subtables of the target database.

### Example 2

A more complex example shows how to export the entire hierarchy of the source database and import it to the target database. Although all of the data for those people over the age of 20 will be exported, only selected data will be imported to the target database:

```

DB2 CONNECT TO Source_db
DB2 EXPORT TO entire_hierarchy.del OF DEL HIERARCHY (Person,
Employee, Manager, Architect, Student) WHERE Age>=20
DB2 CONNECT TO Target_db
DB2 IMPORT FROM entire_hierarchy.del OF DEL INSERT INTO (Person,
Employee(Salary), Architect) IN HIERARCHY (Person, Employee,
Manager, Architect, Student)
  
```

The target tables Person, Employee, and Architect must all exist. Data is imported into the Person, Employee, and Architect subtables. That is, the following will be imported:

- All columns in Person into Person.
- All columns in Person plus Salary in Employee into Employee.
- All columns in Person plus Salary in Employee, plus all columns in Architect into Architect.

Columns SerialNum and REF(Employee\_t) will not be imported into Employee or its subtables (that is, Architect, which is the only subtable having data imported into it).

**Note:** Because Architect is a subtable of Employee, and the only import column specified for Employee is Salary, Salary will also be the only Employee-specific column imported into Architect. That is, neither SerialNum nor REF(Employee\_t) columns are imported into either Employee or Architect rows.

Data for the Manager and the Student tables is not imported.

### Example 3

This example shows how to export from a regular table, and import as a single subtable in a hierarchy. The EXPORT command operates on regular (non-typed) tables, so there is no Type\_id column in the data file. The modifier no\_type\_id is used to indicate this, so that the import utility does not expect the first column to be the Type\_id column.

```
DB2 CONNECT TO Source_db
DB2 EXPORT TO Student_sub_table.del OF DEL SELECT * FROM
Regular_Student
DB2 CONNECT TO Target_db
DB2 IMPORT FROM Student_sub_table.del OF DEL METHOD P(1,2,3,5,4)
MODIFIED BY NO_TYPE_ID INSERT INTO HIERARCHY (Student)
```

In this example, the target table Student must exist. Since Student is a subtable, the modifier no\_type\_id is used to indicate that there is no Type\_id in the first column. However, you must ensure that there is an existing Object\_id column, in addition to all of the other attributes that exist in the Student table. Object-id is expected to be the first column in each row imported into the Student table. The METHOD clause reverses the order of the last two attributes.

#### Related concepts:

- “Moving data between typed tables” on page 218

---

## Using replication to move data

Replication allows you to copy data on a regular basis to multiple remote databases. If you need to have updates to a master database automatically copied to other databases, you can use the replication features of DB2® to specify what data should be copied, which database tables the data should be copied to, and how often the updates should be copied. The replication features in DB2 are part of a larger IBM® solution for replicating data in small and large enterprises.

The IBM Replication tools are a set of DB2 DataPropagator™ programs and DB2 Universal Database™ tools that copy data between distributed relational database management systems:

- Between DB2 Universal Database platforms.
- Between DB2 Universal Database platforms and host databases supporting Distributed Relational Database Architecture™ (DRDA) connectivity.
- Between host databases that support DRDA® connectivity.

Data can also be replicated to non-IBM relational database management systems by way of DB2 DataJoiner®.

You can use the IBM Replication tools to define, synchronize, automate, and manage copy operations from a single control point for data across your enterprise. The replication tools in DB2 Universal Database offer replication between relational databases. They also work in conjunction with IMS™ DataPropagator (formerly DPropNR) to replicate IMS and VSAM data, and with Lotus® NotesPump to replicate to and from Lotus Notes® databases.

Replication allows you to give end users and applications access to production data without putting extra load on the production database. You can copy the data to a database that is local to a user or an application, rather than have them access the data remotely. A typical replication scenario involves a source table with copies in one or more remote databases; for example, a central bank and its local branches. At predetermined times, automatic updates of the DB2 databases takes place, and all changes to the source database are copied to the target database tables.

The replication tools allow you to customize the copy table structure. You can use SQL when copying to the target database to enhance the data being copied. You can produce read-only copies that duplicate the source table, capture data at a specified point in time, provide a history of changes, or stage data to be copied to additional target tables. Moreover, you can create read-write copies that can be updated by end users or applications, and then have the changes replicated back to the master table. You can replicate views of source tables, or views of copies. Event-driven replication is also possible.

You can replicate data between DB2 databases on the following platforms: AIX®, AS/400®, HP-UX, Linux, Windows®, OS/390®, SCO UnixWare, Solaris™ Operating Environment, Sequent®, VM, and VSE. You can also replicate data between DB2 and the following non-DB2 databases (with DB2 DataJoiner): Informix®, Microsoft® Jet, Microsoft SQL Server, Oracle®, Sybase, and Sybase SQLAnywhere. In conjunction with other IBM products, you can replicate DB2 data to and from IMS, VSAM, or Lotus Notes. Finally, you can also replicate data to DB2 Everywhere on Windows CE, or Palm OS devices.

**Related concepts:**

- “The IBM Replication Tools by Component” on page 224

---

## IBM Replication Tools

### The IBM Replication Tools by Component

There are two components of the IBM® Replication tools solution: the Capture program and the Apply program. You can set up these components using the DB2® Control Center. The operation and monitoring of these components happens outside of the Control Center.

The Capture program captures changes to the source tables. A source table can be:

- An external table containing SQL data from a file system or a nonrelational database manager loaded outside DB2 DataPropagator™.
- An existing table in the database.
- A table that has previously been updated by the Apply program, which allows changes to be copied back to the source, or to other target tables.

The changes are copied into a change data table, where they are stored until the target system is ready to copy them. The Apply program then takes the changes from the change data table, and copies them to the target tables.

Use the Control Center to:

- Set up the replication environment.
- Define source and target tables.
- Specify the timing of automated copying.
- Specify SQL enhancements to the data.
- Define relationships between the source and the target tables.

#### Related tasks:

- “Planning for SQL replication” in the *IBM DB2 Information Integrator SQL Replication Guide and Reference*

---

## Using the Data Warehouse Center to Move Data

You can use the Data Warehouse Center (DWC) to move data from operational databases to a warehouse database, which users can query for decision support. You can also use the DWC to define the structure of the operational databases, called *sources*. You can then specify how the operational data is to be moved and transformed for the warehouse. You can model the structure of the tables in the warehouse database, called *targets*, or build the tables automatically as part of the process of defining the data movement operations.

The Data Warehouse Center uses the following DB2® functions to move and transform data:

- SQL  
You can use SQL to select data from sources and insert the data into targets. You also can use SQL to transform the data into its warehouse format. You can use the Data Warehouse Center to generate the SQL, or you can write your own SQL.
- Load and export utilities

You can use these DB2 utilities to export data from a source, and then load the data into a target. These utilities are useful if you need to move large quantities of data. The Data Warehouse Center supports the following types of load and export operations:

**DB2 data export**

Exports data from a local DB2 database into a delimited file.

**ODBC data export**

Selects data from a table in a database that is registered to ODBC, and then writes the data to a delimited file.

**DB2 load**

Loads data from a delimited file into a DB2 table.

**DB2 load into a DB2 UDB ESE database (AIX only)**

Loads data from a delimited file into a DB2 Universal Database™ Enterprise Server Edition database, replacing existing data in a table with new data. This operation acquires the target partitioning map for the database, partitions the input file so that each file can be loaded on a database partition, and then runs a remote load operation on all partitions.

- **Replication**

You also can use replication to copy large quantities of data from warehouse sources into a warehouse target, and then capture any subsequent changes to the source data. The Data Warehouse Center supports the following types of replication:

**Base aggregate**

Creates a target table that contains aggregated data for a user table, and that is appended at specified intervals.

**Change aggregate**

Creates a target table that contains aggregated data, and that is based on changes that are recorded for a source table.

**Point-in-time**

Creates a target table that matches the source table, and adds a time stamp column to the target table.

**Staging table**

Creates a "consistent-change-data" table that can be used as the source for updated data to multiple target tables.

**User copy**

Creates a target table that matches the source table at the time that the copy is made.

These operations are supported on all of the DB2 Universal Database workstation operating environments, DB2 Universal Database for OS/390®, DB2 for AS/400®, and DataJoiner®.

- **Transformer stored procedures**

You can use the Data Warehouse Center to move data into an OLAP (Online Analytical Processing) database. After the data is in the warehouse, you can use transformer stored procedures to clean up the data and then aggregate it into fact and dimension tables. You can also use the transformers to generate statistical data. Once the data is cleaned up and transformed, you can load it into OLAP cubes, or replicate it to departmental servers, which are sometimes called *datamarts*. The transformers are included in only some of the DB2 offerings. See your IBM® representative for more information.

**Related concepts:**

- “What solutions does data warehousing provide?” in the *Data Warehouse Center Administration Guide*

---

## Moving data using the cursor file type

By specifying the CURSOR file type when using the LOAD command, you can load the results of an SQL query directly into a target table without creating an intermediate exported file. By referencing a nickname within the SQL query, the load utility can also load data from another database in a single step.

To execute a load from cursor operation from the CLP, a cursor must first be declared against an SQL query. Once this is done, you can issue the LOAD command using the declared cursor’s name as the *cursorname* and CURSOR as the file type.

For example:

Table ABC.TABLE1 has 3 columns:

- ONE INT
- TWO CHAR(10)
- THREE DATE

Table ABC.TABLE2 has 3 columns:

- ONE VARCHAR
- TWO INT
- THREE DATE

Executing the following CLP commands will load all the data from ABC.TABLE1 into ABC.TABLE2:

```
DECLARE mycurs CURSOR FOR SELECT TWO,ONE,THREE FROM abc.table1
LOAD FROM mycurs OF cursor INSERT INTO abc.table2
```

**Notes:**

1. The above example shows how to load from an SQL query through the CLP. However, loading from an SQL query can also be done through the **db2Load** API, by properly defining the *piSourceList* and *piFileType* values of the *db2LoadStruct* structure.
2. As demonstrated above, the source column types of the SQL query do not need to be identical to their target column types, although they do have to be compatible.

**Related concepts:**

- “Nicknames and data source objects” in the *Federated Systems Guide*

**Related reference:**

- “LOAD” on page 100
- “Assignments and comparisons” in the *SQL Reference, Volume 1*

---

## Appendix A. How to read the syntax diagrams

A syntax diagram shows how a command should be specified so that the operating system can correctly interpret what is typed.

Read a syntax diagram from left to right, and from top to bottom, following the horizontal line (the main path). If the line ends with an arrowhead, the command syntax is continued, and the next line starts with an arrowhead. A vertical bar marks the end of the command syntax.

When typing information from a syntax diagram, be sure to include punctuation, such as quotation marks and equal signs.

Parameters are classified as keywords or variables:

- Keywords represent constants, and are shown in uppercase letters; at the command prompt, however, keywords can be entered in upper, lower, or mixed case. A command name is an example of a keyword.
- Variables represent names or values that are supplied by the user, and are shown in lowercase letters; at the command prompt, however, variables can be entered in upper, lower, or mixed case, unless case restrictions are explicitly stated. A file name is an example of a variable.

A parameter can be a combination of a keyword and a variable.

Required parameters are displayed on the main path:


►►—COMMAND—*required parameter*—►►

Optional parameters are displayed below the main path:

►►—COMMAND—  
└—*optional parameter*—┘—►►

## How to read the syntax diagrams

A parameter's default value is displayed above the path:



A stack of parameters, with the first parameter displayed on the main path, indicates that one of the parameters must be selected:



A stack of parameters, with the first parameter displayed below the main path, indicates that one of the parameters can be selected:



An arrow returning to the left, above the path, indicates that items can be repeated in accordance with the following conventions:

- If the arrow is uninterrupted, the item can be repeated in a list with the items separated by blank spaces:




- If the arrow contains a comma, the item can be repeated in a list with the items separated by commas:



Items from parameter stacks can be repeated in accordance with the stack conventions for required and optional parameters discussed previously.

Some syntax diagrams contain parameter stacks within other parameter stacks. Items from stacks can only be repeated in accordance with the conventions discussed previously. That is, if an inner stack does not have a repeat arrow above it, but an outer stack does, only one parameter from the inner stack can be chosen and combined with any parameter from the outer stack, and that combination can be repeated. For example, the following diagram shows that one could combine parameter *choice2a* with parameter *choice2*, and then repeat that combination again (*choice2* plus *choice2a*):

## How to read the syntax diagrams




Some commands are preceded by an optional path parameter:



If this parameter is not supplied, the system searches the current directory for the command. If it cannot find the command, the system continues searching for the command in all the directories on the paths listed in the `.profile`.

Some commands have syntactical variants that are functionally equivalent:



## How to read the syntax diagrams

## Appendix B. Differences Between the Import and Load Utility

The following table summarizes the important differences between the DB2 load and import utilities.

Import Utility	Load Utility
Slow when moving large amounts of data.	Faster than the import utility when moving large amounts of data, because the load utility writes formatted pages directly into the database.
Limited exploitation of intra-partition parallelism.	Exploitation of intra-partition parallelism. Typically, this requires symmetric multiprocessor (SMP) machines.
No FASTPARSE support.	FASTPARSE support, providing reduced data checking of user-supplied data.
Supports hierarchical data.	Does not support hierarchical data.
Creation of tables, hierarchies, and indexes supported with PC/IXF format.	Tables and indexes must exist.
No support for importing into materialized query tables.	Support for loading into materialized query tables.
WSF format is supported.	WSF format is not supported.
No BINARYNUMERICS support.	BINARYNUMERICS support.
No PACKEDDECIMAL support.	PACKEDDECIMAL support.
No ZONEDDECIMAL support.	ZONEDDECIMAL support.
Cannot override columns defined as GENERATED ALWAYS.	Can override GENERATED ALWAYS columns, by using the GENERATEDOVERRIDE and IDENTITYOVERRIDE file type modifiers.
Supports import into tables and views.	Supports loading into tables only.
All rows are logged.	Minimal logging is performed.
Trigger support.	No trigger support.
If an import operation is interrupted, and a <i>commitcount</i> was specified, the table is usable and will contain the rows that were loaded up to the last COMMIT. The user can restart the import operation, or accept the table as is.	If a load operation is interrupted, and a <i>savecount</i> was specified, the table remains in load pending state and cannot be used until the load operation is restarted, a load terminate operation is invoked, or until the table space is restored from a backup image created some time before the attempted load operation.
Space required is approximately equivalent to the size of the largest index plus 10%. This space is obtained from the temporary table spaces within the database.	Space required is approximately equivalent to the sum of the size of all indexes defined on the table, and can be as much as twice this size. This space is obtained from temporary space within the database.
All constraints are validated during an import operation.	The load utility checks for uniqueness and computes generated column values, but all other constraints must be checked using SET INTEGRITY.

<b>Import Utility</b>	<b>Load Utility</b>
The key values are inserted into the index one at a time during an import operation.	The key values are sorted and the index is built after the data has been loaded.
If updated statistics are required, the runstats utility must be run after an import operation.	Statistics can be gathered during the load operation if all the data in the table is being replaced.
You can import into a host database through DB2 Connect.	You cannot load into a host database.
Import files must reside on the node from which the import utility is invoked.	In a partitioned database environment, load files or pipes must reside on the node that contains the database. In a non-partitioned database environment, load files or pipes can reside on the node that contains the database, or on the remotely connected client from which the load utility is invoked.
A backup image is not required. Because the import utility uses SQL inserts, DB2 logs the activity, and no backups are required to recover these operations in case of failure.	A backup image can be created during the load operation.

**Related concepts:**

- “Import Overview” on page 25
- “Load Overview” on page 74

**Related reference:**

- “IMPORT” on page 35
- “LOAD” on page 100

---

## Appendix C. Export/Import/Load Sessions - API Sample Program

The following sample program shows how to:

- Export data to a file
- Import data to a table
- Load data into a table
- Check the status of a load operation

The source file for this sample program (tbmove.sqc) can be found in the \sql1lib\samples\c directory. It contains both DB2 APIs and embedded SQL calls. The script file bldapp.cmd, located in the same directory, contains the commands to build this and other sample programs.

To run the sample program (executable file), enter tbmove. You might find it useful to examine some of the generated files, such as the message file, and the delimited ASCII data file.

```
/******  
** Licensed Materials - Property of IBM  
**  
** Governed under the terms of the International  
** License Agreement for Non-Warranted Sample Code.  
**  
** (C) COPYRIGHT International Business Machines Corp. 1996 - 2002  
** All Rights Reserved.  
**  
** US Government Users Restricted Rights - Use, duplication or  
** disclosure restricted by GSA ADP Schedule Contract with IBM Corp.  
*****  
**  
** SOURCE FILE NAME: tbmove.sqc  
**  
** SAMPLE: How to move table data  
**  
** DB2 APIs USED:  
**     db2Export -- Export  
**     db2Import -- Import  
**     sqluvqdp -- Quiesce Table Spaces for Table  
**     db2Load -- Load  
**     db2LoadQuery -- Load Query  
**  
** SQL STATEMENTS USED:  
**     PREPARE  
**     DECLARE CURSOR  
**     OPEN  
**     FETCH  
**     CLOSE  
**     CREATE TABLE  
**     DROP  
**  
** OUTPUT FILE: tbmove.out (available in the online documentation)  
*****  
**  
** For more information on the sample programs, see the README file.  
**  
** For information on developing C applications, see the Application  
** Development Guide.
```

```

**
** For information on using SQL statements, see the SQL Reference.
**
** For information on DB2 APIs, see the Administrative API Reference.
**
** For the latest information on programming, building, and running DB2
** applications, visit the DB2 application development website:
**   http://www.software.ibm.com/data/db2/udb/ad
*****/

#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <sqlenv.h>
#include <sqlutil.h>
#include <db2ApiDf.h>
#include "utilemb.h"

int DataExport(char *);
int TbImport(char *);
int TbLoad(char *);
int TbLoadQuery(void);

/* support function */
int ExportedDataDisplay(char *);
int NewTableDisplay(void);

EXEC SQL BEGIN DECLARE SECTION;
  char strStmt[256];
  short deptnumb;
  char deptname[15];
EXEC SQL END DECLARE SECTION;

int main(int argc, char *argv[])
{
  int rc = 0;
  char dbAlias[SQL_ALIAS_SZ + 1];
  char user[USERID_SZ + 1];
  char pswd[PSWD_SZ + 1];
  char dataFileName[256];

  /* check the command line arguments */
  rc = CmdLineArgsCheck1(argc, argv, dbAlias, user, pswd);
  if (rc != 0)
  {
    return rc;
  }

  printf("\nTHIS SAMPLE SHOWS HOW TO MOVE TABLE DATA.\n");

  /* connect to database */
  rc = DbConn(dbAlias, user, pswd);
  if (rc != 0)
  {
    return rc;
  }

#ifdef DB2NT
  sprintf(dataFileName, "%s%stbmove.DEL", getenv("DB2PATH"), PATH_SEP);
#else /* UNIX */
  sprintf(dataFileName, "%s%stbmove.DEL", getenv("HOME"), PATH_SEP);
#endif

  rc = DataExport(dataFileName);
  rc = TbImport(dataFileName);
  rc = TbLoad(dataFileName);
  rc = TbLoadQuery();
}

```

```

/* disconnect from the database */
rc = DbDisconn(dbAlias);
if (rc != 0)
{
    return rc;
}

return 0;
} /* main */

int ExportedDataDisplay(char *dataFileName)
{
    struct sqlca sqlca;
    FILE *fp;
    char buffer[100];
    int maxChars = 100;
    int numChars;
    int charNb;

    fp = fopen(dataFileName, "r");
    if (fp == NULL)
    {
        return 1;
    }

    printf("\n The content of the file '%s' is:\n", dataFileName);
    printf(" ");
    numChars = fread(buffer, 1, maxChars, fp);
    while (numChars > 0)
    {
        for (charNb = 0; charNb < numChars; charNb++)
        {
            if (buffer[charNb] == '\n')
            {
                printf("\n");
                if (charNb < numChars - 1)
                {
                    printf(" ");
                }
            }
            else
            {
                printf("%c", buffer[charNb]);
            }
        }
        numChars = fread(buffer, 1, maxChars, fp);
    }

    if (ferror(fp))
    {
        fclose(fp);
        return 1;
    }
    else
    {
        fclose(fp);
    }

    return 0;
} /* ExportedDataDisplay */

int NewTableDisplay(void)
{
    struct sqlca sqlca;

    printf("\n SELECT * FROM newtable\n");

```

```

printf("   DEPTNUMB DEPTNAME      \n");
printf("   -----\n");

strcpy(strStmt, "SELECT * FROM newtable");

EXEC SQL PREPARE stmt FROM :strStmt;
EMB_SQL_CHECK("statement -- prepare");

EXEC SQL DECLARE c0 CURSOR FOR stmt;

EXEC SQL OPEN c0;
EMB_SQL_CHECK("cursor -- open");

EXEC SQL FETCH c0 INTO :deptnumb, :deptname;
EMB_SQL_CHECK("cursor -- fetch");

while (sqlca.sqlcode != 100)
{
    printf("   %8d %-s\n", deptnumb, deptname);

    EXEC SQL FETCH c0 INTO :deptnumb, :deptname;
    EMB_SQL_CHECK("cursor -- fetch");
}

EXEC SQL CLOSE c0;

return 0;
} /* NewTableDisplay */

int DataExport(char *dataFileName)
{
    int rc = 0;
    struct sqlca sqlca;
    struct sqldcol dataDescriptor;
    char actionString[256];
    struct sqllob *pAction;
    char msgFileName[128];
    struct db2ExportOut outputInfo;
    struct db2ExportStruct exportParmStruct;

    printf("\n-----");
    printf("\nUSE THE DB2 API:\n");
    printf("  db2Export -- Export\n");
    printf("TO EXPORT DATA TO A FILE.\n");

    printf("\n  Be sure to complete all table operations and release\n");
    printf("  all locks before starting an export operation. This\n");
    printf("  can be done by issuing a COMMIT after closing all\n");
    printf("  cursors opened WITH HOLD, or by issuing a ROLLBACK.\n");
    printf("  Please refer to the 'Administrative API Reference'\n");
    printf("  for the details.\n");

    /* export data */
    dataDescriptor.dcolmeth = SQL_METH_D;
    strcpy(actionString, "SELECT deptnumb, deptname FROM org");
    pAction = (struct sqllob *)malloc(sizeof(sqluint32) +
                                     sizeof(actionString) + 1);
    pAction->length = strlen(actionString);
    strcpy(pAction->data, actionString);
    strcpy(msgFileName, "tbexport.MSG");

    exportParmStruct.piDataFileName    = dataFileName;
    exportParmStruct.piLobPathList     = NULL;
    exportParmStruct.piLobFileList     = NULL;
    exportParmStruct.piDataDescriptor  = &dataDescriptor;
    exportParmStruct.piActionString    = pAction;
    exportParmStruct.piFileType        = SQL_DEL;

```

```

exportParmStruct.piFileTypeMod      = NULL;
exportParmStruct.piMsgFileName      = msgFileName;
exportParmStruct.iCallerAction      = SQLU_INITIAL;
exportParmStruct.poExportInfoOut    = &outputInfo;

printf("\n  Export data.\n");
printf("    client destination file name: %s\n", dataFileName);
printf("    action                          : %s\n", actionString);
printf("    client message file name         : %s\n", msgFileName);

/* export data */
db2Export(db2Version820,
          &exportParmStruct,
          &sqlca);

DB2_API_CHECK("data -- export");

/* free memory allocated */
free(pAction);

/* display exported data */
rc = ExportedDataDisplay(dataFileName);

return 0;
} /* DataExport */

int TbImport(char *dataFileName)
{
    int rc = 0;
    struct sqlca sqlca;
    struct sqldcol dataDescriptor;
    char actionString[256];
    struct sqlchar *pAction;
    char msgFileName[128];
    struct db2ImportIn inputInfo;
    struct db2ImportOut outputInfo;
    struct db2ImportStruct importParmStruct;
    long commitcount = 10;

    printf("\n-----");
    printf("\nUSE THE DB2 API:\n");
    printf("  db2Import -- Import\n");
    printf("TO IMPORT DATA TO A TABLE.\n");

    /* create new table */
    printf("\n  CREATE TABLE newtable(deptnumb SMALLINT NOT NULL,");
    printf("\n                                deptname VARCHAR(14))\n");

    EXEC SQL CREATE TABLE newtable(deptnumb SMALLINT NOT NULL,
                                    deptname VARCHAR(14));
    EMB_SQL_CHECK("new table -- create");

    /* import table */
    dataDescriptor.dcolmeth = SQL_METH_D;
    strcpy(actionString, "INSERT INTO newtable");
    pAction = (struct sqlchar *)malloc(sizeof(short) +
                                       sizeof(actionString) + 1);
    pAction->length = strlen(actionString);
    strcpy(pAction->data, actionString);
    strcpy(msgFileName, "tbimport.MSG");

    /* Setup db2ImportIn structure */
    inputInfo.iRowcount = inputInfo.iRestartcount = 0;
    inputInfo.iSkipcount = inputInfo.iWarningcount = 0;
    inputInfo.iNoTimeout = 0;
    inputInfo.iAccessLevel = SQLU_ALLOW_NO_ACCESS;
    inputInfo.piCommitcount = &commitcount;

```

```

printf("\n Import table.\n");
printf(" client source file name : %s\n", dataFileName);
printf(" action : %s\n", actionString);
printf(" client message file name: %s\n", msgFileName);

ImportParmStruct.piDataFileName = dataFileName;
importParmStruct.piLobPathList = NULL;
importParmStruct.piDataDescriptor = &dataDescriptor;
importParmStruct.piActionString = pAction;
importParmStruct.piFileType = SQL_DEL;
importParmStruct.piFileTypeMod = NULL;
importParmStruct.piMsgFileName = msgFileName;
importParmStruct.piImportInfoIn = &inputInfo;
importParmStruct.poImportInfoOut = &outputInfo;
importParmStruct.piNullIndicators = NULL;
importParmStruct.iCallerAction = SQLU_INITIAL;

/* import table */
db2Import(db2Version820,
          &importParmStruct,
          &sqlca);

DB2_API_CHECK("table -- import");

/* free memory allocated */
free(pAction);

/* display import info */
printf("\n Import info.\n");
printf(" rows read : %ld\n", (int)outputInfo.oRowsRead);
printf(" rows skipped : %ld\n", (int)outputInfo.oRowsSkipped);
printf(" rows inserted : %ld\n", (int)outputInfo.oRowsInserted);
printf(" rows updated : %ld\n", (int)outputInfo.oRowsUpdated);
printf(" rows rejected : %ld\n", (int)outputInfo.oRowsRejected);
printf(" rows committed: %ld\n", (int)outputInfo.oRowsCommitted);

/* display content of the new table */
rc = NewTableDisplay();

/* drop new table */
printf("\n DROP TABLE newtable\n");

EXEC SQL DROP TABLE newtable;
EMB_SQL_CHECK("new table -- drop");

return 0;
} /* TbImport */

int TbLoad(char *dataFileName)
{
    int rc = 0;
    struct sqlca sqlca;

    struct db2LoadStruct paramStruct;
    struct db2LoadIn inputInfoStruct;
    struct db2LoadOut outputInfoStruct;

    struct sqlu_media_list mediaList;
    struct sqldcol dataDescriptor;
    char actionString[256];
    struct sqlchar *pAction;
    char localMsgFileName[128];

    printf("\n-----");
    printf("\nUSE THE DB2 API:\n");
    printf(" sqluvqdp -- Quiesce Table Spaces for Table\n");

```

```

printf(" db2Load -- Load\n");
printf("TO LOAD DATA INTO A TABLE.\n");

/* create new table */
printf("\n CREATE TABLE newtable(deptnumb SMALLINT NOT NULL,");
printf("\n                                deptname VARCHAR(14))\n");

EXEC SQL CREATE TABLE newtable(deptnumb SMALLINT NOT NULL,
                                deptname VARCHAR(14));
EMB_SQL_CHECK("new table -- create");

/* quiesce table spaces for table */
printf("\n Quiesce the table spaces for 'newtable'.\n");

EXEC SQL COMMIT;
EMB_SQL_CHECK("transaction -- commit");

/* quiesce table spaces for table */
sqluvqdp("newtable", SQLU_QUIESCEMODE_RESET_OWNED, NULL, &sqlca);
DB2_API_CHECK("tablespaces for table -- quiesce");

/* load table */
mediaList.media_type = SQLU_CLIENT_LOCATION;
mediaList.sessions = 1;
mediaList.target.location =
    (struct sqlu_location_entry *)malloc(sizeof(struct sqlu_location_entry) *
                                        mediaList.sessions);
strcpy(mediaList.target.location->location_entry, dataFileName);

dataDescriptor.dcolmeth = SQL_METH_D;

strcpy(actionString, "INSERT INTO newtable");
pAction = (struct sqlchar *)malloc(sizeof(short) +
                                   sizeof(actionString) + 1);
pAction->length = strlen(actionString);
strcpy(pAction->data, actionString);

strcpy(localMsgFileName, "tblload.MSG");

/* Setup the input information structure */
inputInfoStruct.piUseTablespace = NULL;
inputInfoStruct.iSavecount = 0; /* consistency points */
/* as infrequently as possible */
inputInfoStruct.iRestartcount = 0; /* start at row 1 */
inputInfoStruct.iRowcount = 0; /* load all rows */
inputInfoStruct.iWarningcount = 0; /* don't stop for warnings */
inputInfoStruct.iDataBufferSize = 0; /* default data buffer size */
inputInfoStruct.iSortBufferSize = 0; /* def. warning buffer size */
inputInfoStruct.iHoldQuiesce = 0; /* don't hold the quiesce */
inputInfoStruct.iRestartphase = ' '; /* ignored anyway */
inputInfoStruct.iStatsOpt = SQLU_STATS_NONE; /* don't bother with them */
inputInfoStruct.iIndexingMode = SQLU_INX_AUTOSELECT; /* let load choose */
/* indexing mode */

inputInfoStruct.iCpuParallelism = 0;
inputInfoStruct.iNonrecoverable = SQLU_NON_RECOVERABLE_LOAD;
inputInfoStruct.iAccessLevel = SQLU_ALLOW_NO_ACCESS;
inputInfoStruct.iLockWithForce = SQLU_NO_FORCE;
inputInfoStruct.iCheckPending = SQLU_CHECK_PENDING_CASCADE_DEFERRED;

/* Setup the parameter structure */
paramStruct.piSourceList = &mediaList;
paramStruct.piLobPathList = NULL;
paramStruct.piDataDescriptor = &dataDescriptor;
paramStruct.piActionString = pAction;
paramStruct.piFileType = SQL_DEL;
paramStruct.piFileTypeMod = NULL;
paramStruct.piLocalMsgFileName = localMsgFileName;

```

```

paramStruct.piTempFilesPath = NULL;
paramStruct.piVendorSortWorkPaths = NULL;
paramStruct.piCopyTargetList = NULL;
paramStruct.piNullIndicators = NULL;
paramStruct.piLoadInfoIn = &inputInfoStruct;
paramStruct.poLoadInfoOut = &outputInfoStruct;
paramStruct.piPartLoadInfoIn = NULL;
paramStruct.poPartLoadInfoOut = NULL;
paramStruct.iCallerAction = SQLU_INITIAL;

printf("\n Load table.\n");
printf(" client source file name : %s\n", dataFileName);
printf(" action : %s\n", actionString);
printf(" client message file name: %s\n", localMsgFileName);

/* load table */
db2Load (db2Version810, /* Database version number */
        &paramStruct, /* In/out parameters */
        &sqlca); /* SQLCA */

DB2_API_CHECK("table -- load");

/* free memory allocated */
free(pAction);

/* display load info */
printf("\n Load info.\n");
printf(" rows read : %d\n", (int)outputInfoStruct.oRowsRead);
printf(" rows skipped : %d\n", (int)outputInfoStruct.oRowsSkipped);
printf(" rows loaded : %d\n", (int)outputInfoStruct.oRowsLoaded);
printf(" rows deleted : %d\n", (int)outputInfoStruct.oRowsDeleted);
printf(" rows rejected : %d\n", (int)outputInfoStruct.oRowsRejected);
printf(" rows committed: %d\n", (int)outputInfoStruct.oRowsCommitted);

/* display content of the new table */
rc = NewTableDisplay();

/* drop new table */
printf("\n DROP TABLE newtable\n");

EXEC SQL DROP TABLE newtable;
EMB_SQL_CHECK("new table -- drop");

return 0;
} /* TbLoad */

int TbLoadQuery(void)
{
    int rc = 0;
    struct sqlca sqlca;
    char tableName[128];
    char loadMsgFileName[128];
    db2LoadQueryStruct loadQueryParameters;
    db2LoadQueryOutputStruct loadQueryOutputStructure;

    printf("\n-----");
    printf("\nUSE THE DB2 API:\n");
    printf(" db2LoadQuery -- Load Query\n");
    printf("TO CHECK THE STATUS OF A LOAD OPERATION.\n");

    /* Initialize structures */
    memset(&loadQueryParameters, 0, sizeof(db2LoadQueryStruct));
    memset(&loadQueryOutputStructure, 0, sizeof(db2LoadQueryOutputStruct));

    /* Set up the tablename to query. */
    loadQueryParameters.iStringType = DB2LOADQUERY_TABLENAME;
    loadQueryParameters.piString = tableName;

```

```

/* Specify that we want all LOAD messages to be reported. */
loadQueryParameters.iShowLoadMessages = DB2LOADQUERY_SHOW_ALL_MSGS;

/* LOAD summary information goes here. */
loadQueryParameters.poOutputStruct = &loadQueryOutputStructure;

/* Set up the local message file. */
loadQueryParameters.piLocalMessageFile = loadMsgFileName;

/* call the DB2 API */
strcpy(tableName, "ORG");
strcpy(loadMsgFileName, "tbldqry.MSG");

/* load query */
db2LoadQuery(db2Version810, &loadQueryParameters, &sqlca);
printf("\n Note: the table load for '%s' is NOT in progress.\n", tableName);
printf(" So an empty message file '%s' will be created,\n", loadMsgFileName);
printf(" and the following values will be zero.\n");
DB2_API_CHECK("status of load operation -- check");

printf("\n Load status has been written to local file %s.\n",
       loadMsgFileName);

printf("   Number of rows read           = %d\n",
       loadQueryOutputStructure.oRowsRead);

printf("   Number of rows skipped          = %d\n",
       loadQueryOutputStructure.oRowsSkipped);

printf("   Number of rows loaded           = %d\n",
       loadQueryOutputStructure.oRowsLoaded);

printf("   Number of rows rejected         = %d\n",
       loadQueryOutputStructure.oRowsRejected);

printf("   Number of rows deleted          = %d\n",
       loadQueryOutputStructure.oRowsDeleted);

printf("   Number of rows committed        = %d\n",
       loadQueryOutputStructure.oRowsCommitted);

printf("   Number of warnings              = %d\n",
       loadQueryOutputStructure.oWarningCount);

return 0;
} /* TbLoadQuery */

```



---

## Appendix D. File Formats

---

### Export/Import/Load Utility File Formats

Five operating system file formats supported by the DB2<sup>®</sup> export, import, and load utilities are described:

**DEL** Delimited ASCII, for data exchange among a wide variety of database managers and file managers. This common approach to storing data uses special character delimiters to separate column values.

**ASC** Non-delimited ASCII, for importing or loading data from other applications that create flat text files with aligned column data.

**PC/IXF**

PC version of the Integrated Exchange Format (IXF), the preferred method for data exchange within the database manager. PC/IXF is a structured description of a database table that contains an external representation of the internal table.

**WSF** Work-sheet format, for data exchange with products such as Lotus<sup>®</sup> 1-2-3<sup>®</sup> and Symphony. The load utility does not support this file format.

**CURSOR**

A cursor declared against an SQL query. This file type is only supported by the load utility.

When using DEL, WSF, or ASC data file formats, define the table, including its column names and data types, before importing the file. The data types in the operating system file fields are converted into the corresponding type of data in the database table. The import utility accepts data with minor incompatibility problems, including character data imported with possible padding or truncation, and numeric data imported into different types of numeric fields.

When using the PC/IXF data file format, the table does not need to exist before beginning the import operation. User-defined distinct types (UDTs) are not made part of the new table column types; instead, the base type is used. Similarly, when exporting to the PC/IXF data file format, UDTs are stored as base data types in the PC/IXF file.

When using the CURSOR file type, the table, including its column names and data types, must be defined before beginning the load operation. The column types of the SQL query must be compatible with the corresponding column types in the target table. It is not necessary for the specified cursor to be open before starting the load operation. The load utility will process the entire result of the query associated with the specified cursor whether or not the cursor has been used to fetch rows.

**Related concepts:**

- “Queries and table expressions” in the *SQL Reference, Volume 1*

**Related reference:**

- “Delimited ASCII (DEL) File Format” on page 244
- “Non-delimited ASCII (ASC) File Format” on page 249

- “PC Version of IXF File Format” on page 252
- “Casting between data types” in the *SQL Reference, Volume 1*
- “Assignments and comparisons” in the *SQL Reference, Volume 1*

**Related samples:**

- “dtformat.out -- HOW TO LOAD AND IMPORT DATA FORMAT EXTENSIONS (C)”
- “dtformat.sqc -- Load and import data format extensions (C)”

## Delimited ASCII (DEL) File Format

A Delimited ASCII (DEL) file is a sequential ASCII file with row and column delimiters. Each DEL file is a stream of ASCII characters consisting of cell values ordered by row, and then by column. Rows in the data stream are separated by row delimiters; within each row, individual cell values are separated by column delimiters.

The following table describes the format of DEL files that can be imported, or that can be generated as the result of an export action.

```

DEL file ::= Row 1 data || Row delimiter ||
           Row 2 data || Row delimiter ||
           .
           .
           Row n data || Optional row delimiter

Row i data ::= Cell value(i,1) || Column delimiter ||
              Cell value(i,2) || Column delimiter ||
              .
              .
              Cell value(i,m)

Row delimiter ::= ASCII line feed sequencea

Column delimiter ::= Default value ASCII comma (,)b

Cell value(i,j) ::= Leading spaces
                  || ASCII representation of a numeric value
                   (integer, decimal, or float)
                  || Delimited character string
                  || Non-delimited character string
                  || Trailing spaces

Non-delimited character string ::= A set of any characters except a
                                row delimiter or a column delimiter

Delimited character string ::= A character string delimiter ||
                              An extended character string ||
                              A character string delimiter ||
                              Trailing garbage

Trailing garbage ::= A set of any characters except a row delimiter
                    or a column delimiter

Character string delimiter ::= Default value ASCII double quotation
                              marks ("c)

extended character string ::= || A set of any characters except a
                              row delimiter or a character string
                              delimiter if the NODOUBLEDEL
  
```

```

        modifier is specified
    || A set of any characters except a
        row delimiter or a character string
        delimiter if the character string
        is not part of two consecutive
        character string delimiters
    || A set of any characters except a
        character string delimiter if the
        character string delimiter is not
        part of two consecutive character
        string delimiters, and the DELPRIORITYCHAR
        modifier is specified

```

End-of-file character ::= Hex '1A' (Windows operating system only)

```

ASCII representation of a numeric valued ::= Optional sign '+' or '-'
    || 1 to 31 decimal digits with an optional decimal point before,
        after, or between two digits
    || Optional exponent

```

```

Exponent ::= Character 'E' or 'e'
    || Optional sign '+' or '-'
    || 1 to 3 decimal digits with no decimal point

```

Decimal digit ::= Any one of the characters '0', '1', ... '9'

Decimal point ::= Default value ASCII period (.)<sup>e</sup>

- <sup>a</sup> The record delimiter is assumed to be a new line character, ASCII x0A. Data generated on the Windows operating system can use the carriage return/line feed 2-byte standard of 0x0D0A. Data in EBCDIC code pages should use the EBCDIC LF character (0x25) as the record delimiter (EBCDIC data can be loaded using the CODEPAGE option on the LOAD command).
- <sup>b</sup> The column delimiter can be specified with the COLDEL option.
- <sup>c</sup> The character string delimiter can be specified with the CHARDEL option.

**Note:** The default priority of delimiters is:

1. Record delimiter
  2. Character delimiter
  3. Column delimiter
- <sup>d</sup> If the ASCII representation of a numeric value contains an exponent, it is a FLOAT constant. If it has a decimal point but no exponent, it is a DECIMAL constant. If it has no decimal point and no exponent, it is an INTEGER constant.
  - <sup>e</sup> The decimal point character can be specified with the DECPT option.

**Related reference:**

- “DEL Data Type Descriptions” on page 246

---

## Example and Data Type Descriptions

### Example DEL File

Following is an example of a DEL file. Each line ends with a line feed sequence (on the Windows operating system, each line ends with a carriage return/line feed sequence).

```
"Smith, Bob",4973,15.46
"Jones, Bill",12345,16.34
"Williams, Sam",452,193.78
```

The following example illustrates the use of non-delimited character strings. The column delimiter has been changed to a semicolon, because the character data contains a comma.

```
Smith, Bob;4973;15.46
Jones, Bill;12345;16.34
Williams, Sam;452;193.78
```

**Notes:**

1. A space (X'20') is never a valid delimiter.
2. Spaces that precede the first character, or that follow the last character of a cell value, are discarded during import. Spaces that are embedded in a cell value are not discarded.
3. A period (.) is not a valid character string delimiter, because it conflicts with periods in time stamp values.
4. For pure DBCS (graphic), mixed DBCS, and EUC, delimiters are restricted to the range of x00 to x3F, inclusive.
5. For DEL data specified in an EBCDIC code page, the delimiters may not coincide with the shift-in and shift-out DBCS characters.
6. On the Windows operating system, the first occurrence of an end-of-file character (X'1A') that is not within character delimiters indicates the end-of-file. Any subsequent data is not imported.
7. A null value is indicated by the absence of a cell value where one would normally occur, or by a string of spaces.
8. Since some products restrict character fields to 254 or 255 bytes, the export utility generates a warning message whenever a character column of maximum length greater than 254 bytes is selected for export. The import utility accommodates fields that are as long as the longest LONG VARCHAR and LONG VARGRAPHIC columns.

## DEL Data Type Descriptions

*Table 16. Acceptable Data Type Forms for the DEL File Format*

Data Type	Form in Files Created by the Export Utility	Form Acceptable to the Import Utility
BIGINT	An INTEGER constant in the range -9 223 372 036 854 775 808 to 9 223 372 036 854 775 807.	ASCII representation of a numeric value in the range -9 223 372 036 854 775 808 to 9 223 372 036 854 775 807. Decimal and float numbers are truncated to integer values.
BLOB, CLOB	Character data enclosed by character delimiters (for example, double quotation marks).	A delimited or non-delimited character string. The character string is used as the database column value.

Table 16. Acceptable Data Type Forms for the DEL File Format (continued)

Data Type	Form in Files Created by the Export Utility	Form Acceptable to the Import Utility
BLOB_FILE, CLOB_FILE	The character data for each BLOB/CLOB column is stored in individual files, and the file name is enclosed by character delimiters.	The delimited or non-delimited name of the file that holds the data.
CHAR	Character data enclosed by character delimiters (for example, double quotation marks).	A delimited or non-delimited character string. The character string is truncated or padded with spaces (X'20'), if necessary, to match the width of the database column.
DATE	<p><i>yyyymmdd</i> (year month day) with no character delimiters. For example: 19931029</p> <p>Alternatively, the DATESISO option can be used to specify that all date values are to be exported in ISO format.</p>	A delimited or non-delimited character string containing a date value in an ISO format consistent with the territory code of the target database, or a non-delimited character string of the form <i>yyyymmdd</i> .
DBCLOB (DBCS only)	Graphic data is exported as a delimited character string.	A delimited or non-delimited character string, an even number of bytes in length. The character string is used as the database column value.
DBCLOB_FILE (DBCS only)	The character data for each DBCLOB column is stored in individual files, and the file name is enclosed by character delimiters.	The delimited or non-delimited name of the file that holds the data.
DECIMAL	A DECIMAL constant with the precision and scale of the field being exported. The DECPLUSBLANK option can be used to specify that positive decimal values are to be prefixed with a blank space instead of a plus sign (+).	ASCII representation of a numeric value that does not overflow the range of the database column into which the field is being imported. If the input value has more digits after the decimal point than can be accommodated by the database column, the excess digits are truncated.
FLOAT(long)	A FLOAT constant in the range -10E307 to 10E307.	ASCII representation of a numeric value in the range -10E307 to 10E307.
GRAPHIC (DBCS only)	Graphic data is exported as a delimited character string.	A delimited or non-delimited character string, an even number of bytes in length. The character string is truncated or padded with double-byte spaces (for example, X'8140'), if necessary, to match the width of the database column.

Table 16. Acceptable Data Type Forms for the DEL File Format (continued)

Data Type	Form in Files Created by the Export Utility	Form Acceptable to the Import Utility
INTEGER	An INTEGER constant in the range -2 147 483 648 to 2 147 483 647.	ASCII representation of a numeric value in the range -2 147 483 648 to 2 147 483 647. Decimal and float numbers are truncated to integer values.
LONG VARCHAR	Character data enclosed by character delimiters (for example, double quotation marks).	A delimited or non-delimited character string. The character string is used as the database column value.
LONG VARGRAPHIC (DBCS only)	Graphic data is exported as a delimited character string.	A delimited or non-delimited character string, an even number of bytes in length. The character string is used as the database column value.
SMALLINT	An INTEGER constant in the range -32 768 to 32 767.	ASCII representation of a numeric value in the range -32 768 to 32 767. Decimal and float numbers are truncated to integer values.
TIME	<i>hh.mm.ss</i> (hour minutes seconds). A time value in ISO format enclosed by character delimiters. For example: "09.39.43"	A delimited or non-delimited character string containing a time value in a format consistent with the territory code of the target database.
TIMESTAMP	<i>yyyy-mm-dd-hh.mm.ss.nnnnnn</i> (year month day hour minutes seconds microseconds). A character string representing a date and time enclosed by character delimiters.	A delimited or non-delimited character string containing a time stamp value acceptable for storage in a database.
VARCHAR	Character data enclosed by character delimiters (for example, double quotation marks).	A delimited or non-delimited character string. The character string is truncated, if necessary, to match the maximum width of the database column.
VARGRAPHIC (DBCS only)	Graphic data is exported as a delimited character string.	A delimited or non-delimited character string, an even number of bytes in length. The character string is truncated, if necessary, to match the maximum width of the database column.

---

## Non-delimited ASCII (ASC) File Format

A non-delimited ASCII (ASC) file is a sequential ASCII file with row delimiters. It can be used for data exchange with any ASCII product that has a columnar format for data, including word processors. Each ASC file is a stream of ASCII characters consisting of data values ordered by row and column. Rows in the data stream are separated by row delimiters. Each column within a row is defined by a beginning-ending location pair (specified by IMPORT parameters). Each pair represents locations within a row specified as byte positions. The first position within a row is byte position 1. The first element of each location pair is the byte on which the column begins, and the second element of each location pair is the byte on which the column ends. The columns might overlap. Every row in an ASC file has the same column definition.

An ASC file is defined by:

```
ASC file ::= Row 1 data || Row delimiter ||  
           Row 2 data || Row delimiter ||  
           .  
           .  
           .  
           Row n data
```

```
Row i data ::= ASCII characters || Row delimiter
```

```
Row Delimiter ::= ASCII line feed sequencea
```

- <sup>a</sup> The record delimiter is assumed to be a new line character, ASCII x0A. Data generated on the Windows operating system can use the carriage return/line feed 2-byte standard of 0x0D0A. Data in EBCDIC code pages should use the EBCDIC LF character (0x25) as the record delimiter (EBCDIC data can be loaded using the CODEPAGE option on the LOAD command). The record delimiter is never interpreted to be part of a field of data.

**Related reference:**

- “ASC Data Type Descriptions” on page 250

---

## Example and Data Type Descriptions

### Example ASC File

Following is an example of an ASC file. Each line ends with a line feed sequence (on the Windows operating system, each line ends with a carriage return/line feed sequence).

```
Smith, Bob      4973      15.46  
Jones, Suzanne 12345      16.34  
Williams, Sam  452123    193.78
```

**Notes:**

1. ASC files are assumed not to contain column names.
2. Character strings are *not* enclosed by delimiters. The data type of a column in the ASC file is determined by the data type of the target column in the database table.
3. A NULL is imported into a nullable database column if:
  - A field of blanks is targeted for a numeric, DATE, TIME, or TIMESTAMP database column
  - A field with no beginning and ending location pairs is specified

- A location pair with beginning and ending locations equal to zero is specified
  - A row of data is too short to contain a valid value for the target column
  - The NULL INDICATORS load option is used, and an N (or other value specified by the user) is found in the null indicator column.
4. If the target column is not nullable, an attempt to import a field of blanks into a numeric, DATE, TIME, or TIMESTAMP column causes the row to be rejected.
  5. If the input data is not compatible with the target column, and that column is nullable, a null is imported or the row is rejected, depending on where the error is detected. If the column is not nullable, the row is rejected. Messages are written to the message file, specifying incompatibilities that are found.

## ASC Data Type Descriptions

Table 17. Acceptable Data Type Forms for the ASC File Format

Data Type	Form Acceptable to the Import Utility
BIGINT	<p>A constant in any numeric type (SMALLINT, INTEGER, BIGINT, DECIMAL, or FLOAT) is accepted. Individual values are rejected if they are not in the range -9 223 372 036 854 775 808 to 9 223 372 036 854 775 807. Decimal numbers are truncated to integer values. A comma, period, or colon is considered to be a decimal point. Thousands separators are not allowed.</p> <p>The beginning and ending locations should specify a field whose width does not exceed 50 bytes. Integers, decimal numbers, and the mantissas of floating point numbers can have no more than 31 digits. Exponents of floating point numbers can have no more than 3 digits.</p>
BLOB/CLOB	A string of characters. The character string is truncated on the right, if necessary, to match the maximum length of the target column. If the ASC <i>truncate blanks</i> option is in effect, trailing blanks are stripped from the original or the truncated string.
BLOB_FILE, CLOB_FILE, DBCLOB_FILE (DBCS only)	A delimited or non-delimited name of the file that holds the data.
CHAR	A string of characters. The character string is truncated or padded with spaces on the right, if necessary, to match the width of the target column.
DATE	<p>A character string representing a date value in a format consistent with the territory code of the target database.</p> <p>The beginning and ending locations should specify a field width that is within the range for the external representation of a date.</p>
DBCLOB (DBCS only)	A string of an even number of bytes. A string of an odd number of bytes is invalid and is not accepted. A valid string is truncated on the right, if necessary, to match the maximum length of the target column.

Table 17. Acceptable Data Type Forms for the ASC File Format (continued)

Data Type	Form Acceptable to the Import Utility
DECIMAL	<p>A constant in any numeric type (SMALLINT, INTEGER, BIGINT, DECIMAL, or FLOAT) is accepted. Individual values are rejected if they are not in the range of the database column into which they are being imported. If the input value has more digits after the decimal point than the scale of the database column, the excess digits are truncated. A comma, period, or colon is considered to be a decimal point. Thousands separators are not allowed.</p> <p>The beginning and ending locations should specify a field whose width does not exceed 50 bytes. Integers, decimal numbers, and the mantissas of floating point numbers can have no more than 31 digits. Exponents of floating point numbers can have no more than 3 digits.</p>
FLOAT(long)	<p>A constant in any numeric type (SMALLINT, INTEGER, BIGINT, DECIMAL, or FLOAT) is accepted. All values are valid. A comma, period, or colon is considered to be a decimal point. An uppercase or lowercase E is accepted as the beginning of the exponent of a FLOAT constant.</p> <p>The beginning and ending locations should specify a field whose width does not exceed 50 bytes. Integers, decimal numbers, and the mantissas of floating point numbers can have no more than 31 digits. Exponents of floating point numbers can have no more than 3 digits.</p>
GRAPHIC (DBCS only)	<p>A string of an even number of bytes. A string of an odd number of bytes is invalid and is not accepted. A valid string is truncated or padded with double-byte spaces (0x8140) on the right, if necessary, to match the maximum length of the target column.</p>
INTEGER	<p>A constant in any numeric type (SMALLINT, INTEGER, BIGINT, DECIMAL, or FLOAT) is accepted. Individual values are rejected if they are not in the range -2 147 483 648 to 2 147 483 647. Decimal numbers are truncated to integer values. A comma, period, or colon is considered to be a decimal point. Thousands separators are not allowed.</p> <p>The beginning and ending locations should specify a field whose width does not exceed 50 bytes. Integers, decimal numbers, and the mantissas of floating point numbers can have no more than 31 digits. Exponents of floating point numbers can have no more than 3 digits.</p>
LONG VARCHAR	<p>A string of characters. The character string is truncated on the right, if necessary, to match the maximum length of the target column. If the ASC <i>truncate blanks</i> option is in effect, trailing blanks are stripped from the original or the truncated string.</p>
LONG VARGRAPHIC (DBCS only)	<p>A string of an even number of bytes. A string of an odd number of bytes is invalid and is not accepted. A valid string is truncated on the right, if necessary, to match the maximum length of the target column.</p>

Table 17. Acceptable Data Type Forms for the ASC File Format (continued)

Data Type	Form Acceptable to the Import Utility
SMALLINT	<p>A constant in any numeric type (SMALLINT, INTEGER, BIGINT, DECIMAL, or FLOAT) is accepted. Individual values are rejected if they are not in the range -32 768 to 32 767. Decimal numbers are truncated to integer values. A comma, period, or colon is considered to be a decimal point. Thousands separators are not allowed.</p> <p>The beginning and ending locations should specify a field whose width does not exceed 50 bytes. Integers, decimal numbers, and the mantissas of floating point numbers can have no more than 31 digits. Exponents of floating point numbers can have no more than 3 digits.</p>
TIME	<p>A character string representing a time value in a format consistent with the territory code of the target database.</p> <p>The beginning and ending locations should specify a field width that is within the range for the external representation of a time.</p>
TIMESTAMP	<p>A character string representing a time stamp value acceptable for storage in a database.</p> <p>The beginning and ending locations should specify a field width that is within the range for the external representation of a time stamp.</p>
VARCHAR	<p>A string of characters. The character string is truncated on the right, if necessary, to match the maximum length of the target column. If the ASC <i>truncate blanks</i> option is in effect, trailing blanks are stripped from the original or the truncated string.</p>
VARGRAPHIC (DBCS only)	<p>A string of an even number of bytes. A string of an odd number of bytes is invalid and is not accepted. A valid string is truncated on the right, if necessary, to match the maximum length of the target column.</p>

## PC Version of IXF File Format

The PC version of IXF (PC/IXF) file format is a database manager adaptation of the Integration Exchange Format (IXF) data interchange architecture. The IXF architecture was specifically designed to enable the exchange of relational database structures and data. The PC/IXF architecture allows the database manager to export a database without having to anticipate the requirements and idiosyncrasies of a receiving product. Similarly, a product importing a PC/IXF file need only understand the PC/IXF architecture; the characteristics of the product which exported the file are not relevant. The PC/IXF file architecture maintains the independence of both the exporting and the importing database systems.

The IXF architecture is a generic relational database exchange format that supports a rich set of relational data types, including some types that might not be supported by specific relational database products. The PC/IXF file format preserves this flexibility; for example, the PC/IXF architecture supports both single-byte character string (SBCS) and double-byte character string (DBCS) data types. Not all implementations support all PC/IXF data types; however, even restricted implementations provide for the detection and disposition of unsupported data types during import.

In general, a PC/IXF file consists of an unbroken sequence of variable-length records. The file contains the following record types in the order shown:

- One header record of record type H
- One table record of record type T
- Multiple column descriptor records of record type C (one record for each column in the table)
- Multiple data records of record type D (each row in the table is represented by one or more D records).

A PC/IXF file might also contain application records of record type A, anywhere after the H record. These records are permitted in PC/IXF files to enable an application to include additional data, not defined by the PC/IXF format, in a PC/IXF file. A records are ignored by any program reading a PC/IXF file that does not have particular knowledge about the data format and content implied by the application identifier in the A record.

Every record in a PC/IXF file begins with a record length indicator. This is a 6-byte right justified character representation of an integer value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. Programs reading PC/IXF files should use these record lengths to locate the end of the current record and the beginning of the next record. H, T, and C records must be sufficiently large to include all of their defined fields, and, of course, their record length fields must agree with their actual lengths. However, if extra data (for example, a *new* field), is added to the end of one of these records, pre-existing programs reading PC/IXF files should ignore the extra data, and generate no more than a warning message. Programs writing PC/IXF files, however, should write H, T and C records that are the precise length needed to contain all of the defined fields.

If a PC/IXF file contains LOB Location Specifier (LLS) columns, each LLS column must have its own D record. D records are automatically created by the export utility, but you will need to create them manually if you are using a third party tool to generate the PC/IXF files. Further, an LLS is required for each LOB column in a table, including those with a null value. If a LOB column is null, you will need to create an LLS representing a null LOB.

PC/IXF file records are composed of fields which contain character data. The import and export utilities interpret this character data using the CPGID of the target database, with two exceptions:

- The IXFADATA field of A records.  
The code page environment of character data contained in an IXFADATA field is established by the application which creates and processes a particular A record; that is, the environment varies by implementation.
- The IXFDCOLS field of D records.  
The code page environment of character data contained in an IXFDCOLS field is a function of information contained in the C record which defines a particular column and its data.

Numeric fields in H, T, and C records, and in the prefix portion of D and A records should be right justified single-byte character representations of integer values, filled with leading zeros or blanks. A value of zero should be indicated with at least one (right justified) zero character, not blanks. Whenever one of these numeric

fields is not used, for example IXFCLENG, where the length is implied by the data type, it should be filled with blanks. These numeric fields are:

```
IXFHRECL, IXFTRECL, IXFCRECL, IXFDRECL, IXFARECL,
IXFHHCNT, IXFHSBCP, IXFHDBCP, IXFTCCNT, IXFTNAML,
IXFCLENG, IXFCDRID, IXFCPOSN, IXFCNAML, IXFCTYPE,
IXFCSBCP, IXFCBCP, IXFCNDIM, IXFCDSIZ, IXFDRID
```

**Note:** The database manager PC/IXF file format is not identical to the System/370.

**Related reference:**

- "PC/IXF Record Types" on page 254
- "PC/IXF Data Types" on page 270
- "General Rules Governing PC/IXF File Import into Databases" on page 279
- "Data Type-Specific Rules Governing PC/IXF File Import into Databases" on page 281
- "FORCEIN Option" on page 283
- "Differences Between PC/IXF and Version 0 System/370 IXF" on page 290
- "PC/IXF Data Type Descriptions" on page 275

## PC Version of IXF File Format - Details

### PC/IXF Record Types

There are five basic PC/IXF record types:

- header
- table
- column descriptor
- data
- application

and six application subtypes that DB2 UDB uses:

- index
- hierarchy
- subtable
- continuation
- terminate
- identity

Each PC/IXF record type is defined as a sequence of fields; these fields are required, and must appear in the order shown.

HEADER RECORD

FIELD NAME	LENGTH	TYPE	COMMENTS
-----	-----	-----	-----
IXFHRECL	06-BYTE	CHARACTER	record length
IXFHRECT	01-BYTE	CHARACTER	record type = 'H'
IXFHID	03-BYTE	CHARACTER	IXF identifier
IXFHVERS	04-BYTE	CHARACTER	IXF version
IXFHPROD	12-BYTE	CHARACTER	product
IXFHDATE	08-BYTE	CHARACTER	date written
IXFHTIME	06-BYTE	CHARACTER	time written
IXFHHCNT	05-BYTE	CHARACTER	heading record count

IXFHSBCP	05-BYTE	CHARACTER	single byte code page
IXFHDBCP	05-BYTE	CHARACTER	double byte code page
IXHFHIL1	02-BYTE	CHARACTER	reserved

The following fields are contained in the header record:

**IXFHRECL**

The record length indicator. A 6-byte character representation of an integer value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. The H record must be sufficiently long to include all of its defined fields.

**IXFHRECT**

The IXF record type, which is set to H for this record.

**IXFHID**

The file format identifier, which is set to IXF for this file.

**IXFHVERS**

The PC/IXF format level used when the file was created, which is set to '0002'.

**IXFHPROD**

A field that can be used by the program creating the file to identify itself. If this field is filled in, the first six bytes are used to identify the product creating the file, and the last six bytes are used to indicate the version or release of the creating product. The database manager uses this field to signal the existence of database manager-specific data.

**IXFHDATE**

The date on which the file was written, in the form *yyyymmdd*.

**IXFHTIME**

The time at which the file was written, in the form *hhmmss*. This field is optional and can be left blank.

**IXFHHCNT**

The number of H, T, and C records in this file that precede the first data record. A records are not included in this count.

**IXFHSBCP**

Single-byte code page field, containing a single-byte character representation of a SBCS CPGID or '00000'.

The export utility sets this field equal to the SBCS CPGID of the exported database table. For example, if the table SBCS CPGID is 850, this field contains '00850'.

**IXFHDBCP**

Double-byte code page field, containing a single-byte character representation of a DBCS CPGID or '00000'.

The export utility sets this field equal to the DBCS CPGID of the exported database table. For example, if the table DBCS CPGID is 301, this field contains '00301'.

**IXHFHIL1**

Spare field set to two blanks to match a reserved field in host IXF files.

TABLE RECORD

FIELD NAME	LENGTH	TYPE	COMMENTS
-----	-----	-----	-----

IXFTRECL	006-BYTE	CHARACTER	record length
IXFTRECT	001-BYTE	CHARACTER	record type = 'T'
IXFTNAML	003-BYTE	CHARACTER	name length
IXFTNAME	256-BYTE	CHARACTER	name of data
IXFTQULL	003-BYTE	CHARACTER	qualifier length
IXFTQUAL	256-BYTE	CHARACTER	qualifier
IXFTSRC	012-BYTE	CHARACTER	data source
IXFTDATA	001-BYTE	CHARACTER	data convention = 'C'
IXFTFORM	001-BYTE	CHARACTER	data format = 'M'
IXFTMFRM	005-BYTE	CHARACTER	machine format = 'PC'
IXFTLOC	001-BYTE	CHARACTER	data location = 'I'
IXFTCCNT	005-BYTE	CHARACTER	'C' record count
IXFTFIL1	002-BYTE	CHARACTER	reserved
IXFTDESC	030-BYTE	CHARACTER	data description
IXFTPKNM	257-BYTE	CHARACTER	primary key name
IXFTDSPC	257-BYTE	CHARACTER	reserved
IXFTISPC	257-BYTE	CHARACTER	reserved
IXFTLSPC	257-BYTE	CHARACTER	reserved

The following fields are contained in the table record:

#### **IXFTRECL**

The record length indicator. A 6-byte character representation of an integer value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. The T record must be sufficiently long to include all of its defined fields.

#### **IXFTRECT**

The IXF record type, which is set to T for this record.

#### **IXFTNAML**

The length, in bytes, of the table name in the IXFTNAME field.

#### **IXFTNAME**

The name of the table. If each file has only one table, this is an informational field only. The database manager does not use this field when importing data. When writing a PC/IXF file, the database manager writes the DOS file name (and possibly path information) to this field.

#### **IXFTQULL**

The length, in bytes, of the table name qualifier in the IXFTQUAL field.

#### **IXFTQUAL**

Table name qualifier, which identifies the creator of a table in a relational system. This is an informational field only. If a program writing a file has no data to write to this field, the preferred fill value is blanks. Programs reading a file might print or display this field, or store it in an informational field, but no computations should depend on the content of this field.

#### **IXFTSRC**

Used to indicate the original source of the data. This is an informational field only. If a program writing a file has no data to write to this field, the preferred fill value is blanks. Programs reading a file might print or display this field, or store it in an informational field, but no computations should depend on the content of this field.

#### **IXFTDATA**

Convention used to describe the data. This field must be set to C for

import and export, indicating that individual column attributes are described in the following column descriptor (C) records, and that data follows PC/IXF conventions.

#### IXFTFORM

Convention used to store numeric data. This field must be set to M, indicating that numeric data in the data (D) records is stored in the machine (internal) format specified by the IXFTMFRM field.

#### IXFTMFRM

The format of any machine data in the PC/IXF file. The database manager will only read or write files if this field is set to PCbbb, where b represents a blank, and PC specifies that data in the PC/IXF file is in IBM PC machine format.

#### IXFTLOC

The location of the data. The database manager only supports a value of I, meaning the data is internal to this file.

#### IXFTCCNT

The number of C records in this table. It is a right-justified character representation of an integer value.

#### IXFTFIL1

Spare field set to two blanks to match a reserved field in host IXF files.

#### IXFTDESC

Descriptive data about the table. This is an informational field only. If a program writing a file has no data to write to this field, the preferred fill value is blanks. Programs reading a file might print or display this field, or store it in an informational field, but no computations should depend on the content of this field. This field contains NOT NULL WITH DEFAULT if the column was not null with default, and the table name came from a workstation database.

#### IXFTPKNM

The name of the primary key defined on the table (if any). The name is stored as a null-terminated string.

#### IXFTDSPC

This field is reserved for future use.

#### IXFTISPC

This field is reserved for future use.

#### IXFTLSPC

This field is reserved for future use.

#### COLUMN DESCRIPTOR RECORD

FIELD NAME	LENGTH	TYPE	COMMENTS
-----	-----	-----	-----
IXFCRECL	006-BYTE	CHARACTER	record length
IXFCRECT	001-BYTE	CHARACTER	record type = 'C'
IXFCNAML	003-BYTE	CHARACTER	column name length
IXFCNAME	256-BYTE	CHARACTER	column name
IXFCNULL	001-BYTE	CHARACTER	column allows nulls
IXFCDEF	001-BYTE	CHARACTER	column has defaults
IXFCSLCT	001-BYTE	CHARACTER	column selected flag
IXFCKPOS	002-BYTE	CHARACTER	position in primary key
IXFCCLAS	001-BYTE	CHARACTER	data class
IXFCTYPE	003-BYTE	CHARACTER	data type
IXFCSBCP	005-BYTE	CHARACTER	single byte code page
IXFCDBCP	005-BYTE	CHARACTER	double byte code page

IXFCLENG	005-BYTE	CHARACTER	column data length
IXFCDRID	003-BYTE	CHARACTER	'D' record identifier
IXFCPOSN	006-BYTE	CHARACTER	column position
IXFCDESC	030-BYTE	CHARACTER	column description
IXFCLOBL	020-BYTE	CHARACTER	lob column length
IXFCUDTL	003-BYTE	CHARACTER	UDT name length
IXFCUDTN	256-BYTE	CHARACTER	UDT name
IXFCDEFL	003-BYTE	CHARACTER	default value length
IXFCDEFV	254-BYTE	CHARACTER	default value
IXFCDLPR	010-BYTE	CHARACTER	datalink properties
IXFCREF	001-BYTE	CHARACTER	reference type
IXFCDIM	002-BYTE	CHARACTER	number of dimensions
IXFCDSIZ	varying	CHARACTER	size of each dimension

The following fields are contained in column descriptor records:

#### **IXFCRECL**

The record length indicator. A 6-byte character representation of an integer value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. The C record must be sufficiently long to include all of its defined fields.

#### **IXFCRECT**

The IXF record type, which is set to C for this record.

#### **IXFCNAML**

The length, in bytes, of the column name in the IXFCNAME field.

#### **IXFCNAME**

The name of the column.

#### **IXFCNULL**

Specifies if nulls are permitted in this column. Valid settings are Y or N.

#### **IXFCDEF**

Specifies if a default value is defined for this field. Valid settings are Y or N.

#### **IXFCSLCT**

An obsolete field whose intended purpose was to allow selection of a subset of columns in the data. Programs writing PC/IXF files should always store a Y in this field. Programs reading PC/IXF files should ignore the field.

#### **IXFCKPOS**

The position of the column as part of the primary key. Valid values range from 01 to 16, or N if the column is not part of the primary key.

#### **IXFCCLAS**

The class of data types to be used in the IXFCTYPE field. The database manager only supports relational types (R).

#### **IXFCTYPE**

The data type for the column.

#### **IXFCSBCP**

Contains a single-byte character representation of a SBCS CPGID. This field specifies the CPGID for single-byte character data, which occurs with the IXFDCOLS field of the D records for this column.

The semantics of this field vary with the data type for the column (specified in the IXFCTYPE field).

- For a character string column, this field should normally contain a non-zero value equal to that of the IXFHSBCP field in the H record;

however, other values are permitted. If this value is zero, the column is interpreted to contain bit string data.

- For a numeric column, this field is not meaningful. It is set to zero by the export utility, and ignored by the import utility.
- For a date or time column, this field is not meaningful. It is set to the value of the IXFHSBCP field by the export utility, and ignored by the import utility.
- For a graphic column, this field must be zero.

#### **IXFCDBCP**

Contains a single-byte character representation of a DBCS CPGID. This field specifies the CPGID for double-byte character data, which occurs with the IXFDCOLS field of the D records for this column.

The semantics of this field vary with the data type for the column (specified in the IXFCTYPE field).

- For a character string column, this field should either be zero, or contain a value equal to that of the IXFHDBCP field in the H record; however, other values are permitted. If the value in the IXFCSBCP field is zero, the value in this field must be zero.
- For a numeric column, this field is not meaningful. It is set to zero by the export utility, and ignored by the import utility.
- For a date or time column, this field is not meaningful. It is set to zero by the export utility, and ignored by the import utility.
- For a graphic column, this field must have a value equal to the value of the IXFHDBCP field.

#### **IXFCLENG**

Provides information about the size of the column being described. For some data types, this field is unused, and should contain blanks. For other data types, this field contains the right-justified character representation of an integer specifying the column length. For yet other data types, this field is divided into two subfields: 3 bytes for precision, and 2 bytes for scale; both of these subfields are right-justified character representations of integers.

#### **IXFCDRID**

The D record identifier. This field contains the right-justified character representation of an integer value. Several D records can be used to contain each row of data in the PC/IXF file. This field specifies which D record (of the several D records contributing to a row of data) contains the data for the column. A value of one (for example, 001) indicates that the data for a column is in the first D record in a row of data. The first C record must have an IXFCDRID value of one. All subsequent C records must have an IXFCDRID value equal to the value in the preceding C record, or one higher.

#### **IXFCPOSN**

The value in this field is used to locate the data for the column within one of the D records representing a row of table data. It is the starting position of the data for this column within the IXFDCOLS field of the D record. If the column is nullable, IXFCPOSN points to the null indicator; otherwise, it points to the data itself. If a column contains varying length data, the data itself begins with the current length indicator. The IXFCPOSN value for the first byte in the IXFDCOLS field of the D record is one (not zero). If a column is in a new D record, the value of IXFCPOSN should be one;

otherwise, IXFCPOSN values should increase from column to column to such a degree that the data values do not overlap.

**IXFCDESC**

Descriptive information about the column. This is an informational field only. If a program writing to a file has no data to write to this field, the preferred fill value is blanks. Programs reading a file might print or display this field, or store it in an informational field, but no computations should depend on the content of this field.

**IXFCLOBL**

The length, in bytes, of the long or the LOB defined in this column. If this column is not a long or a LOB, the value in this field is 000.

**IXFCUDTL**

The length, in bytes, of the user defined type (UDT) name in the IXFCUDTN field. If the type of this column is not a UDT, the value in this field is 000.

**IXFCUDTN**

The name of the user defined type that is used as the data type for this column.

**IXFCDEFL**

The length, in bytes, of the default value in the IXFCDEFV field. If this column does not have a default value, the value in this field is 000.

**IXFCDEFV**

Specifies the default value for this column, if one has been defined.

**IXFCDLPR**

If the column is a DATALINK column, this field describes the following properties:

- The first character represents the link type, and has a value of U.
- The second character represents the link control type. Valid values are N for no control, and F for file control.
- The third character represents the level of integrity, and has a value of A (for database manager controlling all DATALINK values).
- The fourth character represents read permission. Valid values are D for database determined permissions, and F for file system determined permissions.
- The fifth character represents write permission. Valid values are B for blocked access, and F for file system determined permissions.
- The sixth character represents recovery options. Valid values are Y (DB2 will support point-in-time recovery of files referenced in this column), and N (no support).
- The seventh character represents the action that is to be taken when the data file is unlinked. Valid values are R for restore, and D for delete the file.

**IXFCREF**

If the column is part of a hierarchy, this field specifies whether the column is a data column (D), or a reference column (R).

**IXFCNDIM**

The number of dimensions in the column. Arrays are not supported in this version of PC/IXF. This field must therefore contain a character representation of a zero integer value.

## IXFCDSIZ

The size or range of each dimension. The length of this field is five bytes per dimension. Since arrays are not supported (that is, the number of dimensions must be zero), this field has zero length, and does not actually exist.

### DATA RECORD

FIELD NAME	LENGTH	TYPE	COMMENTS
IXFDRECL	06-BYTE	CHARACTER	record length
IXFDRECT	01-BYTE	CHARACTER	record type = 'D'
IXFDRID	03-BYTE	CHARACTER	'D' record identifier
IXDFIL1	04-BYTE	CHARACTER	reserved
IXFDCOLS	varying	variable	columnar data

The following fields are contained in the data records:

## IXFDRECL

The record length indicator. A 6-byte character representation of an integer value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. Each D record must be sufficiently long to include all significant data for the current occurrence of the last data column stored in the record.

## IXFDRECT

The IXF record type, which is set to D for this record, indicating that it contains data values for the table.

## IXFDRID

The record identifier, which identifies a particular D record within the sequence of several D records contributing to a row of data. For the first D record in a row of data, this field has a value of one; for the second D record in a row of data, this field has a value of two, and so on. In each row of data, all the D record identifiers called out in the C records must actually exist.

## IXDFIL1

Spare field set to four blanks to match reserved fields, and hold a place for a possible shift-out character, in host IXF files.

## IXFDCOLS

The area for columnar data. The data area of a data record (D record) is composed of one or more column entries. There is one column entry for each column descriptor record, which has the same D record identifier as the D record. In the D record, the starting position of the column entries is indicated by the IXFCPOSN value in the C records.

The format of the column entry data depends on whether or not the column is nullable:

- If the column is nullable (the IXFCNULL field is set to Y), the column entry data includes a null indicator. If the column is not null, the indicator is followed by data type-specific information, including the actual database value. The null indicator is a two-byte value set to x'0000' for not null, and x'FFFF' for null.
- If the column is not nullable, the column entry data includes only data type-specific information, including the actual database value.

For varying-length data types, the data type-specific information includes a current length indicator. The current length indicators are 2-byte integers in a form specified by the IXFTMFRM field.

The length of the data area of a D record cannot exceed 32 771 bytes.

APPLICATION RECORD

FIELD NAME	LENGTH	TYPE	COMMENTS
-----	-----	-----	-----
IXFARECL	06-BYTE	CHARACTER	record length
IXFARECT	01-BYTE	CHARACTER	record type = 'A'
IXFAPPID	12-BYTE	CHARACTER	application identifier
IXFADATA	varying	variable	application-specific data

The following fields are contained in application records:

**IXFARECL**

The record length indicator. A 6-byte character representation of an integer value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. Each A record must be sufficiently long to include at least the entire IXFAPPID field.

**IXFARECT**

The IXF record type, which is set to A for this record, indicating that this is an application record. These records are ignored by programs which do not have particular knowledge about the content and the format of the data implied by the application identifier.

**IXFAPPID**

The application identifier, which identifies the application creating the A record. PC/IXF files created by the database manager can have A records with the first 6 characters of this field set to a constant identifying the database manager, and the last 6 characters identifying the release or version of the database manager or another application writing the A record.

**IXFADATA**

This field contains application dependent supplemental data, whose form and content are known only to the program creating the A record, and to other applications which are likely to process the A record.

DB2 INDEX RECORD

FIELD NAME	LENGTH	TYPE	COMMENTS
-----	-----	-----	-----
IXFARECL	006-BYTE	CHARACTER	record length
IXFARECT	001-BYTE	CHARACTER	record type = 'A'
IXFAPPID	012-BYTE	CHARACTER	application identifier = 'DB2 02.00'
IXFAITYP	001-BYTE	CHARACTER	application specific data type = 'I'
IXFADATE	008-BYTE	CHARACTER	date written from the 'H' record
IXFATIME	006-BYTE	CHARACTER	time written from the 'H' record
IXFANDXL	002-BYTE	SHORT INT	length of name of the index
IXFANDXN	256-BYTE	CHARACTER	name of the index
IXFANCL	002-BYTE	SHORT INT	length of name of the index creator
IXFANCN	256-BYTE	CHARACTER	name of the index creator
IXFATABL	002-BYTE	SHORT INT	length of name of the table
IXFATABN	256-BYTE	CHARACTER	name of the table
IXFATCL	002-BYTE	SHORT INT	length of name of the table creator
IXFATCN	256-BYTE	CHARACTER	name of the table creator
IXFAUNIQ	001-BYTE	CHARACTER	unique rule
IXFACCNT	002-BYTE	CHARACTER	column count
IXFAREVS	001-BYTE	CHARACTER	allow reverse scan flag
IXFAPCTF	002-BYTE	CHARACTER	amount of pct free
IXFAPCTU	002-BYTE	CHARACTER	amount of minpctused

IXFAEXTI	001-BYTE	CHARACTER	reserved
IXFACNML	002-BYTE	SHORT INT	length of name of the columns
IXFACOLN	varying	CHARACTER	name of the columns in the index

One record of this type is specified for each user defined index. This record is located after all of the C records for the table. The following fields are contained in DB2 index records:

**IXFARECL**

The record length indicator. A 6-byte character representation of an integer value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. Each A record must be sufficiently long to include at least the entire IXFAPPID field.

**IXFARECT**

The IXF record type, which is set to A for this record, indicating that this is an application record. These records are ignored by programs which do not have particular knowledge about the content and the format of the data implied by the application identifier.

**IXFAPPID**

The application identifier, which identifies DB2 as the application creating this A record.

**IXFAITYP**

Specifies that this is subtype "I" of DB2 application records.

**IXFADATE**

The date on which the file was written, in the form *yyyymmdd*. This field must have the same value as IXFHDATE.

**IXFATIME**

The time at which the file was written, in the form *hhmmss*. This field must have the same value as IXFHTIME.

**IXFANDXL**

The length, in bytes, of the index name in the IXFANDXN field.

**IXFANDXN**

The name of the index.

**IXFANCL**

The length, in bytes, of the index creator name in the IXFANCN field.

**IXFANCN**

The name of the index creator.

**IXFATABL**

The length, in bytes, of the table name in the IXFATABN field.

**IXFATABN**

The name of the table.

**IXFATCL**

The length, in bytes, of the table creator name in the IXFATCN field.

**IXFATCN**

The name of the table creator.

**IXFAUNIQ**

Specifies the type of index. Valid values are P for a primary key, U for a unique index, and D for a non unique index.

**IXFACCNT**

Specifies the number of columns in the index definition.

**IXFAREVS**

Specifies whether reverse scan is allowed on this index. Valid values are Y for reverse scan, and N for no reverse scan.

**IXFAPCTF**

Specifies the percentage of index pages to leave as free. Valid values range from -1 to 99. If a value of -1 or zero is specified, the system default value is used.

**IXFAPCTU**

Specifies the minimum percentage of index pages that must be free before two index pages can be merged. Valid values range from 00 to 99.

**IXFAEXTI**

Reserved for future use.

**IXFACNML**

The length, in bytes, of the column names in the IXFACOLN field.

**IXFACOLN**

The names of the columns that are part of this index. Valid values are in the form *+name-name...*, where + specifies an ascending sort on the column, and - specifies a descending sort on the column.

**DB2 HIERARCHY RECORD**

FIELD NAME	LENGTH	TYPE	COMMENTS
IXFARECL	006-BYTE	CHARACTER	record length
IXFARECT	001-BYTE	CHARACTER	record type = 'A'
IXFAPPID	012-BYTE	CHARACTER	application identifier = 'DB2 02.00'
IXFAXTYP	001-BYTE	CHARACTER	application specific data type = 'X'
IXFADATE	008-BYTE	CHARACTER	date written from the 'H' record
IXFATIME	006-BYTE	CHARACTER	time written from the 'H' record
IXFAYCNT	010-BYTE	CHARACTER	'Y' record count for this hierarchy
IXFAYSTR	010-BYTE	CHARACTER	starting column of this hierarchy

One record of this type is used to describe a hierarchy. All subtable records (see below) must be located immediately after the hierarchy record, and hierarchy records are located after all of the C records for the table. The following fields are contained in DB2 hierarchy records:

**IXFARECL**

The record length indicator. A 6-byte character representation of an integer value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. Each A record must be sufficiently long to include at least the entire IXFAPPID field.

**IXFARECT**

The IXF record type, which is set to A for this record, indicating that this is an application record. These records are ignored by programs which do not have particular knowledge about the content and the format of the data implied by the application identifier.

**IXFAPPID**

The application identifier, which identifies DB2 as the application creating this A record.

**IXFAXTYP**

Specifies that this is subtype "X" of DB2 application records.

**IXFADATE**

The date on which the file was written, in the form *yyyymmdd*. This field must have the same value as IXFHDATE.

**IXFATIME**

The time at which the file was written, in the form *hhmmss*. This field must have the same value as IXFHTIME.

**IXFAYCNT**

Specifies the number of subtable records that are expected after this hierarchy record.

**IXFAYSTR**

Specifies the index of the subtable records at the beginning of the exported data. If export of a hierarchy was started from a non-root subtable, all parent tables of this subtable are exported. The position of this subtable inside of the IXF file is also stored in this field. The first X record represents the column with an index of zero.

**DB2 SUBTABLE RECORD**

FIELD NAME	LENGTH	TYPE	COMMENTS
-----	-----	-----	-----
IXFARECL	006-BYTE	CHARACTER	record length
IXFARECT	001-BYTE	CHARACTER	record type = 'A'
IXFAPPID	012-BYTE	CHARACTER	application identifier = 'DB2 02.00'
IXFAYTYP	001-BYTE	CHARACTER	application specific data type = 'Y'
IXFADATE	008-BYTE	CHARACTER	date written from the 'H' record
IXFATIME	006-BYTE	CHARACTER	time written from the 'H' record
IXFASCHL	003-BYTE	CHARACTER	type schema name length
IXFASCHN	256-BYTE	CHARACTER	type schema name
IXFATYPL	003-BYTE	CHARACTER	type name length
IXFATYPN	256-BYTE	CHARACTER	type name
IXFATABL	003-BYTE	CHARACTER	table name length
IXFATABN	256-BYTE	CHARACTER	table name
IXFAPNDX	010-BYTE	CHARACTER	subtable index of parent table
IXFASNDX	005-BYTE	CHARACTER	starting column index of current table
IXFAENDX	005-BYTE	CHARACTER	ending column index of current table

One record of this type is used to describe a subtable as part of a hierarchy. All subtable records belonging to a hierarchy must be stored together, and immediately after the corresponding hierarchy record. A subtable is composed of one or more columns, and each column is described in a column record. Each column in a subtable must be described in a consecutive set of C records. The following fields are contained in DB2 subtable records:

**IXFARECL**

The record length indicator. A 6-byte character representation of an integer value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. Each A record must be sufficiently long to include at least the entire IXFAPPID field.

**IXFARECT**

The IXF record type, which is set to A for this record, indicating that this is

an application record. These records are ignored by programs which do not have particular knowledge about the content and the format of the data implied by the application identifier.

**IXFAPPID**

The application identifier, which identifies DB2 as the application creating this A record.

**IXFAYTYP**

Specifies that this is subtype "Y" of DB2 application records.

**IXFADATE**

The date on which the file was written, in the form *yyyymmdd*. This field must have the same value as IXFHDATE.

**IXFATIME**

The time at which the file was written, in the form *hhmmss*. This field must have the same value as IXFHTIME.

**IXFASCHL**

The length, in bytes, of the subtable schema name in the IXFASCHN field.

**IXFASCHN**

The name of the subtable schema.

**IXFATYPL**

The length, in bytes, of the subtable name in the IXFATYPN field.

**IXFATYPN**

The name of the subtable.

**IXFATABL**

The length, in bytes, of the table name in the IXFATABN field.

**IXFATABN**

The name of the table.

**IXFAPNDX**

Subtable record index of the parent subtable. If this subtable is the root of a hierarchy, this field contains the value -1.

**IXFASNDX**

Starting index of the column records that made up this subtable.

**IXFAENDX**

Ending index of the column records that made up this subtable.

**DB2 CONTINUATION RECORD**

FIELD NAME	LENGTH	TYPE	COMMENTS
IXFARECL	006-BYTE	CHARACTER	record length
IXFARECT	001-BYTE	CHARACTER	record type = 'A'
IXFAPPID	012-BYTE	CHARACTER	application identifier = 'DB2 02.00'
IXFACTYP	001-BYTE	CHARACTER	application specific data type = 'C'
IXFADATE	008-BYTE	CHARACTER	date written from the 'H' record
IXFATIME	006-BYTE	CHARACTER	time written from the 'H' record
IXFALAST	002-BYTE	SHORT INT	last diskette volume number
IXFATHIS	002-BYTE	SHORT INT	this diskette volume number
IXFANEXT	002-BYTE	SHORT INT	next diskette volume number

This record is found at the end of each file that is part of a multi-volume IXF file, unless that file is the final volume; it can also be found at the beginning of each

file that is part of a multi-volume IXF file, unless that file is the first volume. The purpose of this record is to keep track of file order. The following fields are contained in DB2 continuation records:

**IXFARECL**

The record length indicator. A 6-byte character representation of an integer value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. Each A record must be sufficiently long to include at least the entire IXFAPPID field.

**IXFARECT**

The IXF record type, which is set to A for this record, indicating that this is an application record. These records are ignored by programs which do not have particular knowledge about the content and the format of the data implied by the application identifier.

**IXFAPPID**

The application identifier, which identifies DB2 as the application creating this A record.

**IXFACTYP**

Specifies that this is subtype "C" of DB2 application records.

**IXFADATE**

The date on which the file was written, in the form *yyyymmdd*. This field must have the same value as IXFHDATE.

**IXFATIME**

The time at which the file was written, in the form *hhmmss*. This field must have the same value as IXFHTIME.

**IXFALAST**

This field is a binary field, in little-endian format. The value should be one less than the value in IXFATHIS.

**IXFATHIS**

This field is a binary field, in little-endian format. The value in this field on consecutive volumes should also be consecutive. The first volume has a value of 1.

**IXFANEXT**

This field is a binary field, in little-endian format. The value should be one more than the value in IXFATHIS, unless the record is at the beginning of the file, in which case the value should be zero.

**DB2 TERMINATE RECORD**

FIELD NAME	LENGTH	TYPE	COMMENTS
IXFARECL	006-BYTE	CHARACTER	record length
IXFARECT	001-BYTE	CHARACTER	record type = 'A'
IXFAPPID	012-BYTE	CHARACTER	application identifier = 'DB2 02.00'
IXFAETYP	001-BYTE	CHARACTER	application specific data type = 'E'
IXFADATE	008-BYTE	CHARACTER	date written from the 'H' record
IXFATIME	006-BYTE	CHARACTER	time written from the 'H' record

This record is the end-of-file marker found at the end of an IXF file. The following fields are contained in DB2 terminate records:

**IXFARECL**

The record length indicator. A 6-byte character representation of an integer

value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. Each A record must be sufficiently long to include at least the entire IXFAPPID field.

**IXFARECT**

The IXF record type, which is set to A for this record, indicating that this is an application record. These records are ignored by programs which do not have particular knowledge about the content and the format of the data implied by the application identifier.

**IXFAPPID**

The application identifier, which identifies DB2 as the application creating this A record.

**IXFAETYP**

Specifies that this is subtype "E" of DB2 application records.

**IXFADATE**

The date on which the file was written, in the form *yyyymmdd*. This field must have the same value as IXFHDATE.

**IXFATIME**

The time at which the file was written, in the form *hhmmss*. This field must have the same value as IXFHTIME.

DB2 IDENTITY RECORD

FIELD NAME	LENGTH	TYPE	COMMENTS
IXFARECL	06-BYTE	CHARACTER	record length
IXFARECT	01-BYTE	CHARACTER	record type = 'A'
IXFAPPID	12-BYTE	CHARACTER	application identifier
IXFATYPE	01-BYTE	CHARACTER	application specific record type = 'S'
IXFADATE	08-BYTE	CHARACTER	application record creation date
IXFATIME	06-BYTE	CHARACTER	application record creation time
IXFACOLN	06-BYTE	CHARACTER	column number of the identity column
IXFAITYP	01-BYTE	CHARACTER	generated always ('Y' or 'N')
IXFASTRT	33-BYTE	CHARACTER	identity START AT value
IXFAINCR	33-BYTE	CHARACTER	identity INCREMENT BY value
IXFACACH	10-BYTE	CHARACTER	identity CACHE value
IXFAMINV	33-BYTE	CHARACTER	identity MINVALUE
IXFAMAXV	33-BYTE	CHARACTER	identity MAXVALUE
IXFACYCL	01-BYTE	CHARACTER	identity CYCLE ('Y' or 'N')
IXFAORDR	01-BYTE	CHARACTER	identity ORDER ('Y' or 'N')
IXFARMRL	03-BYTE	CHARACTER	identity Remark length
IXFARMRK	254-BYTE	CHARACTER	identity Remark value

The following fields are contained in DB2 identity records:

**IXFARECL**

The record length indicator. A 6-byte character representation of an integer value specifying the length, in bytes, of the portion of the PC/IXF record that follows the record length indicator; that is, the total record size minus 6 bytes. Each A record must be sufficiently long to include at least the entire IXFAPPID field.

**IXFARECT**

The IXF record type, which is set to A for this record, indicating that this is an application record. These records are ignored by programs which do not have particular knowledge about the content and the format of the data implied by the application identifier.

| **IXFAPPID**

|       The application identifier, which identifies DB2 as the application creating  
|       this A record.

| **IXFATYPE**

|       Application specific record type. This field should always have a value of  
|       "S".

| **IXFADATE**

|       The date on which the file was written, in the form *yyyymmdd*. This field  
|       must have the same value as IXFHDATE.

| **IXFATIME**

|       The time at which the file was written, in the form *hhmmss*. This field must  
|       have the same value as IXFHTIME.

| **IXFACOLN**

|       Column number of the identity column in the table.

| **IXFAITYP**

|       The type of the identity column. A value of "Y" indicates that the identity  
|       column is always GENERATED. All other values are interpreted to mean  
|       that the column is of type GENERATED BY DEFAULT.

| **IXFASTRT**

|       The START AT value for the identity column that was supplied to the  
|       CREATE TABLE statement at the time of table creation.

| **IXFAINCR**

|       The INCREMENT BY value for the identity column that was supplied to  
|       the CREATE TABLE statement at the time of table creation.

| **IXFACACH**

|       The CACHE value for the identity column that was supplied to the  
|       CREATE TABLE statement at the time of table creation. A value of "1"  
|       corresponds to the NO CACHE option.

| **IXFAMINV**

|       The MINVALUE for the identity column that was supplied to the CREATE  
|       TABLE statement at the time of table creation.

| **IXFAMAXV**

|       The MAXVALUE for the identity column that was supplied to the CREATE  
|       TABLE statement at the time of table creation.

| **IXFACYCL**

|       The CYCLE value for the identity column that was supplied to the  
|       CREATE TABLE statement at the time of table creation. A value of "Y"  
|       corresponds to the CYCLE option, any other value corresponds to NO  
|       CYCLE.

| **IXFAORDR**

|       The ORDER value for the identity column that was supplied to the  
|       CREATE TABLE statement at the time of table creation. A value of "Y"  
|       corresponds to the ORDER option, any other value corresponds to NO  
|       ORDER.

| **IXFARMRL**

|       The length, in bytes, of the remark in IXFARMRK field.

## IXFARMRK

This is the user-entered remark associated with the identity column. This is an informational field only. The database manager does not use this field when importing data.

### Related reference:

- “PC/IXF Data Types” on page 270
- “PC/IXF Data Type Descriptions” on page 275

## PC/IXF Data Types

Table 18. PC/IXF Data Types

Name	IXFCTYPE Value	Description
BIGINT	492	An 8-byte integer in the form specified by IXFTMFRM. It represents a whole number between -9 223 372 036 854 775 808 and 9 223 372 036 854 775 807. IXFCSBCP and IXFCDBCP are not significant, and should be zero. IXFCLENG is not used, and should contain blanks.
BLOB, CLOB	404, 408	<p>A variable-length character string. The maximum length of the string is contained in the IXFCLENG field of the column descriptor record, and cannot exceed 32 767 bytes. The string itself is preceded by a current length indicator, which is a 4-byte integer specifying the length of the string, in bytes. The string is in the code page indicated by IXFCSBCP.</p> <p>The following applies to BLOBs only: If IXFCSBCP is zero, the string is bit data, and should not be translated by any transformation program.</p> <p>The following applies to CLOBs only: If IXFCDBCP is non-zero, the string can also contain double-byte characters in the code page indicated by IXFCDBCP.</p>
BLOB_LOCATION_SPECIFIER, BLOB_LOCATION_SPECIFIER, and DBCLOB_LOCATION_SPECIFIER	960, 964, 968	<p>A fixed-length field, which cannot exceed 255 bytes. The LOB Location Specifier (LLS) is located in the code page indicated by IXFCSBCP. If IXFCSBCP is zero, the LLS is bit data and should not be translated by any transformation program. If IXFCDBCP is non-zero, the string can also contain double-byte characters in the code page indicated by IXFCDBCP.</p> <p>Since the length of the LLS is stored in IXFCLENG, the actual length of the original LOB is lost. PC/IXF files with columns of this type should not be used to recreate the LOB field since the LOB will be created with the length of the LLS.</p>

Table 18. PC/IXF Data Types (continued)

Name	IXFCTYPE Value	Description
BLOB_FILE, CLOB_FILE, DBCLOB_FILE	916, 920, 924	<p>A fixed-length field containing an SQLFILE structure with the <i>name_length</i> and the <i>name</i> fields filled in. The length of the structure is contained in the IXFCLENG field of the column descriptor record, and cannot exceed 255 bytes. The file name is in the code page indicated by IXFCSBCP. If IXFCDBCP is non-zero, the file name can also contain double-byte characters in the code page indicated by IXFCDBCP. If IXFCSBCP is zero, the file name is bit data and should not be translated by any transformation program.</p> <p>Since the length of the structure is stored in IXFCLENG, the actual length of the original LOB is lost. IXF files with columns of type BLOB_FILE, CLOB_FILE, or DBCLOB_FILE should not be used to recreate the LOB field, since the LOB will be created with a length of <i>sql_lobfile_len</i>.</p>
CHAR	452	<p>A fixed-length character string. The string length is contained in the IXFCLENG field of the column descriptor record, and cannot exceed 254 bytes. The string is in the code page indicated by IXFCSBCP. If IXFCDBCP is non-zero, the string can also contain double-byte characters in the code page indicated by IXFCDBCP. If IXFCSBCP is zero, the string is bit data and should not be translated by any transformation program.</p>
DATE	384	<p>A point in time in accordance with the Gregorian calendar. Each date is a 10-byte character string in International Standards Organization (ISO) format: <i>yyyy-mm-dd</i>. The range of the year part is 0001 to 9999. The range of the month part is 01 to 12. The range of the day part is 01 to <i>n</i>, where <i>n</i> depends on the month, using the usual rules for days of the month and leap year. Leading zeros cannot be omitted from any part. IXFCLENG is not used, and should contain blanks. Valid characters within DATE are invariant in all PC ASCII code pages; therefore, IXFCSBCP and IXFCDBCP are not significant, and should be zero.</p>

Table 18. PC/IXF Data Types (continued)

Name	IXFCTYPE Value	Description
DBCLOB	412	A variable-length string of double-byte characters. The IXFLENG field in the column descriptor record specifies the maximum number of double-byte characters in the string, and cannot exceed 16 383. The string itself is preceded by a current length indicator, which is a 4-byte integer specifying the length of the string in double-byte characters (that is, the value of this integer is one half the length of the string, in bytes). The string is in the DBCS code page, as specified by IXFCDBCP in the C record. Since the string consists of double-byte character data only, IXFCSBCP should be zero. There are no surrounding shift-in or shift-out characters.
DECIMAL	484	A packed decimal number with precision P (as specified by the first three bytes of IXFLENG in the column descriptor record) and scale S (as specified by the last two bytes of IXFLENG). The length, in bytes, of a packed decimal number is $(P+2)/2$ . The precision must be an odd number between 1 and 31, inclusive. The packed decimal number is in the internal format specified by IXFTMFRM, where packed decimal for the PC is defined to be the same as packed decimal for the System/370. IXFCSBCP and IXFCDBCP are not significant, and should be zero.
FLOATING POINT	480	Either a long (8-byte) or short (4-byte) floating point number, depending on whether IXFLENG is set to eight or to four. The data is in the internal machine form, as specified by IXFTMFRM. IXFCSBCP and IXFCDBCP are not significant, and should be zero. Four-byte floating point is not supported by the database manager.
GRAPHIC	468	A fixed-length string of double-byte characters. The IXFLENG field in the column descriptor record specifies the number of double-byte characters in the string, and cannot exceed 127. The actual length of the string is twice the value of the IXFLENG field, in bytes. The string is in the DBCS code page, as specified by IXFCDBCP in the C record. Since the string consists of double-byte character data only, IXFCSBCP should be zero. There are no surrounding shift-in or shift-out characters.

Table 18. PC/IXF Data Types (continued)

Name	IXFCTYPE Value	Description
INTEGER	496	A 4-byte integer in the form specified by IXFTMFRM. It represents a whole number between -2 147 483 648 and +2 147 483 647. IXFCSBCP and IXFCDBCP are not significant, and should be zero. IXFCLENG is not used, and should contain blanks.
LONGVARCHAR	456	A variable-length character string. The maximum length of the string is contained in the IXFCLENG field of the column descriptor record, and cannot exceed 32 767 bytes. The string itself is preceded by a current length indicator, which is a 2-byte integer specifying the length of the string, in bytes. The string is in the code page indicated by IXFCSBCP. If IXFCDBCP is non-zero, the string can also contain double-byte characters in the code page indicated by IXFCDBCP. If IXFCSBCP is zero, the string is bit data and should not be translated by any transformation program.
LONG VARGRAPHIC	472	A variable-length string of double-byte characters. The IXFCLENG field in the column descriptor record specifies the maximum number of double-byte characters for the string, and cannot exceed 16 383. The string itself is preceded by a current length indicator, which is a 2-byte integer specifying the length of the string in double-byte characters (that is, the value of this integer is one half the length of the string, in bytes). The string is in the DBCS code page, as specified by IXFCDBCP in the C record. Since the string consists of double-byte character data only, IXFCSBCP should be zero. There are no surrounding shift-in or shift-out characters.
SMALLINT	500	A 2-byte integer in the form specified by IXFTMFRM. It represents a whole number between -32 768 and +32 767. IXFCSBCP and IXFCDBCP are not significant, and should be zero. IXFCLENG is not used, and should contain blanks.

Table 18. PC/IXF Data Types (continued)

Name	IXFCTYPE Value	Description
TIME	388	<p>A point in time in accordance with the 24-hour clock. Each time is an 8-byte character string in ISO format: <i>hh.mm.ss</i>. The range of the hour part is 00 to 24, and the range of the other parts is 00 to 59. If the hour is 24, the other parts are 00. The smallest time is 00.00.00, and the largest is 24.00.00. Leading zeros cannot be omitted from any part. IXFLENG is not used, and should contain blanks. Valid characters within TIME are invariant in all PC ASCII code pages; therefore, IXFCSBCP and IXFCDBCP are not significant, and should be zero.</p>
TIMESTAMP	392	<p>The date and time with microsecond precision. Each time stamp is a character string of the form <i>yyyy-mm-dd-hh.mm.ss.nnnnnn</i> (year month day hour minutes seconds microseconds). IXFLENG is not used, and should contain blanks. Valid characters within TIMESTAMP are invariant in all PC ASCII code pages; therefore, IXFCSBCP and IXFCDBCP are not significant, and should be zero.</p>
VARCHAR	448	<p>A variable-length character string. The maximum length of the string, in bytes, is contained in the IXFLENG field of the column descriptor record, and cannot exceed 254 bytes. The string itself is preceded by a current length indicator, which is a two-byte integer specifying the length of the string, in bytes. The string is in the code page indicated by IXFCSBCP. If IXFCDBCP is non-zero, the string can also contain double-byte characters in the code page indicated by IXFCDBCP. If IXFCSBCP is zero, the string is bit data and should not be translated by any transformation program.</p>
VARGRAPHIC	464	<p>A variable-length string of double-byte characters. The IXFLENG field in the column descriptor record specifies the maximum number of double-byte characters in the string, and cannot exceed 127. The string itself is preceded by a current length indicator, which is a 2-byte integer specifying the length of the string in double-byte characters (that is, the value of this integer is one half the length of the string, in bytes). The string is in the DBCS code page, as specified by IXFCDBCP in the C record. Since the string consists of double-byte character data only, IXFCSBCP should be zero. There are no surrounding shift-in or shift-out characters.</p>

Not all combinations of IXFCSBCP and IXFCDBCP values for PC/IXF character or graphic columns are valid. A PC/IXF character or graphic column with an invalid (IXFCSBCP,IXFCDBCP) combination is an invalid data type.

Table 19. Valid PC/IXF Data Types

PC/IXF Data Type	Valid (IXFCSBCP,IXFCDBCP) Pairs	Invalid (IXFCSBCP,IXFCDBCP) Pairs
CHAR, VARCHAR, or LONG VARCHAR	(0,0), (x,0), or (x,y)	(0,y)
BLOB	(0,0)	(x,0), (0,y), or (x,y)
CLOB	(x,0), (x,y)	(0,0), (0,y)
GRAPHIC, VARGRAPHIC, LONG VARGRAPHIC, or DBCLOB	(0,y)	(0,0), (x,0), or (x,y)
<b>Note:</b> x and y are not 0.		

**Related reference:**

- “PC/IXF Record Types” on page 254
- “FORCEIN Option” on page 283
- “PC/IXF Data Type Descriptions” on page 275

## PC/IXF Data Type Descriptions

Table 20. Acceptable Data Type Forms for the PC/IXF File Format

Data Type	Form in Files Created by the Export Utility	Form Acceptable to the Import Utility
BIGINT	A BIGINT column, identical to the database column, is created.	A column in any numeric type (SMALLINT, INTEGER, BIGINT, DECIMAL, or FLOAT) is accepted. Individual values are rejected if they are not in the range -9 223 372 036 854 775 808 to 9 223 372 036 854 775 807.
BLOB	A PC/IXF BLOB column is created. The maximum length of the database column, the SBCS CPGID value, and the DBCS CPGID value are copied to the column descriptor record.	A PC/IXF CHAR, VARCHAR, LONG VARCHAR, BLOB, BLOB_FILE, or BLOB_LOCATION_SPECIFIER column is acceptable if: <ul style="list-style-type: none"> <li>• The database column is marked FOR BIT DATA</li> <li>• The PC/IXF column single-byte code page value equals the SBCS CPGID of the database column, and the PC/IXF column double-byte code page value equals zero, or the DBCS CPGID of the database column. A PC/IXF GRAPHIC, VARGRAPHIC, or LONG VARGRAPHIC BLOB column is also acceptable. If the PC/IXF column is of fixed length, its length must be compatible with the maximum length of the database column.</li> </ul>

Table 20. Acceptable Data Type Forms for the PC/IXF File Format (continued)

Data Type	Form in Files Created by the Export Utility	Form Acceptable to the Import Utility
CHAR	A PC/IXF CHAR column is created. The database column length, the SBCS CPGID value, and the DBCS CPGID value are copied to the PC/IXF column descriptor record.	<p>A PC/IXF CHAR, VARCHAR, or LONG VARCHAR column is acceptable if:</p> <ul style="list-style-type: none"> <li>• The database column is marked FOR BIT DATA</li> <li>• The PC/IXF column single-byte code page value equals the SBCS CPGID of the database column, and the PC/IXF column double-byte code page value equals zero, or the DBCS CPGID of the database column.</li> </ul> <p>A PC/IXF GRAPHIC, VARGRAPHIC, or LONG VARGRAPHIC column is also acceptable if the database column is marked FOR BIT DATA. In any case, if the PC/IXF column is of fixed length, its length must be compatible with the length of the database column. The data is padded on the right with single-byte spaces (x'20'), if necessary.</p>
CLOB	A PC/IXF CLOB column is created. The maximum length of the database column, the SBCS CPGID value, and the DBCS CPGID value are copied to the column descriptor record.	A PC/IXF CHAR, VARCHAR, LONG VARCHAR, CLOB, CLOB_FILE, or CLOB_LOCATION_SPECIFIER column is acceptable if the PC/IXF column single-byte code page value equals the SBCS CPGID of the database column, and the PC/IXF column double-byte code page value equals zero, or the DBCS CPGID of the database column. If the PC/IXF column is of fixed length, its length must be compatible with the maximum length of the database column.
DATE	A DATE column, identical to the database column, is created.	A PC/IXF column of type DATE is the usual input. The import utility also attempts to accept columns in any of the character types, except those with incompatible lengths. The character column in the PC/IXF file must contain dates in a format consistent with the territory code of the target database.
DBCLOB	A PC/IXF DBCLOB column is created. The maximum length of the database column, the SBCS CPGID value, and the DBCS CPGID value are copied to the column descriptor record.	A PC/IXF GRAPHIC, VARGRAPHIC, LONG VARGRAPHIC, DBCLOB, DBCLOB_FILE, or DBCLOB_LOCATION_SPECIFIER column is acceptable if the PC/IXF column double-byte code page value equals that of the database column. If the PC/IXF column is of fixed length, its length must be compatible with the maximum length of the database column.

Table 20. Acceptable Data Type Forms for the PC/IXF File Format (continued)

Data Type	Form in Files Created by the Export Utility	Form Acceptable to the Import Utility
DECIMAL	A DECIMAL column, identical to the database column, is created. The precision and scale of the column is stored in the column descriptor record.	A column in any numeric type (SMALLINT, INTEGER, BIGINT, DECIMAL, or FLOAT) is accepted. Individual values are rejected if they are not in the range of the DECIMAL column into which they are being imported.
FLOAT	A FLOAT column, identical to the database column, is created.	A column in any numeric type (SMALLINT, INTEGER, BIGINT, DECIMAL, or FLOAT) is accepted. All values are within range.
GRAPHIC (DBCS only)	A PC/IXF GRAPHIC column is created. The database column length, the SBCS CPGID value, and the DBCS CPGID value are copied to the column descriptor record.	A PC/IXF GRAPHIC, VARGRAPHIC, or LONG VARGRAPHIC column is acceptable if the PC/IXF column double-byte code page value equals that of the database column. If the PC/IXF column is of fixed length, its length must be compatible with the database column length. The data is padded on the right with double-byte spaces (x'8140'), if necessary.
INTEGER	An INTEGER column, identical to the database column, is created.	A column in any numeric type (SMALLINT, INTEGER, BIGINT, DECIMAL, or FLOAT) is accepted. Individual values are rejected if they are not in the range -2 147 483 648 to 2 147 483 647.
LONG VARCHAR	A PC/IXF LONG VARCHAR column is created. The maximum length of the database column, the SBCS CPGID value, and the DBCS CPGID value are copied to the column descriptor record.	<p>A PC/IXF CHAR, VARCHAR, or LONG VARCHAR column is acceptable if:</p> <ul style="list-style-type: none"> <li>• The database column is marked FOR BIT DATA</li> <li>• The PC/IXF column single-byte code page value equals the SBCS CPGID of the database column, and the PC/IXF column double-byte code page value equals zero, or the DBCS CPGID of the database column.</li> </ul> <p>A PC/IXF GRAPHIC, VARGRAPHIC, or LONG VARGRAPHIC column is also acceptable if the database column is marked FOR BIT DATA. In any case, if the PC/IXF column is of fixed length, its length must be compatible with the maximum length of the database column.</p>

Table 20. Acceptable Data Type Forms for the PC/IXF File Format (continued)

Data Type	Form in Files Created by the Export Utility	Form Acceptable to the Import Utility
LONG VARGRAPHIC (DBCS only)	A PC/IXF LONG VARGRAPHIC column is created. The maximum length of the database column, the SBCS CPGID value, and the DBCS CPGID value are copied to the column descriptor record.	A PC/IXF GRAPHIC, VARGRAPHIC, or LONG VARGRAPHIC column is acceptable if the PC/IXF column double-byte code page value equals that of the database column. If the PC/IXF column is of fixed length, its length must be compatible with the maximum length of the database column.
SMALLINT	A SMALLINT column, identical to the database column, is created.	A column in any numeric type (SMALLINT, INTEGER, BIGINT, DECIMAL, or FLOAT) is accepted. Individual values are rejected if they are not in the range -32 768 to 32 767.
TIME	A TIME column, identical to the database column, is created.	A PC/IXF column of type TIME is the usual input. The import utility also attempts to accept columns in any of the character types, except those with incompatible lengths. The character column in the PC/IXF file must contain time data in a format consistent with the territory code of the target database.
TIMESTAMP	A TIMESTAMP column, identical to the database column, is created.	A PC/IXF column of type TIMESTAMP is the usual input. The import utility also attempts to accept columns in any of the character types, except those with incompatible lengths. The character column in the PC/IXF file must contain data in the input format for time stamps.
VARCHAR	If the maximum length of the database column is $\leq 254$ , a PC/IXF VARCHAR column is created. If the maximum length of the database column is $> 254$ , a PC/IXF LONG VARCHAR column is created. The maximum length of the database column, the SBCS CPGID value, and the DBCS CPGID value are copied to the column descriptor record.	A PC/IXF CHAR, VARCHAR, or LONG VARCHAR column is acceptable if: <ul style="list-style-type: none"> <li>• The database column is marked FOR BIT DATA</li> <li>• The PC/IXF column single-byte code page value equals the SBCS CPGID of the database column, and the PC/IXF column double-byte code page value equals zero, or the DBCS CPGID of the database column.</li> </ul> A PC/IXF GRAPHIC, VARGRAPHIC, or LONG VARGRAPHIC column is also acceptable if the database column is marked FOR BIT DATA. In any case, if the PC/IXF column is of fixed length, its length must be compatible with the maximum length of the database column.

Table 20. Acceptable Data Type Forms for the PC/IXF File Format (continued)

Data Type	Form in Files Created by the Export Utility	Form Acceptable to the Import Utility
VARGRAPHIC (DBCS only)	If the maximum length of the database column is <= 127, a PC/IXF VARGRAPHIC column is created. If the maximum length of the database column is > 127, a PC/IXF LONG VARGRAPHIC column is created. The maximum length of the database column, the SBCS CPGID value, and the DBCS CPGID value are copied to the column descriptor record.	A PC/IXF GRAPHIC, VARGRAPHIC, or LONG VARGRAPHIC column is acceptable if the PC/IXF column double-byte code page value equals that of the database column. If the PC/IXF column is of fixed length, its length must be compatible with the maximum length of the database column.

**Related reference:**

- “PC/IXF Record Types” on page 254
- “PC/IXF Data Types” on page 270

## General Rules Governing PC/IXF File Import into Databases

The database manager import utility applies the following general rules when importing a PC/IXF file in either an SBCS or a DBCS environment:

- The import utility accepts PC/IXF format files only (IXFHID = 'IXF'). IXF files of other formats cannot be imported.
- The import utility rejects a PC/IXF file with more than 1024 columns.
- The value of IXFHSBCP in the PC/IXF H record must equal the SBCS CPGID, or there must be a conversion table between the IXFHSBCP/IXFHDBCP and the SBCS/DBCS CPGID of the target database. The value of IXFHDBCP must equal either '00000', or the DBCS CPGID of the target database. If either of these conditions is not satisfied, the import utility rejects the PC/IXF file, unless the FORCEIN option is specified.
- Invalid Data Types — New Table  
 Import of a PC/IXF file into a *new* table is specified by the CREATE or the REPLACE\_CREATE keywords in the IMPORT command. If a PC/IXF column of an invalid data type is selected for import into a new table, the import utility terminates. The entire PC/IXF file is rejected, no table is created, and no data is imported.
- Invalid Data Types — Existing Table  
 Import of a PC/IXF file into an *existing* table is specified by the INSERT, the INSERT\_UPDATE, or the REPLACE\_CREATE keywords in the IMPORT command. If a PC/IXF column of an invalid data type is selected for import into an existing table, one of two actions is possible:

- If the target table column is nullable, all values for the invalid PC/IXF column are ignored, and the table column values are set to NULL
- If the target table column is not nullable, the import utility terminates. The entire PC/IXF file is rejected, and no data is imported. The existing table remains unaltered.
- When importing into a new table, nullable PC/IXF columns generate nullable database columns, and not nullable PC/IXF columns generate not nullable database columns.
- A not nullable PC/IXF column can be imported into a nullable database column.
- A nullable PC/IXF column can be imported into a not nullable database column. If a NULL value is encountered in the PC/IXF column, the import utility rejects the values of all columns in the PC/IXF row that contains the NULL value (the entire row is rejected), and processing continues with the next PC/IXF row. That is, no data is imported from a PC/IXF row that contains a NULL value if a target table column (for the NULL) is not nullable.

- **Incompatible Columns — New Table**

If, during import to a *new* database table, a PC/IXF column is selected that is incompatible with the target database column, the import utility terminates. The entire PC/IXF file is rejected, no table is created, and no data is imported.

**Note:** The IMPORT FORCEIN option extends the scope of compatible columns.

- **Incompatible Columns — Existing Table**

If, during import to an *existing* database table, a PC/IXF column is selected that is incompatible with the target database column, one of two actions is possible:

- If the target table column is nullable, all values for the PC/IXF column are ignored, and the table column values are set to NULL
- If the target table column is not nullable, the import utility terminates. The entire PC/IXF file is rejected, and no data is imported. The existing table remains unaltered.

**Note:** The IMPORT FORCEIN option extends the scope of compatible columns.

- **Invalid Values**

If, during import, a PC/IXF column value is encountered that is not valid for the target database column, the import utility rejects the values of all columns in the PC/IXF row that contains the invalid value (the entire row is rejected), and processing continues with the next PC/IXF row.

- Importing or loading PC/IXF files containing DBCS data requires that the corresponding conversion files (located in `sqllib\conv`) be installed on the client machine. The names of these conversion files contain both the source and the target code page numbers; the extension is always `.cnv`. For example, file `09320943.cnv` contains the conversion table for converting code page 932 to 943.

If the client machine does not have the appropriate conversion files, they can be copied from a server machine to the `sqllib\conv` directory on the client machine. Be sure to copy the files from a compatible platform; for example, if the client is running on a UNIX based operating system, copy the files from a server that is also running on a UNIX based operating system.

**Related reference:**

- “PC/IXF Data Types” on page 270
- “FORCEIN Option” on page 283

## Data Type-Specific Rules Governing PC/IXF File Import into Databases

- A valid PC/IXF numeric column can be imported into any compatible numeric database column. PC/IXF columns containing 4-byte floating point data are not imported, because this is an invalid data type.
- Database date/time columns can accept values from matching PC/IXF date/time columns (DATE, TIME, and TIMESTAMP), as well as from PC/IXF character columns (CHAR, VARCHAR, and LONG VARCHAR), subject to column length and value compatibility restrictions.
- A valid PC/IXF character column (CHAR, VARCHAR, or LONG VARCHAR) can always be imported into an *existing* database character column marked FOR BIT DATA; otherwise:
  - IXFCSBCP and the SBCS CPGID must agree
  - There must be a conversion table for the IXFCSBCP/IXFCDBCP and the SBCS/DBCS
  - One set must be all zeros (FOR BIT DATA).

If IXFCSBCP is not zero, the value of IXFCDBCP must equal either zero or the DBCS CPGID of the target database column.

If either of these conditions is not satisfied, the PC/IXF and database columns are incompatible.

When importing a valid PC/IXF character column into a *new* database table, the value of IXFCSBCP must equal either zero or the SBCS CPGID of the database, or there must be a conversion table. If IXFCSBCP is zero, IXFCDBCP must also be zero (otherwise the PC/IXF column is an invalid data type); IMPORT creates a character column marked FOR BIT DATA in the new table. If IXFCSBCP is not zero, and equals the SBCS CPGID of the database, the value of IXFCDBCP must equal either zero or the DBCS CPGID of the database; in this case, the utility creates a character column in the new table with SBCS and DBCS CPGID values equal to those of the database. If these conditions are not satisfied, the PC/IXF and database columns are incompatible.

The FORCEIN option can be used to override code page equality checks. However, a PC/IXF character column with IXFCSBCP equal to zero and IXFCDBCP not equal to zero is an invalid data type, and cannot be imported, even if FORCEIN is specified.

- A valid PC/IXF graphic column (GRAPHIC, VARGRAPHIC, or LONG VARGRAPHIC) can always be imported into an *existing* database character column marked FOR BIT DATA, but is incompatible with all other database columns. The FORCEIN option can be used to relax this restriction. However, a PC/IXF graphic column with IXFCSBCP not equal to zero, or IXFCDBCP equal to zero, is an invalid data type, and cannot be imported, even if FORCEIN is specified.

When importing a valid PC/IXF graphic column into a database graphic column, the value of IXFCDBCP must equal the DBCS CPGID of the target database column (that is, the double-byte code pages of the two columns must agree).

- If, during import of a PC/IXF file into an existing database table, a fixed-length string column (CHAR or GRAPHIC) is selected whose length is greater than the maximum length of the target column, the columns are incompatible.
- If, during import of a PC/IXF file into an existing database table, a variable-length string column (VARCHAR, LONG VARCHAR, VARGRAPHIC, or LONG VARGRAPHIC) is selected whose length is greater than the maximum length of the target column, the columns *are* compatible. Individual values are

processed according to the compatibility rules governing the database manager INSERT statement, and PC/IXF values which are too long for the target database column are invalid.

- PC/IXF values imported into a fixed-length database *character* column (that is, a CHAR column) are padded on the right with single-byte spaces (0x20), if necessary, to obtain values whose length equals that of the database column. PC/IXF values imported into a fixed-length database *graphic* column (that is, a GRAPHIC column) are padded on the right with double-byte spaces (0x8140), if necessary, to obtain values whose length equals that of the database column.
- Since PC/IXF VARCHAR columns have a maximum length of 254 bytes, a database VARCHAR column of maximum length *n*, with  $254 < n < 4001$ , must be exported into a PC/IXF LONG VARCHAR column of maximum length *n*.
- Although PC/IXF LONG VARCHAR columns have a maximum length of 32 767 bytes, and database LONG VARCHAR columns have a maximum length restriction of 32 700 bytes, PC/IXF LONG VARCHAR columns of length greater than 32 700 bytes (but less than 32 768 bytes) are still valid, and can be imported into database LONG VARCHAR columns, but data might be lost.
- Since PC/IXF VARGRAPHIC columns have a maximum length of 127 bytes, a database VARGRAPHIC column of maximum length *n*, with  $127 < n < 2001$ , must be exported into a PC/IXF LONG VARGRAPHIC column of maximum length *n*.
- Although PC/IXF LONG VARGRAPHIC columns have a maximum length of 16 383 bytes, and database LONG VARGRAPHIC columns have a maximum length restriction of 16 350, PC/IXF LONG VARGRAPHIC columns of length greater than 16 350 bytes (but less than 16 384 bytes) are still valid, and can be imported into database LONG VARGRAPHIC columns, but data might be lost.

Table 21 summarizes PC/IXF file import into new or existing database tables without the FORCEIN option.

Table 21. Summary of PC/IXF File Import without FORCEIN Option

PC/IXF COLUMN DATA TYPE	DATABASE COLUMN DATA TYPE											
	NUMERIC					CHARACTER			GRAPH	DATETIME		
	SMALL INT	INT	BIGINT	DEC	FLT	(0,0)	(SBCS, 0) <sup>d</sup>	(SBCS, DBCS) <sup>b</sup>	<sup>b</sup>	DATE	TIME	TIME STAMP
Numeric												
-SMALLINT	N											
	E	E	E	E <sup>a</sup>	E							
-INTEGER		N										
	E <sup>a</sup>	E	E	E <sup>a</sup>	E							
-BIGINT			N									
	E <sup>a</sup>	E <sup>a</sup>	E	E <sup>a</sup>	E							
-DECIMAL				N								
	E <sup>a</sup>	E <sup>a</sup>	E <sup>a</sup>	E <sup>a</sup>	E							
-FLOAT					N							
	E <sup>a</sup>	E <sup>a</sup>	E <sup>a</sup>	E <sup>a</sup>	E							
Character												
-(0,0)						N						
						E				E <sup>c</sup>	E <sup>c</sup>	E <sup>c</sup>
-(SBCS,0)							N	N				
						E	E	E		E <sup>c</sup>	E <sup>c</sup>	E <sup>c</sup>
-(SBCS, DBCS)								N		E <sup>c</sup>	E <sup>c</sup>	E <sup>c</sup>

Table 21. Summary of PC/IXF File Import without FORCEIN Option (continued)

PC/IXF COLUMN DATA TYPE	DATABASE COLUMN DATA TYPE											
	NUMERIC					CHARACTER			GRAPH	DATETIME		
	SMALL INT	INT	BIGINT	DEC	FLT	(0,0)	(SBCS, 0) <sup>d</sup>	(SBCS, DBCS) <sup>b</sup>	<sup>b</sup>	DATE	TIME	TIME STAMP
						E		E				
Graphic												
									N			
						E			E			
Datetime												
-DATE										N		
									E			
-TIME											N	
											E	
-TIME STAMP												N
												E
<p><b>Notes:</b></p> <ol style="list-style-type: none"> <li>The table is a matrix of all valid PC/IXF and database manager data types. If a PC/IXF column can be imported into a database column, a letter is displayed in the matrix cell at the intersection of the PC/IXF data type matrix row and the database manager data type matrix column. An 'N' indicates that the utility is creating a new database table (a database column of the indicated data type is created). An 'E' indicates that the utility is importing data to an existing database table (a database column of the indicated data type is a valid target).</li> <li>Character string data types are distinguished by code page attributes. These attributes are shown as an ordered pair (SBCS, DBCS), where: <ul style="list-style-type: none"> <li>SBCS is either zero or denotes a non-zero value of the single-byte code page attribute of the character data type</li> <li>DBCS is either zero or denotes a non-zero value of the double-byte code page attribute of the character data type.</li> </ul> </li> <li>If the table indicates that a PC/IXF character column can be imported into a database character column, the values of their respective code page attribute pairs satisfy the rules governing code page equality.</li> </ol> <p><sup>a</sup> Individual values are rejected if they are out of range for the target numeric data type.</p> <p><sup>b</sup> Data type is available only in DBCS environments.</p> <p><sup>c</sup> Individual values are rejected if they are not valid date or time values.</p> <p><sup>d</sup> Data type is not available in DBCS environments.</p>												

## FORCEIN Option

The FORCEIN option permits import of a PC/IXF file despite code page differences between data in the PC/IXF file and the target database. It offers additional flexibility in the definition of compatible columns.

### FORCEIN General Semantics

The following general semantics apply when using the FORCEIN option in either an SBCS or a DBCS environment:

- The FORCEIN option should be used with caution. It is usually advisable to attempt an import without this option enabled. However, because of the generic nature of the PC/IXF data interchange architecture, some PC/IXF files might contain data types or values that cannot be imported without intervention.
- Import with FORCEIN to a *new* table might yield a different result than import to an existing table. An existing table has predefined target data types for each PC/IXF data type.
- When LOB data is exported with the LOBSINFILE option, and the files move to another client with a different code page, then, unlike other data, the CLOBS

and DBCLOBS in the separate files are not converted to the client code page when imported or loaded into a database.

## FORCEIN Code Page Semantics

The following code page semantics apply when using the FORCEIN option in either an SBCS or a DBCS environment:

- The FORCEIN option disables all import utility code page comparisons.  
This rule applies to code page comparisons at the column level and at the file level as well, when importing to a new or an existing database table. At the column (for example, data type) level, this rule applies only to the following database manager and PC/IXF data types: character (CHAR, VARCHAR, and LONG VARCHAR), and graphic (GRAPHIC, VARGRAPHIC, and LONG VARGRAPHIC). The restriction follows from the fact that code page attributes of other data types are not relevant to the interpretation of data type values.
- The FORCEIN option does not disable inspection of code page attributes to determine data types.  
For example, the database manager allows a CHAR column to be declared with the FOR BIT DATA attribute. Such a declaration sets both the SBCS CPGID and the DBCS CPGID of the column to zero; it is the zero value of these CPGIDs that identifies the column values as bit strings (rather than character strings).
- The FORCEIN option does not imply code page translation.  
Values of data types that are sensitive to the FORCEIN option are copied "as is". No code point mappings are employed to account for a change of code page environments. Padding of the imported value with spaces might be necessary in the case of fixed length target columns.
- When data is imported to an *existing* table using the FORCEIN option:
  - The code page value of the target database table and columns always prevails.
  - The code page value of the PC/IXF file and columns is ignored.This rule applies whether or not the FORCEIN option is used. The database manager does not permit changes to a database or a column code page value once a database is created.
- When importing to a *new* table using the FORCEIN option:
  - The code page value of the target database prevails.
  - PC/IXF character columns with IXFCSBCP = IXFCDBCP = 0 generate table columns marked FOR BIT DATA.
  - All other PC/IXF character columns generate table character columns with SBCS and DBCS CPGID values equal to those of the database.
  - PC/IXF graphic columns generate table graphic columns with an SBCS CPGID of "undefined", and a DBCS CPGID equal to that of the database (DBCS environment only).

## FORCEIN Example

Consider a PC/IXF CHAR column with IXFCSBCP = '00897' and IXFCDBCP = '00301'. This column is to be imported into a database CHAR column whose SBCS CPGID = '00850' and DBCS CPGID = '00000'. Without FORCEIN, the utility terminates, and no data is imported, or the PC/IXF column values are ignored, and the database column contains NULLs (if the database column is nullable). With FORCEIN, the utility proceeds, ignoring code page incompatibilities. If there are no other data type incompatibilities (such as length, for example), the values of

the PC/IXF column are imported "as is", and become available for interpretation under the database column code page environment.

The following table shows:

- The code page attributes of a column created in a *new* database table when a PC/IXF file data type with specified code page attributes is imported
- That the import utility rejects PC/IXF data types if they invalid or incompatible.

*Table 22. Summary of Import Utility Code Page Semantics (New Table).* This table assumes there is no conversion table between a and x. If there were, items 3 and 4 would work successfully without the FORCEIN option.

CODE PAGE ATTRIBUTES of PC/IXF DATA TYPE	CODE PAGE ATTRIBUTES OF DATABASE TABLE COLUMN	
	Without FORCEIN	With FORCEIN
SBCS		
(0,0)	(0,0)	(0,0)
(a,0)	(a,0)	(a,0)
(x,0)	reject	(a,0)
(x,y)	reject	(a,0)
(a,y)	reject	(a,0)
(0,y)	reject	(0,0)
DBCS		
(0,0)	(0,0)	(0,0)
(a,0)	(a,b)	(a,b)
(x,0)	reject	(a,b)
(a,b)	(a,b)	(a,b)
(x,y)	reject	(a,b)
(a,y)	reject	(a,b)
(x,b)	reject	(a,b)
(0,b)	(-,b)	(-,b)
(0,y)	reject	(-,b)

Table 22. Summary of Import Utility Code Page Semantics (New Table) (continued). This table assumes there is no conversion table between a and x. If there were, items 3 and 4 would work successfully without the FORCEIN option.

CODE PAGE ATTRIBUTES of PC/IXF DATA TYPE	CODE PAGE ATTRIBUTES OF DATABASE TABLE COLUMN	
	Without FORCEIN	With FORCEIN
<b>Notes:</b>		
1. Code page attributes of a PC/IXF data type are shown as an ordered pair, where x represents a non-zero single-byte code page value, and y represents a non-zero double-byte code page value. A '-' represents an undefined code page value.		
2. The use of different letters in various code page attribute pairs is deliberate. Different letters imply different values. For example, if a PC/IXF data type is shown as (x,y), and the database column as (a,y), x does not equal a, but the PC/IXF file and the database have the same double-byte code page value y.		
3. Only character and graphic data types are affected by the FORCEIN code page semantics.		
4. It is assumed that the database containing the new table has code page attributes of (a,0); therefore, all character columns in the new table must have code page attributes of either (0,0) or (a,0).  In a DBCS environment, it is assumed that the database containing the new table has code page attributes of (a,b); therefore, all graphic columns in the new table must have code page attributes of (-,b), and all character columns must have code page attributes of (a,b). The SBCS CPGID is shown as '-', because it is undefined for graphic data types.		
5. The data type of the result is determined by the rules described in "FORCEIN Data Type Semantics" on page 288.		
6. The reject result is a reflection of the rules for invalid or incompatible data types.		

The following table shows:

- That the import utility accepts PC/IXF data types with various code page attributes into an *existing* table column (the *target* column) having the specified code page attributes
- That the import utility does not permit a PC/IXF data type with certain code page attributes to be imported into an *existing* table column having the code page attributes shown. The utility rejects PC/IXF data types if they are invalid or incompatible.

Table 23. Summary of Import Utility Code Page Semantics (Existing Table). This table assumes there is no conversion table between a and x.

CODE PAGE ATTRIBUTES OF PC/IXF DATA TYPE	CODE PAGE ATTRIBUTES OF TARGET DATABASE COLUMN	RESULTS OF IMPORT	
		Without FORCEIN	With FORCEIN
SBCS			
(0,0)	(0,0)	accept	accept
(a,0)	(0,0)	accept	accept
(x,0)	(0,0)	accept	accept
(x,y)	(0,0)	accept	accept
(a,y)	(0,0)	accept	accept
(0,y)	(0,0)	accept	accept

Table 23. Summary of Import Utility Code Page Semantics (Existing Table) (continued). This table assumes there is no conversion table between a and x.

CODE PAGE ATTRIBUTES OF PC/IXF DATA TYPE	CODE PAGE ATTRIBUTES OF TARGET DATABASE COLUMN	RESULTS OF IMPORT	
		Without FORCEIN	With FORCEIN
(0,0)	(a,0)	null or reject	accept
(a,0)	(a,0)	accept	accept
(x,0)	(a,0)	null or reject	accept
(x,y)	(a,0)	null or reject	accept
(a,y)	(a,0)	null or reject	accept
(0,y)	(a,0)	null or reject	null or reject
DBCS			
(0,0)	(0,0)	accept	accept
(a,0)	(0,0)	accept	accept
(x,0)	(0,0)	accept	accept
(a,b)	(0,0)	accept	accept
(x,y)	(0,0)	accept	accept
(a,y)	(0,0)	accept	accept
(x,b)	(0,0)	accept	accept
(0,b)	(0,0)	accept	accept
(0,y)	(0,0)	accept	accept
(0,0)	(a,b)	null or reject	accept
(a,0)	(a,b)	accept	accept
(x,0)	(a,b)	null or reject	accept
(a,b)	(a,b)	accept	accept
(x,y)	(a,b)	null or reject	accept
(a,y)	(a,b)	null or reject	accept
(x,b)	(a,b)	null or reject	accept
(0,b)	(a,b)	null or reject	null or reject
(0,y)	(a,b)	null or reject	null or reject
(0,0)	(-,b)	null or reject	accept
(a,0)	(-,b)	null or reject	null or reject
(x,0)	(-,b)	null or reject	null or reject
(a,b)	(-,b)	null or reject	null or reject
(x,y)	(-,b)	null or reject	null or reject
(a,y)	(-,b)	null or reject	null or reject
(x,b)	(-,b)	null or reject	null or reject
(0,b)	(-,b)	accept	accept

Table 23. Summary of Import Utility Code Page Semantics (Existing Table) (continued). This table assumes there is no conversion table between a and x.

CODE PAGE ATTRIBUTES OF PC/IXF DATA TYPE	CODE PAGE ATTRIBUTES OF TARGET DATABASE COLUMN	RESULTS OF IMPORT	
		Without FORCEIN	With FORCEIN
(0,y)	(-,b)	null or reject	accept
<b>Notes:</b> 1. See the notes for Table 22 on page 285. 2. The null or reject result is a reflection of the rules for invalid or incompatible data types.			

### FORCEIN Data Type Semantics

The FORCEIN option permits import of certain PC/IXF columns into target database columns of unequal and otherwise incompatible data types. The following data type semantics apply when using the FORCEIN option in either an SBCS or a DBCS environment (except where noted):

- In SBCS environments, the FORCEIN option permits import of:
  - A PC/IXF BIT data type (IXFCSBCP = 0 = IXFCDBCP for a PC/IXF character column) into a database character column (non-zero SBCS CPGID, and DBCS CPGID = 0); existing tables only
  - A PC/IXF MIXED data type (non-zero IXFCSBCP and IXFCDBCP) into a database character column; both new and existing tables
  - A PC/IXF GRAPHIC data type into a database FOR BIT DATA column (SBCS CPGID = 0 = DBCS CPGID); new tables only (this is always permitted for existing tables).
- The FORCEIN option does not extend the scope of valid PC/IXF data types. PC/IXF columns with data types not defined as valid PC/IXF data types are invalid for import with or without the FORCEIN option.
- In DBCS environments, the FORCEIN option permits import of:
  - A PC/IXF BIT data type into a database character column
  - A PC/IXF BIT data type into a database graphic column; however, if the PC/IXF BIT column is of fixed length, that length must be even. A fixed length PC/IXF BIT column of odd length is not compatible with a database graphic column. A varying-length PC/IXF BIT column is compatible whether its length is odd or even, although an odd-length value from a varying-length column is an invalid value for import into a database graphic column
  - A PC/IXF MIXED data type into a database character column.

Table 24 summarizes PC/IXF file import into new or existing database tables with the FORCEIN option.

Table 24. Summary of PC/IXF File Import with FORCEIN Option

PC/IXF COLUMN DATA TYPE	DATABASE COLUMN DATA TYPE											
	NUMERIC					CHARACTER			GRAPH	DATETIME		
	SMALL INT	INT	BIGINT	DEC	FLT	(0,0)	(SBCS, 0) <sup>c</sup>	(SBCS, DBCS) <sup>b</sup>	<sup>b</sup>	DATE	TIME	TIME STAMP
Numeric												
-SMALLINT	N											

Table 24. Summary of PC/IXF File Import with FORCEIN Option (continued)

PC/IXF COLUMN DATA TYPE	DATABASE COLUMN DATA TYPE											
	NUMERIC					CHARACTER			GRAPH	DATETIME		
	SMALL INT	INT	BIGINT	DEC	FLT	(0,0)	(SBCS, 0) <sup>e</sup>	(SBCS, DBCS) <sup>b</sup>	<sup>b</sup>	DATE	TIME	TIME STAMP
	E	E	E	E <sup>a</sup>	E							
-INTEGER		N										
	E <sup>a</sup>	E	E	E <sup>a</sup>	E							
-BIGINT			N									
	E <sup>a</sup>	E <sup>a</sup>	E	E <sup>a</sup>	E							
-DECIMAL				N								
	E <sup>a</sup>	E <sup>a</sup>	E <sup>a</sup>	E <sup>a</sup>	E							
-FLOAT					N							
	E <sup>a</sup>	E <sup>a</sup>	E <sup>a</sup>	E <sup>a</sup>	E							
Character												
-(0,0)						N						
						E	E w/F	E w/F	E w/F	E <sup>c</sup>	E <sup>c</sup>	E <sup>c</sup>
-(SBCS,0)							N	N				
						E	E	E		E <sup>c</sup>	E <sup>c</sup>	E <sup>c</sup>
-(SBCS, DBCS)							N w/F <sup>d</sup>	N		E <sup>c</sup>	E <sup>c</sup>	E <sup>c</sup>
						E	E w/F	E				
Graphic												
						N w/F <sup>d</sup>			N			
						E			E			
Datetime												
-DATE										N		
										E		
-TIME											N	
											E	
-TIME STAMP												N
												E
<p><b>Note:</b> If a PC/IXF column can be imported into a database column only with the FORCEIN option, the string 'w/F' is displayed together with an 'N' or an 'E'. An 'N' indicates that the utility is creating a new database table; an 'E' indicates that the utility is importing data to an existing database table. The FORCEIN option affects compatibility of character and graphic data types only.</p> <p><sup>a</sup> Individual values are rejected if they are out of range for the target numeric data type.</p> <p><sup>b</sup> Data type is available only in DBCS environments.</p> <p><sup>c</sup> Individual values are rejected if they are not valid date or time values.</p> <p><sup>d</sup> Applies only if the source PC/IXF data type is not supported by the target database.</p> <p><sup>e</sup> Data type is not available in DBCS environments.</p>												

**Related reference:**

- "PC/IXF Data Types" on page 270
- "General Rules Governing PC/IXF File Import into Databases" on page 279

## Differences Between PC/IXF and Version 0 System/370 IXF

The following describes differences between PC/IXF, used by the database manager, and Version 0 System/370 IXF, used by several host database products:

- PC/IXF files are ASCII, rather than EBCDIC oriented. PC/IXF files have significantly expanded code page identification, including new code page identifiers in the H record, and the use of actual code page values in the column descriptor records. There is also a mechanism for marking columns of character data as FOR BIT DATA. FOR BIT DATA columns are of special significance, because transforms which convert a PC/IXF file format to or from any other IXF or database file format cannot perform any code page translation on the values contained in FOR BIT DATA columns.
- Only the machine data form is permitted; that is, the IXFTFORM field must always contain the value M. Furthermore, the machine data must be in PC forms; that is, the IXFTMFRM field must contain the value PC. This means that integers, floating point numbers, and decimal numbers in data portions of PC/IXF data records must be in PC forms.
- Application (A) records are permitted anywhere after the H record in a PC/IXF file. They are not counted when the value of the IXFHHCNT field is computed.
- Every PC/IXF record begins with a record length indicator. This is a 6-byte character representation of an integer value containing the length, in bytes, of the PC/IXF record not including the record length indicator itself; that is, the total record length minus 6 bytes. The purpose of the record length field is to enable PC programs to identify record boundaries.
- To facilitate the compact storage of variable-length data, and to avoid complex processing when a field is split into multiple records, PC/IXF does not support Version 0 IXF X records, but does support D record identifiers. Whenever a variable-length field or a nullable field is the last field in a data D record, it is not necessary to write the entire maximum length of the field to the PC/IXF file.

---

## Worksheet File Format (WSF)

Lotus 1-2-3 and Symphony products use the same basic format, with additional functions added at each new release. The database manager supports the subset of the worksheet records that are the same for all the Lotus products. That is, for the releases of Lotus 1-2-3 and Symphony products supported by the database manager, all file names with any three-character extension are accepted; for example: WKS, WK1, WRK, WR1, WJ2.

Each WSF file represents one worksheet. The database manager uses the following conventions to interpret worksheets and to provide consistency in worksheets generated by its export operations:

- Cells in the first row (ROW value 0) are reserved for descriptive information about the entire worksheet. All data within this row is optional. It is ignored during import.
- Cells in the second row (ROW value 1) are used for column labels.
- The remaining rows are data rows (records, or rows of data from the table).
- Cell values under any column heading are values for that particular column or field.
- A NULL value is indicated by the absence of a real cell content record (for example, no integer, number, label, or formula record) for a particular column within a row of cell content records.

**Note:** A row of NULLs will be neither imported nor exported.

To create a file that is compliant with the WSF format during an export operation, some loss of data may occur.

WSF files use a Lotus code point mapping that is not necessarily the same as existing code pages supported by DB2. As a result, when importing or exporting a WSF file, data is converted from the Lotus code points to or from the code points used by the application code page. DB2 supports conversion between the Lotus code points and code points defined by code pages 437, 819, 850, 860, 863, and 865.

**Note:** For multi-byte character set users, no conversions are performed.



---

## Appendix E. Export/Import/Load Utility Unicode Considerations

The export, import, and load utilities are not supported when they are used with a Unicode client connected to a non-Unicode database. Unicode client files are only supported when the Unicode client is connected to a Unicode database.

The DEL, ASC, and PC/IXF file formats are supported for a UCS-2 database, as described in this section. The WSF format is not supported.

When exporting from a UCS-2 database to an ASCII delimited (DEL) file, all character data is converted to the application code page. Both character string and graphic string data are converted to the same SBCS or MBCS code page of the client. This is expected behavior for the export of any database, and cannot be changed, because the entire delimited ASCII file can have only one code page. Therefore, if you export to a delimited ASCII file, only those UCS-2 characters that exist in your application code page will be saved. Other characters are replaced with the default substitution character for the application code page. For UTF-8 clients (code page 1208), there is no data loss, because all UCS-2 characters are supported by UTF-8 clients.

When importing from an ASCII file (DEL or ASC) to a UCS-2 database, character string data is converted from the application code page to UTF-8, and graphic string data is converted from the application code page to UCS-2. There is no data loss. If you want to import ASCII data that has been saved under a different code page, you should change the data file code page before issuing the IMPORT command. One way to accomplish this is to set DB2CODEPAGE to the code page of the ASCII data file.

The range of valid ASCII delimiters for SBCS and MBCS clients is identical to what is currently supported by DB2<sup>®</sup> UDB for those clients. The range of valid delimiters for UTF-8 clients is X'01' to X'7F', with the usual restrictions.

When exporting from a UCS-2 database to a PC/IXF file, character string data is converted to the SBCS/MBCS code page of the client. Graphic string data is not converted, and is stored in UCS-2 (code page 1200). There is no data loss.

When importing from a PC/IXF file to a UCS-2 database, character string data is assumed to be in the SBCS/MBCS code page stored in the PC/IXF header, and graphic string data is assumed to be in the DBCS code page stored in the PC/IXF header. Character string data is converted by the import utility from the code page specified in the PC/IXF header to the code page of the client, and then from the client code page to UTF-8 (by the INSERT statement). graphic string data is converted by the import utility from the DBCS code page specified in the PC/IXF header directly to UCS-2 (code page 1200).

The load utility places the data directly into the database and, by default, assumes data in ASC or DEL files to be in the code page of the database. Therefore, by default, no code page conversion takes place for ASCII files. When the code page for the data file has been explicitly specified (using the codepage modifier), the load utility uses this information to convert from the specified code page to the database code page before loading the data. For PC/IXF files, the load utility

always converts from the code pages specified in the IXF header to the database code page (1208 for CHAR, and 1200 for GRAPHIC).

The code page for DBCLOB files is always 1200 for UCS-2. The code page for CLOB files is the same as the code page for the data files being imported, loaded or exported. For example, when loading or importing data using the PC/IXF format, the CLOB file is assumed to be in the code page specified by the PC/IXF header. If the DBCLOB file is in ASC or DEL format, the load utility assumes that CLOB data is in the code page of the database (unless explicitly specified otherwise using the codepage modifier), while the import utility assumes it to be in the code page of the client application.

The `nochecklengths` modifier is always specified for a UCS-2 database, because:

- Any SBCS can be connected to a database for which there is no DBCS code page
- Character strings in UTF-8 format usually have different lengths than those in client code pages.

---

## Restrictions for Code Pages 1394, 1392 and 5488

The import, export and load utilities can now be used to transfer data from the new Chinese code page GB 18030 (code page identifier 1392 and 5488) and the new Japanese code page ShiftJISX 0213 (code page identifier 1394) to DB2 UDB Unicode databases. In addition, the export utility can be used to transfer data from DB2 UDB Unicode databases to GB 18030 or ShiftJIS X0213 code page data.

For example, the following command will load the `Shift_JISX0213` data file `u/jp/user/x0213/data.del` residing on a remotely connected client into MYTABLE:

```
db2 load client from /u/jp/user/x0213/data.del
of del modified by codepage=1394 insert into mytable
```

where MYTABLE is located on a DB2 UDB Unicode database.

Since only connections between a Unicode client and a Unicode server are supported, so you need to use either a Unicode client or set the DB2 registry variable `DB2CODEPAGE` to 1208 prior to using the load, import, or export utilities.

Conversion from code page 1394, 1392, or 5488 to Unicode may result in expansion. For example, a 2-byte character may be stored as two 16-bit Unicode characters in the GRAPHIC columns. You need to ensure the target columns in the Unicode database are wide enough to contain any expanded Unicode byte.

---

## Incompatibilities

For applications connected to a UCS-2 database, graphic string data is always in UCS-2 (code page 1200). For applications connected to non-UCS-2 databases, the graphic string data is in the DBCS code page of the application, or not allowed if the application code page is SBCS. For example, when a 932 client is connected to a Japanese non-UCS-2 database, the graphic string data is in code page 301. For the 932 client applications connected to a UCS-2 database, the graphic string data is in UCS-2.

### Related reference:

- “DEL Data Type Descriptions” on page 246
- “Non-delimited ASCII (ASC) File Format” on page 249

- “PC Version of IXF File Format” on page 252



## Appendix F. Bind Files Used by the Export, Import and Load Utilities

The following table lists bind files with their default isolation levels, as well as which utilities use them and for what purpose.

Bind File (Default Isolation Level)	Utility/Purpose
db2ueiwi.bnd (CS)	Import/Export. Used to query information about table columns and indexes.
db2uexpm.bnd (CS)	Export. Used to fetch from the SQL query specified for the export operation.
db2uimpb.bnd (RS)	Import. Used to insert data from the source data file into the target table.
db2uipkg.bnd (CS)	Import. Used to check bind options.
db2uiici.bnd (RR)	Import. Used to create indexes when the IXF CREATE option is specified.
db2ucktb.bnd (CS)	Load. Used to perform general initialization processes for a load operation.
db2ulxld.bnd (CS)	Load. Used to process the SQL query provided during a load from cursor operation.
db2uigsi.bnd (RS on UNIX based systems, RR on all other platforms)	Import/Export. Used to drop indexes and check for referential constraints for an import replace operation. Also used to retrieve identity column information for exporting IXF files.
db2uiict.bnd (RR)	Import. Used to create tables when the IXF CREATE option is specified.
db2uqtpd.bnd (RR)	Import/Export. Used to perform processing for hierarchical tables.
db2uqtnm.bnd (RR)	Import. Used to perform processing for hierarchical tables when the IXF CREATE option is specified.
db2uimtb.bnd (RS)	Import. Used to perform general initialization processes for an import operation.



---

## Appendix G. Warning, error and completion messages

Messages generated by the various utilities are included among the SQL messages. These messages are generated by the database manager when a warning or error condition has been detected. Each message has a message identifier that consists of a prefix (SQL) and a four- or five-digit message number. There are three message types: notification, warning, and critical. Message identifiers ending with an N are error messages. Those ending with a W indicate warning or informational messages. Message identifiers ending with a C indicate critical system errors.

The message number is also referred to as the *SQLCODE*. The *SQLCODE* is passed to the application as a positive or negative number, depending on its message type (N, W, or C). N and C yield negative values, whereas W yields a positive value. DB2 returns the *SQLCODE* to the application, and the application can get the message associated with the *SQLCODE*. DB2 also returns an *SQLSTATE* value for conditions that could be the result of an SQL statement. Some *SQLCODE* values have associated *SQLSTATE* values.

You can use the information contained in this book to identify an error or problem, and to resolve the problem by using the appropriate recovery action. This information can also be used to understand where messages are generated and logged.

SQL messages, and the message text associated with *SQLSTATE* values, are also accessible from the operating system command line. To access help for these error messages, enter the following at the operating system command prompt:

```
db2 ? SQLnnnn
```

where *nnnnn* represents the message number. On UNIX based systems, the use of double quotation mark delimiters is recommended; this will avoid problems if there are single character file names in the directory:

```
db2 "? SQLnnnn"
```

The message identifier accepted as a parameter for the **db2** command is not case sensitive, and the terminating letter is not required. Therefore, the following commands will produce the same result:

```
db2 ? SQL0000N
db2 ? sq10000
db2 ? SQL0000n
```

If the message text is too long for your screen, use the following command (on UNIX based operating systems and others that support the "more" pipe):

```
db2 ? SQLnnnn | more
```

You can also redirect the output to a file which can then be browsed.

Help can also be invoked from interactive input mode. To access this mode, enter the following at the operating system command prompt:

```
db2
```

To get DB2 message help in this mode, type the following at the command prompt (db2 =>):

? SQLnnnnn

The message text associated with SQLSTATEs can be retrieved by issuing:

db2 ? nnnnn

or

db2 ? nn

where *nnnnn* is a five-character SQLSTATE value (alphanumeric), and *nn* is a two-digit SQLSTATE class code (the first two digits of the SQLSTATE value).

---

## Appendix H. DB2 Universal Database technical information

---

### DB2 documentation and help

DB2<sup>®</sup> technical information is available through the following tools and methods:

- DB2 Information Center
  - Topics
  - Help for DB2 tools
  - Sample programs
  - Tutorials
- Downloadable PDF files, PDF files on CD, and printed books
  - Guides
  - Reference manuals
- Command line help
  - Command help
  - Message help
  - SQL state help
- Installed source code
  - Sample programs

You can access additional DB2 Universal Database<sup>™</sup> technical information such as technotes, white papers, and Redbooks<sup>™</sup> online at [ibm.com](http://ibm.com)<sup>®</sup>. Access the DB2 Information Management software library site at [www.ibm.com/software/data/pubs/](http://www.ibm.com/software/data/pubs/).

### DB2 documentation updates

IBM<sup>®</sup> may periodically make documentation FixPaks and other documentation updates to the DB2 Information Center available. If you access the DB2 Information Center at <http://publib.boulder.ibm.com/infocenter/db2help/>, you will always be viewing the most up-to-date information. If you have installed the DB2 Information Center locally, then you need to install any updates manually before you can view them. Documentation updates allow you to update the information that you installed from the *DB2 Information Center CD* when new information becomes available.

The Information Center is updated more frequently than either the PDF or the hardcopy books. To get the most current DB2 technical information, install the documentation updates as they become available or go to the DB2 Information Center at the [www.ibm.com](http://www.ibm.com) site.

#### Related tasks:

- “Invoking contextual help from a DB2 tool” on page 318

#### Related reference:

- “DB2 PDF and printed documentation” on page 312

---

## DB2 Information Center

The DB2<sup>®</sup> Information Center gives you access to all of the information you need to take full advantage of DB2 family products, including DB2 Universal Database<sup>™</sup>, DB2 Connect<sup>™</sup>, DB2 Information Integrator and DB2 Query Patroller<sup>™</sup>. The DB2 Information Center also contains information for major DB2 features and components including replication, data warehousing, and the DB2 extenders.

The DB2 Information Center has the following features if you view it in Mozilla 1.0 or later or Microsoft<sup>®</sup> Internet Explorer 5.5 or later. Some features require you to enable support for JavaScript<sup>™</sup>:

### Flexible installation options

You can choose to view the DB2 documentation using the option that best meets your needs:

- To effortlessly ensure that your documentation is always up to date, you can access all of your documentation directly from the DB2 Information Center hosted on the IBM<sup>®</sup> Web site at <http://publib.boulder.ibm.com/infocenter/db2help/>
- To minimize your update efforts and keep your network traffic within your intranet, you can install the DB2 documentation on a single server on your intranet
- To maximize your flexibility and reduce your dependence on network connections, you can install the DB2 documentation on your own computer

### Search

You can search all of the topics in the DB2 Information Center by entering a search term in the **Search** text field. You can retrieve exact matches by enclosing terms in quotation marks, and you can refine your search with wildcard operators (\*, ?) and Boolean operators (AND, NOT, OR).

### Task-oriented table of contents

You can locate topics in the DB2 documentation from a single table of contents. The table of contents is organized primarily by the kind of tasks you may want to perform, but also includes entries for product overviews, goals, reference information, an index, and a glossary.

- Product overviews describe the relationship between the available products in the DB2 family, the features offered by each of those products, and up to date release information for each of these products.
- Goal categories such as installing, administering, and developing include topics that enable you to quickly complete tasks and develop a deeper understanding of the background information for completing those tasks.
- Reference topics provide detailed information about a subject, including statement and command syntax, message help, and configuration parameters.

### Show current topic in table of contents

You can show where the current topic fits into the table of contents by clicking the **Refresh / Show Current Topic** button in the table of contents frame or by clicking the **Show in Table of Contents** button in the content frame. This feature is helpful if you have followed several links to related topics in several files or arrived at a topic from search results.

**Index** You can access all of the documentation from the index. The index is organized in alphabetical order by index term.

**Glossary**

You can use the glossary to look up definitions of terms used in the DB2 documentation. The glossary is organized in alphabetical order by glossary term.

**Integrated localized information**

The DB2 Information Center displays information in the preferred language set in your browser preferences. If a topic is not available in your preferred language, the DB2 Information Center displays the English version of that topic.

For iSeries™ technical information, refer to the IBM eServer™ iSeries information center at [www.ibm.com/eserver/series/infocenter/](http://www.ibm.com/eserver/series/infocenter/).

**Related concepts:**

- “DB2 Information Center installation scenarios” on page 303

**Related tasks:**

- “Updating the DB2 Information Center installed on your computer or intranet server” on page 311
- “Displaying topics in your preferred language in the DB2 Information Center” on page 311
- “Invoking the DB2 Information Center” on page 310
- “Installing the DB2 Information Center using the DB2 Setup wizard (UNIX)” on page 305
- “Installing the DB2 Information Center using the DB2 Setup wizard (Windows)” on page 308

---

## DB2 Information Center installation scenarios

Different working environments can pose different requirements for how to access DB2® information. The DB2 Information Center can be accessed on the IBM® Web site, on a server on your organization’s network, or on a version installed on your computer. In all three cases, the documentation is contained in the DB2 Information Center, which is an architected web of topic-based information that you view with a browser. By default, DB2 products access the DB2 Information Center on the IBM Web site. However, if you want to access the DB2 Information Center on an intranet server or on your own computer, you must install the DB2 Information Center using the DB2 Information Center CD found in your product Media Pack. Refer to the summary of options for accessing DB2 documentation which follows, along with the three installation scenarios, to help determine which method of accessing the DB2 Information Center works best for you and your work environment, and what installation issues you might need to consider.

**Summary of options for accessing DB2 documentation:**

The following table provides recommendations on which options are possible in your work environment for accessing the DB2 product documentation in the DB2 Information Center.

Internet access	Intranet access	Recommendation
Yes	Yes	Access the DB2 Information Center on the IBM Web site, or access the DB2 Information Center installed on an intranet server.
Yes	No	Access the DB2 Information Center on the IBM Web site.
No	Yes	Access the DB2 Information Center installed on an intranet server.
No	No	Access the DB2 Information Center on a local computer.

### Scenario: Accessing the DB2 Information Center on your computer:

Tsu-Chen owns a factory in a small town that does not have a local ISP to provide him with Internet access. He purchased DB2 Universal Database™ to manage his inventory, his product orders, his banking account information, and his business expenses. Never having used a DB2 product before, Tsu-Chen needs to learn how to do so from the DB2 product documentation.

After installing DB2 Universal Database on his computer using the typical installation option, Tsu-Chen tries to access the DB2 documentation. However, his browser gives him an error message that the page he tried to open cannot be found. Tsu-Chen checks the installation manual for his DB2 product and discovers that he has to install the DB2 Information Center if he wants to access DB2 documentation on his computer. He finds the *DB2 Information Center CD* in the media pack and installs it.

From the application launcher for his operating system, Tsu-Chen now has access to the DB2 Information Center and can learn how to use his DB2 product to increase the success of his business.

### Scenario: Accessing the DB2 Information Center on the IBM Web site:

Colin is an information technology consultant with a training firm. He specializes in database technology and SQL and gives seminars on these subjects to businesses all over North America using DB2 Universal Database. Part of Colin's seminars includes using DB2 documentation as a teaching tool. For example, while teaching courses on SQL, Colin uses the DB2 documentation on SQL as a way to teach basic and advanced syntax for database queries.

Most of the businesses at which Colin teaches have Internet access. This situation influenced Colin's decision to configure his mobile computer to access the DB2 Information Center on the IBM Web site when he installed the latest version of DB2 Universal Database. This configuration allows Colin to have online access to the latest DB2 documentation during his seminars.

However, sometimes while travelling Colin does not have Internet access. This posed a problem for him, especially when he needed to access to DB2 documentation to prepare for seminars. To avoid situations like this, Colin installed a copy of the DB2 Information Center on his mobile computer.

Colin enjoys the flexibility of always having a copy of DB2 documentation at his disposal. Using the **db2set** command, he can easily configure the registry variables

on his mobile computer to access the DB2 Information Center on either the IBM Web site, or his mobile computer, depending on his situation.

**Scenario: Accessing the DB2 Information Center on an intranet server:**

Eva works as a senior database administrator for a life insurance company. Her administration responsibilities include installing and configuring the latest version of DB2 Universal Database on the company's UNIX® database servers. Her company recently informed its employees that, for security reasons, it would not provide them with Internet access at work. Because her company has a networked environment, Eva decides to install a copy of the DB2 Information Center on an intranet server so that all employees in the company who use the company's data warehouse on a regular basis (sales representatives, sales managers, and business analysts) have access to DB2 documentation.

Eva instructs her database team to install the latest version of DB2 Universal Database on all of the employee's computers using a response file, to ensure that each computer is configured to access the DB2 Information Center using the host name and the port number of the intranet server.

However, through a misunderstanding Migual, a junior database administrator on Eva's team, installs a copy of the DB2 Information Center on several of the employee computers, rather than configuring DB2 Universal Database to access the DB2 Information Center on the intranet server. To correct this situation Eva tells Migual to use the **db2set** command to change the DB2 Information Center registry variables (DB2\_DOCHOST for the host name, and DB2\_DOCPORT for the port number) on each of these computers. Now all of the appropriate computers on the network have access to the DB2 Information Center, and employees can find answers to their DB2 questions in the DB2 documentation.

**Related concepts:**

- "DB2 Information Center" on page 302

**Related tasks:**

- "Updating the DB2 Information Center installed on your computer or intranet server" on page 311
- "Installing the DB2 Information Center using the DB2 Setup wizard (UNIX)" on page 305
- "Installing the DB2 Information Center using the DB2 Setup wizard (Windows)" on page 308

**Related reference:**

- "db2set - DB2 Profile Registry Command" in the *Command Reference*

---

## Installing the DB2 Information Center using the DB2 Setup wizard (UNIX)

DB2 product documentation can be accessed in three ways: on the IBM Web site, on an intranet server, or on a version installed on your computer. By default, DB2 products access DB2 documentation on the IBM Web site. If you want to access the DB2 documentation on an intranet server or on your own computer, you must install the documentation from the *DB2 Information Center CD*. Using the DB2 Setup wizard, you can define your installation preferences and install the DB2 Information Center on a computer that uses a UNIX operating system.

## Prerequisites:

This section lists the hardware, operating system, software, and communication requirements for installing the DB2 Information Center on UNIX computers.

- **Hardware requirements**

You require one of the following processors:

- PowerPC (AIX)
- HP 9000 (HP-UX)
- Intel 32-bit (Linux)
- Solaris UltraSPARC computers (Solaris Operating Environment)

- **Operating system requirements**

You require one of the following operating systems:

- IBM AIX 5.1 (on PowerPC)
- HP-UX 11i (on HP 9000)
- Red Hat Linux 8.0 (on Intel 32-bit)
- SuSE Linux 8.1 (on Intel 32-bit)
- Sun Solaris Version 8 (on Solaris Operating Environment UltraSPARC computers)

**Note:** The DB2 Information Center runs on a subset of the UNIX operating systems on which DB2 clients are supported. It is therefore recommended that you either access the DB2 Information Center from the IBM Web site, or that you install and access the DB2 Information Center on an intranet server.

- **Software requirements**

- The following browser is supported:
  - Mozilla Version 1.0 or greater

- The DB2 Setup wizard is a graphical installer. You must have an implementation of the X Window System software capable of rendering a graphical user interface for the DB2 Setup wizard to run on your computer. Before you can run the DB2 Setup wizard you must ensure that you have properly exported your display. For example, enter the following command at the command prompt:  
`export DISPLAY=9.26.163.144:0.`

- **Communication requirements**

- TCP/IP

## Procedure:

To install the DB2 Information Center using the DB2 Setup wizard:

1. Log on to the system.
2. Insert and mount the DB2 Information Center product CD on your system.
3. Change to the directory where the CD is mounted by entering the following command:

```
cd /cd
```

where */cd* represents the mount point of the CD.

4. Enter the `./db2setup` command to start the DB2 Setup wizard.
5. The IBM DB2 Setup Launchpad opens. To proceed directly to the installation of the DB2 Information Center, click **Install Product**. Online help is available

- to guide you through the remaining steps. To invoke the online help, click **Help**. You can click **Cancel** at any time to end the installation.
6. On the **Select the product you would like to install** page, click **Next**.
  7. Click **Next** on the **Welcome to the DB2 Setup wizard** page. The DB2 Setup wizard will guide you through the program setup process.
  8. To proceed with the installation, you must accept the license agreement. On the **License Agreement** page, select **I accept the terms in the license agreement** and click **Next**.
  9. Select **Install DB2 Information Center on this computer** on the **Select the installation action** page. If you want to use a response file to install the DB2 Information Center on this or other computers at a later time, select **Save your settings in a response file**. Click **Next**.
  10. Select the languages in which the DB2 Information Center will be installed on **Select the languages to install** page. Click **Next**.
  11. Configure the DB2 Information Center for incoming communication on the **Specify the DB2 Information Center port** page. Click **Next** to continue the installation.
  12. Review the installation choices you have made in the **Start copying files** page. To change any settings, click **Back**. Click **Install** to copy the DB2 Information Center files onto your computer.

You can also install the DB2 Information Center using a response file.

The installation logs `db2setup.his`, `db2setup.log`, and `db2setup.err` are located, by default, in the `/tmp` directory.

The `db2setup.log` file captures all DB2 product installation information, including errors. The `db2setup.his` file records all DB2 product installations on your computer. DB2 appends the `db2setup.log` file to the `db2setup.his` file. The `db2setup.err` file captures any error output that is returned by Java, for example, exceptions and trap information.

When the installation is complete, the DB2 Information Center will be installed in one of the following directories, depending upon your UNIX operating system:

- AIX: `/usr/opt/db2_08_01`
- HP-UX: `/opt/IBM/db2/V8.1`
- Linux: `/opt/IBM/db2/V8.1`
- Solaris Operating Environment: `/opt/IBM/db2/V8.1`

**Related concepts:**

- “DB2 Information Center installation scenarios” on page 303

**Related tasks:**

- “Displaying topics in your preferred language in the DB2 Information Center” on page 311
- “Installing the DB2 Information Center using the DB2 Setup wizard (Windows)” on page 308

---

## Installing the DB2 Information Center using the DB2 Setup wizard (Windows)

DB2 product documentation can be accessed in three ways: on the IBM Web site, on an intranet server, or on a version installed on your computer. By default, DB2 products access DB2 documentation on the IBM Web site. If you want to access the DB2 documentation on an intranet server or on your own computer, you must install the DB2 documentation from the *DB2 Information Center CD*. Using the DB2 Setup wizard, you can define your installation preferences and install the DB2 Information Center on a computer that uses a Windows operating system.

### Prerequisites:

This section lists the hardware, operating system, software, and communication requirements for installing the DB2 Information Center on Windows.

- **Hardware requirements**

You require one of the following processors:

- 32-bit computers: a Pentium or Pentium compatible CPU

- **Operating system requirements**

You require one of the following operating systems:

- Windows 2000
- Windows XP

**Note:** The DB2 Information Center runs on a subset of the Windows operating systems on which DB2 clients are supported. It is therefore recommended that you either access the DB2 Information Center on the IBM Web site, or that you install and access the DB2 Information Center on an intranet server.

- **Software requirements**

- The following browsers are supported:
  - Mozilla 1.0 or greater
  - Internet Explorer Version 5.5 or 6.0 (Version 6.0 for Windows XP)

- **Communication requirements**

- TCP/IP

### Restrictions:

- You require an account with administrative privileges to install the DB2 Information Center.

### Procedure:

To install the DB2 Information Center using the DB2 Setup wizard:

1. Log on to the system with the account that you have defined for the DB2 Information Center installation.
2. Insert the CD into the drive. If enabled, the auto-run feature starts the IBM DB2 Setup Launchpad.
3. The DB2 Setup wizard determines the system language and launches the setup program for that language. If you want to run the setup program in a language other than English, or the setup program fails to auto-start, you can start the DB2 Setup wizard manually.

To start the DB2 Setup wizard manually:

- a. Click **Start** and select **Run**.
- b. In the **Open** field, type the following command:

```
x:\setup.exe /i 2-letter language identifier
```

where *x*: represents your CD drive, and *2-letter language identifier* represents the language in which the setup program will be run.

- c. Click **OK**.
4. The IBM DB2 Setup Launchpad opens. To proceed directly to the installation of the DB2 Information Center, click **Install Product**. Online help is available to guide you through the remaining steps. To invoke the online help, click **Help**. You can click **Cancel** at any time to end the installation.
5. On the **Select the product you would like to install** page, click **Next**.
6. Click **Next** on the **Welcome to the DB2 Setup wizard** page. The DB2 Setup wizard will guide you through the program setup process.
7. To proceed with the installation, you must accept the license agreement. On the **License Agreement** page, select **I accept the terms in the license agreement** and click **Next**.
8. Select **Install DB2 Information Center on this computer** on the **Select the installation action** page. If you want to use a response file to install the DB2 Information Center on this or other computers at a later time, select **Save your settings in a response file**. Click **Next**.
9. Select the languages in which the DB2 Information Center will be installed on **Select the languages to install** page. Click **Next**.
10. Configure the DB2 Information Center for incoming communication on the **Specify the DB2 Information Center port** page. Click **Next** to continue the installation.
11. Review the installation choices you have made in the **Start copying files** page. To change any settings, click **Back**. Click **Install** to copy the DB2 Information Center files onto your computer.

You can install the DB2 Information Center using a response file. You can also use the **db2rspgn** command to generate a response file based on an existing installation.

For information on errors encountered during installation, see the `db2.log` and `db2wi.log` files located in the 'My Documents'\DB2LOG\ directory. The location of the 'My Documents' directory will depend on the settings on your computer.

The `db2wi.log` file captures the most recent DB2 installation information. The `db2.log` captures the history of DB2 product installations.

#### **Related concepts:**

- “DB2 Information Center installation scenarios” on page 303

#### **Related tasks:**

- “Displaying topics in your preferred language in the DB2 Information Center” on page 311
- “Installing the DB2 Information Center using the DB2 Setup wizard (UNIX)” on page 305

---

## Invoking the DB2 Information Center

The DB2 Information Center gives you access to all of the information that you need to use DB2 products for Linux, UNIX, and Windows operating systems such as DB2 Universal Database, DB2 Connect, DB2 Information Integrator, and DB2 Query Patroller.

You can invoke the DB2 Information Center from one of the following places:

- Computers on which a DB2 UDB client or server is installed
- An intranet server or local computer on which the DB2 Information Center installed
- The IBM Web site

### Prerequisites:

Before you invoke the DB2 Information Center:

- *Optional:* Configure your browser to display topics in your preferred language
- *Optional:* Configure your DB2 client to use the DB2 Information Center installed on your computer or intranet server

### Procedure:

To invoke the DB2 Information Center on a computer on which a DB2 UDB client or server is installed:

- From the Start Menu (Windows operating system): Click **Start** → **Programs** → **IBM DB2** → **Information** → **Information Center**.
- From the command line prompt:
  - For Linux and UNIX operating systems, issue the **db2icdocs** command.
  - For the Windows operating system, issue the **db2icdocs.exe** command.

To open the DB2 Information Center installed on an intranet server or local computer in a Web browser:

- Open the Web page at `http://<host-name>:<port-number>/`, where `<host-name>` represents the host name and `<port-number>` represents the port number on which the DB2 Information Center is available.

To open the DB2 Information Center on the IBM Web site in a Web browser:

- Open the Web page at `publib.boulder.ibm.com/infocenter/db2help/`.

### Related concepts:

- “DB2 Information Center” on page 302

### Related tasks:

- “Displaying topics in your preferred language in the DB2 Information Center” on page 311
- “Invoking contextual help from a DB2 tool” on page 318
- “Updating the DB2 Information Center installed on your computer or intranet server” on page 311
- “Invoking message help from the command line processor” on page 319
- “Invoking command help from the command line processor” on page 320
- “Invoking SQL state help from the command line processor” on page 320

---

## Updating the DB2 Information Center installed on your computer or intranet server

The DB2 Information Center available from <http://publib.boulder.ibm.com/infocenter/db2help/> will be periodically updated with new or changed documentation. IBM may also make DB2 Information Center updates available to download and install on your computer or intranet server. Updating the DB2 Information Center does not update DB2 client or server products.

### Prerequisites:

You must have access to a computer that is connected to the Internet.

### Procedure:

To update the DB2 Information Center installed on your computer or intranet server:

1. Open the DB2 Information Center hosted on the IBM Web site at: <http://publib.boulder.ibm.com/infocenter/db2help/>
2. In the Downloads section of the welcome page under the Service and Support heading, click the **DB2 Universal Database documentation** link.
3. Determine if the version of your DB2 Information Center is out of date by comparing the latest refreshed documentation image level to the documentation level you have installed. The documentation level you have installed is listed on the DB2 Information Center welcome page.
4. If a more recent version of the DB2 Information Center is available, download the latest refreshed *DB2 Information Center* image applicable to your operating system.
5. To install the refreshed *DB2 Information Center* image, follow the instructions provided on the Web page.

### Related concepts:

- “DB2 Information Center installation scenarios” on page 303

### Related tasks:

- “Invoking the DB2 Information Center” on page 310
- “Installing the DB2 Information Center using the DB2 Setup wizard (UNIX)” on page 305
- “Installing the DB2 Information Center using the DB2 Setup wizard (Windows)” on page 308

---

## Displaying topics in your preferred language in the DB2 Information Center

The DB2 Information Center attempts to display topics in the language specified in your browser preferences. If a topic has not been translated into your preferred language, the DB2 Information Center displays the topic in English.

### Procedure:

To display topics in your preferred language in the Internet Explorer browser:

1. In Internet Explorer, click the **Tools** —> **Internet Options** —> **Languages...** button. The Language Preferences window opens.
2. Ensure your preferred language is specified as the first entry in the list of languages.
  - To add a new language to the list, click the **Add...** button.

**Note:** Adding a language does not guarantee that the computer has the fonts required to display the topics in the preferred language.

- To move a language to the top of the list, select the language and click the **Move Up** button until the language is first in the list of languages.
3. Refresh the page to display the DB2 Information Center in your preferred language.

To display topics in your preferred language in the Mozilla browser:

1. In Mozilla, select the **Edit** —> **Preferences** —> **Languages** button. The Languages panel is displayed in the Preferences window.
2. Ensure your preferred language is specified as the first entry in the list of languages.
  - To add a new language to the list, click the **Add...** button to select a language from the Add Languages window.
  - To move a language to the top of the list, select the language and click the **Move Up** button until the language is first in the list of languages.
3. Refresh the page to display the DB2 Information Center in your preferred language.

---

## DB2 PDF and printed documentation

The following tables provide official book names, form numbers, and PDF file names. To order hardcopy books, you must know the official book name. To print a PDF file, you must know the PDF file name.

The DB2 documentation is categorized by the following headings:

- Core DB2 information
- Administration information
- Application development information
- Business intelligence information
- DB2 Connect information
- Getting started information
- Tutorial information
- Optional component information
- Release notes

The following tables describe, for each book in the DB2 library, the information needed to order the hard copy, or to print or view the PDF for that book. A full description of each of the books in the DB2 library is available from the IBM Publications Center at [www.ibm.com/shop/publications/order](http://www.ibm.com/shop/publications/order)

### Core DB2 information

The information in these books is fundamental to all DB2 users; you will find this information useful whether you are a programmer, a database administrator, or someone who works with DB2 Connect, DB2 Warehouse Manager, or other DB2

products.

*Table 25. Core DB2 information*

<b>Name</b>	<b>Form Number</b>	<b>PDF File Name</b>
<i>IBM DB2 Universal Database Command Reference</i>	SC09-4828	db2n0x81
<i>IBM DB2 Universal Database Glossary</i>	No form number	db2f0x81
<i>IBM DB2 Universal Database Message Reference, Volume 1</i>	GC09-4840, not available in hardcopy	db2m1x81
<i>IBM DB2 Universal Database Message Reference, Volume 2</i>	GC09-4841, not available in hardcopy	db2m2x81
<i>IBM DB2 Universal Database What's New</i>	SC09-4848	db2q0x81

## Administration information

The information in these books covers those topics required to effectively design, implement, and maintain DB2 databases, data warehouses, and federated systems.

*Table 26. Administration information*

<b>Name</b>	<b>Form number</b>	<b>PDF file name</b>
<i>IBM DB2 Universal Database Administration Guide: Planning</i>	SC09-4822	db2d1x81
<i>IBM DB2 Universal Database Administration Guide: Implementation</i>	SC09-4820	db2d2x81
<i>IBM DB2 Universal Database Administration Guide: Performance</i>	SC09-4821	db2d3x81
<i>IBM DB2 Universal Database Administrative API Reference</i>	SC09-4824	db2b0x81
<i>IBM DB2 Universal Database Data Movement Utilities Guide and Reference</i>	SC09-4830	db2dmx81
<i>IBM DB2 Universal Database Data Recovery and High Availability Guide and Reference</i>	SC09-4831	db2hax81
<i>IBM DB2 Universal Database Data Warehouse Center Administration Guide</i>	SC27-1123	db2ddx81
<i>IBM DB2 Universal Database SQL Reference, Volume 1</i>	SC09-4844	db2s1x81
<i>IBM DB2 Universal Database SQL Reference, Volume 2</i>	SC09-4845	db2s2x81
<i>IBM DB2 Universal Database System Monitor Guide and Reference</i>	SC09-4847	db2f0x81

## Application development information

The information in these books is of special interest to application developers or programmers working with DB2 Universal Database (DB2 UDB). You will find information about supported languages and compilers, as well as the documentation required to access DB2 UDB using the various supported programming interfaces, such as embedded SQL, ODBC, JDBC, SQLJ, and CLI. If you are using the DB2 Information Center, you can also access HTML versions of the source code for the sample programs.

*Table 27. Application development information*

<b>Name</b>	<b>Form number</b>	<b>PDF file name</b>
<i>IBM DB2 Universal Database Application Development Guide: Building and Running Applications</i>	SC09-4825	db2axx81
<i>IBM DB2 Universal Database Application Development Guide: Programming Client Applications</i>	SC09-4826	db2a1x81
<i>IBM DB2 Universal Database Application Development Guide: Programming Server Applications</i>	SC09-4827	db2a2x81
<i>IBM DB2 Universal Database Call Level Interface Guide and Reference, Volume 1</i>	SC09-4849	db2l1x81
<i>IBM DB2 Universal Database Call Level Interface Guide and Reference, Volume 2</i>	SC09-4850	db2l2x81
<i>IBM DB2 Universal Database Data Warehouse Center Application Integration Guide</i>	SC27-1124	db2adx81
<i>IBM DB2 XML Extender Administration and Programming</i>	SC27-1234	db2sxx81

## Business intelligence information

The information in these books describes how to use components that enhance the data warehousing and analytical capabilities of DB2 Universal Database.

*Table 28. Business intelligence information*

<b>Name</b>	<b>Form number</b>	<b>PDF file name</b>
<i>IBM DB2 Warehouse Manager Standard Edition Information Catalog Center Administration Guide</i>	SC27-1125	db2dix81
<i>IBM DB2 Warehouse Manager Standard Edition Installation Guide</i>	GC27-1122	db2idx81
<i>IBM DB2 Warehouse Manager Standard Edition Managing ETI Solution Conversion Programs with DB2 Warehouse Manager</i>	SC18-7727	iwhe1mstx80

## DB2 Connect information

The information in this category describes how to access data on mainframe and midrange servers using DB2 Connect Enterprise Edition or DB2 Connect Personal Edition.

Table 29. DB2 Connect information

Name	Form number	PDF file name
<i>IBM Connectivity Supplement</i>	No form number	db2h1x81
<i>IBM DB2 Connect Quick Beginnings for DB2 Connect Enterprise Edition</i>	GC09-4833	db2c6x81
<i>IBM DB2 Connect Quick Beginnings for DB2 Connect Personal Edition</i>	GC09-4834	db2c1x81
<i>IBM DB2 Connect User's Guide</i>	SC09-4835	db2c0x81

## Getting started information

The information in this category is useful when you are installing and configuring servers, clients, and other DB2 products.

Table 30. Getting started information

Name	Form number	PDF file name
<i>IBM DB2 Universal Database Quick Beginnings for DB2 Clients</i>	GC09-4832, not available in hardcopy	db2itx81
<i>IBM DB2 Universal Database Quick Beginnings for DB2 Servers</i>	GC09-4836	db2isx81
<i>IBM DB2 Universal Database Quick Beginnings for DB2 Personal Edition</i>	GC09-4838	db2i1x81
<i>IBM DB2 Universal Database Installation and Configuration Supplement</i>	GC09-4837, not available in hardcopy	db2iyx81
<i>IBM DB2 Universal Database Quick Beginnings for DB2 Data Links Manager</i>	GC09-4829	db2z6x81

## Tutorial information

Tutorial information introduces DB2 features and teaches how to perform various tasks.

Table 31. Tutorial information

Name	Form number	PDF file name
<i>Business Intelligence Tutorial: Introduction to the Data Warehouse</i>	No form number	db2tux81
<i>Business Intelligence Tutorial: Extended Lessons in Data Warehousing</i>	No form number	db2tax81

Table 31. Tutorial information (continued)

Name	Form number	PDF file name
Information Catalog Center Tutorial	No form number	db2aix81
Video Central for e-business Tutorial	No form number	db2twx81
Visual Explain Tutorial	No form number	db2tvx81

## Optional component information

The information in this category describes how to work with optional DB2 components.

Table 32. Optional component information

Name	Form number	PDF file name
IBM DB2 Cube Views Guide and Reference	SC18-7298	db2aax81
IBM DB2 Query Patroller Guide: Installation, Administration and Usage Guide	GC09-7658	db2dwx81
IBM DB2 Spatial Extender and Geodetic Extender User's Guide and Reference	SC27-1226	db2sbx81
IBM DB2 Universal Database Data Links Manager Administration Guide and Reference	SC27-1221	db2z0x82
DB2 Net Search Extender Administration and User's Guide	SH12-6740	N/A

**Note:** HTML for this document is *not* installed from the HTML documentation CD.

## Release notes

The release notes provide additional information specific to your product's release and FixPak level. The release notes also provide summaries of the documentation updates incorporated in each release, update, and FixPak.

Table 33. Release notes

Name	Form number	PDF file name
DB2 Release Notes	See note.	See note.
DB2 Installation Notes	Available on product CD-ROM only.	Not available.

**Note:** The Release Notes are available in:

- XHTML and Text format, on the product CDs
- PDF format, on the PDF Documentation CD

In addition the portions of the Release Notes that discuss *Known Problems and Workarounds* and *Incompatibilities Between Releases* also appear in the DB2 Information Center.

To view the Release Notes in text format on UNIX-based platforms, see the `Release.Notes` file. This file is located in the `DB2DIR/Readme/%L` directory, where `%L` represents the locale name and `DB2DIR` represents:

- For AIX operating systems: `/usr/opt/db2_08_01`
- For all other UNIX-based operating systems: `/opt/IBM/db2/V8.1`

**Related concepts:**

- “DB2 documentation and help” on page 301

**Related tasks:**

- “Printing DB2 books from PDF files” on page 317
- “Ordering printed DB2 books” on page 318
- “Invoking contextual help from a DB2 tool” on page 318

---

## Printing DB2 books from PDF files

You can print DB2 books from the PDF files on the *DB2 PDF Documentation CD*. Using Adobe Acrobat Reader, you can print either the entire book or a specific range of pages.

**Prerequisites:**

Ensure that you have Adobe Acrobat Reader installed. If you need to install Adobe Acrobat Reader, it is available from the Adobe Web site at [www.adobe.com](http://www.adobe.com)

**Procedure:**

To print a DB2 book from a PDF file:

1. Insert the *DB2 PDF Documentation CD*. On UNIX operating systems, mount the DB2 PDF Documentation CD. Refer to your *Quick Beginnings* book for details on how to mount a CD on UNIX operating systems.
2. Open `index.htm`. The file opens in a browser window.
3. Click on the title of the PDF you want to see. The PDF will open in Acrobat Reader.
4. Select **File** → **Print** to print any portions of the book that you want.

**Related concepts:**

- “DB2 Information Center” on page 302

**Related tasks:**

- “Mounting the CD-ROM (AIX)” in the *Quick Beginnings for DB2 Servers*
- “Mounting the CD-ROM (HP-UX)” in the *Quick Beginnings for DB2 Servers*
- “Mounting the CD-ROM (Linux)” in the *Quick Beginnings for DB2 Servers*
- “Ordering printed DB2 books” on page 318
- “Mounting the CD-ROM (Solaris Operating Environment)” in the *Quick Beginnings for DB2 Servers*

**Related reference:**

- “DB2 PDF and printed documentation” on page 312

---

## Ordering printed DB2 books

If you prefer to use hardcopy books, you can order them in one of three ways.

**Procedure:**

Printed books can be ordered in some countries or regions. Check the IBM Publications website for your country or region to see if this service is available in your country or region. When the publications are available for ordering, you can:

- Contact your IBM authorized dealer or marketing representative. To find a local IBM representative, check the IBM Worldwide Directory of Contacts at [www.ibm.com/planetwide](http://www.ibm.com/planetwide)
- Phone 1-800-879-2755 in the United States or 1-800-IBM-4YOU in Canada.
- Visit the IBM Publications Center at <http://www.ibm.com/shop/publications/order>. The ability to order books from the IBM Publications Center may not be available in all countries.

At the time the DB2 product becomes available, the printed books are the same as those that are available in PDF format on the *DB2 PDF Documentation CD*. Content in the printed books that appears in the *DB2 Information Center CD* is also the same. However, there is some additional content available in DB2 Information Center CD that does not appear anywhere in the PDF books (for example, SQL Administration routines and HTML samples). Not all books available on the DB2 PDF Documentation CD are available for ordering in hardcopy.

**Note:** The DB2 Information Center is updated more frequently than either the PDF or the hardcopy books; install documentation updates as they become available or refer to the DB2 Information Center at <http://publib.boulder.ibm.com/infocenter/db2help/> to get the most current information.

**Related tasks:**

- “Printing DB2 books from PDF files” on page 317

**Related reference:**

- “DB2 PDF and printed documentation” on page 312

---

## Invoking contextual help from a DB2 tool

Contextual help provides information about the tasks or controls that are associated with a particular window, notebook, wizard, or advisor. Contextual help is available from DB2 administration and development tools that have graphical user interfaces. There are two types of contextual help:

- Help accessed through the **Help** button that is located on each window or notebook
- Infopops, which are pop-up information windows displayed when the mouse cursor is placed over a field or control, or when a field or control is selected in a window, notebook, wizard, or advisor and F1 is pressed.

The **Help** button gives you access to overview, prerequisite, and task information. The infopops describe the individual fields and controls.

**Procedure:**

To invoke contextual help:

- For window and notebook help, start one of the DB2 tools, then open any window or notebook. Click the **Help** button at the bottom right corner of the window or notebook to invoke the contextual help.

You can also access the contextual help from the **Help** menu item at the top of each of the DB2 tools centers.

Within wizards and advisors, click on the Task Overview link on the first page to view contextual help.

- For infopop help about individual controls on a window or notebook, click the control, then click F1. Pop-up information containing details about the control is displayed in a yellow window.

**Note:** To display infopops simply by holding the mouse cursor over a field or control, select the **Automatically display infopops** check box on the **Documentation** page of the Tool Settings notebook.

Similar to infopops, diagnosis pop-up information is another form of context-sensitive help; they contain data entry rules. Diagnosis pop-up information is displayed in a purple window that appears when data that is not valid or that is insufficient is entered. Diagnosis pop-up information can appear for:

- Compulsory fields.
- Fields whose data follows a precise format, such as a date field.

**Related tasks:**

- “Invoking the DB2 Information Center” on page 310
- “Invoking message help from the command line processor” on page 319
- “Invoking command help from the command line processor” on page 320
- “Invoking SQL state help from the command line processor” on page 320

---

## Invoking message help from the command line processor

Message help describes the cause of a message and describes any action you should take in response to the error.

**Procedure:**

To invoke message help, open the command line processor and enter:

```
? XXXnnnnn
```

where *XXXnnnnn* represents a valid message identifier.

For example, ? SQL30081 displays help about the SQL30081 message.

**Related tasks:**

- “Invoking contextual help from a DB2 tool” on page 318
- “Invoking the DB2 Information Center” on page 310
- “Invoking command help from the command line processor” on page 320

- “Invoking SQL state help from the command line processor” on page 320

**Related reference:**

- “db2 - Command Line Processor Invocation Command” in the *Command Reference*

---

## Invoking command help from the command line processor

Command help explains the syntax of commands in the command line processor.

**Procedure:**

To invoke command help, open the command line processor and enter:

```
? command
```

where *command* represents a keyword or the entire command.

For example, ? catalog displays help for all of the CATALOG commands, while ? catalog database displays help only for the CATALOG DATABASE command.

**Related tasks:**

- “Invoking contextual help from a DB2 tool” on page 318
- “Invoking the DB2 Information Center” on page 310
- “Invoking message help from the command line processor” on page 319
- “Invoking SQL state help from the command line processor” on page 320

**Related reference:**

- “db2 - Command Line Processor Invocation Command” in the *Command Reference*

---

## Invoking SQL state help from the command line processor

DB2 Universal Database returns an SQLSTATE value for conditions that could be the result of an SQL statement. SQLSTATE help explains the meanings of SQL states and SQL state class codes.

**Procedure:**

To invoke SQL state help, open the command line processor and enter:

```
? sqlstate or ? class code
```

where *sqlstate* represents a valid five-digit SQL state and *class code* represents the first two digits of the SQL state.

For example, ? 08003 displays help for the 08003 SQL state, and ? 08 displays help for the 08 class code.

**Related tasks:**

- “Invoking the DB2 Information Center” on page 310
- “Invoking message help from the command line processor” on page 319
- “Invoking command help from the command line processor” on page 320

---

## DB2 tutorials

The DB2<sup>®</sup> tutorials help you learn about various aspects of DB2 Universal Database. The tutorials provide lessons with step-by-step instructions in the areas of developing applications, tuning SQL query performance, working with data warehouses, managing metadata, and developing Web services using DB2.

### Before you begin:

You can view the XHTML versions of the tutorials from the Information Center at <http://publib.boulder.ibm.com/infocenter/db2help/>.

Some tutorial lessons use sample data or code. See each tutorial for a description of any prerequisites for its specific tasks.

### DB2 Universal Database tutorials:

Click on a tutorial title in the following list to view that tutorial.

*Business Intelligence Tutorial: Introduction to the Data Warehouse Center*  
Perform introductory data warehousing tasks using the Data Warehouse Center.

*Business Intelligence Tutorial: Extended Lessons in Data Warehousing*  
Perform advanced data warehousing tasks using the Data Warehouse Center.

*Information Catalog Center Tutorial*  
Create and manage an information catalog to locate and use metadata using the Information Catalog Center.

*Visual Explain Tutorial*  
Analyze, optimize, and tune SQL statements for better performance using Visual Explain.

---

## DB2 troubleshooting information

A wide variety of troubleshooting and problem determination information is available to assist you in using DB2<sup>®</sup> products.

### DB2 documentation

Troubleshooting information can be found throughout the DB2 Information Center, as well as throughout the PDF books that make up the DB2 library. You can refer to the "Support and troubleshooting" branch of the DB2 Information Center navigation tree (in the left pane of your browser window) to see a complete listing of the DB2 troubleshooting documentation.

### DB2 Technical Support Web site

Refer to the DB2 Technical Support Web site if you are experiencing problems and want help finding possible causes and solutions. The Technical Support site has links to the latest DB2 publications, TechNotes, Authorized Program Analysis Reports (APARs), FixPaks and the latest listing of internal DB2 error codes, and other resources. You can search through this knowledge base to find possible solutions to your problems.

Access the DB2 Technical Support Web site at <http://www.ibm.com/software/data/db2/udb/winos2unix/support>

## DB2 Problem Determination Tutorial Series

Refer to the DB2 Problem Determination Tutorial Series Web site to find information on how to quickly identify and resolve problems you might encounter while working with DB2 products. One tutorial introduces you to the DB2 problem determination facilities and tools available, and helps you decide when to use them. Other tutorials deal with related topics, such as "Database Engine Problem Determination", "Performance Problem Determination", and "Application Problem Determination".

See the full set of DB2 problem determination tutorials on the DB2 Technical Support site at <http://www.ibm.com/software/data/support/pdm/db2tutorials.html>

### Related concepts:

- "DB2 Information Center" on page 302
- "Introduction to problem determination - DB2 Technical Support tutorial" in the *Troubleshooting Guide*

---

## Accessibility

Accessibility features help users with physical disabilities, such as restricted mobility or limited vision, to use software products successfully. The following list specifies the major accessibility features in DB2<sup>®</sup> Version 8 products:

- All DB2 functionality is available using the keyboard for navigation instead of the mouse. For more information, see "Keyboard input and navigation."
- You can customize the size and color of the fonts on DB2 user interfaces. For more information, see "Accessible display" on page 323.
- DB2 products support accessibility applications that use the Java<sup>™</sup> Accessibility API. For more information, see "Compatibility with assistive technologies" on page 323.
- DB2 documentation is provided in an accessible format. For more information, see "Accessible documentation" on page 323.

## Keyboard input and navigation

### Keyboard input

You can operate the DB2 tools using only the keyboard. You can use keys or key combinations to perform operations that can also be done using a mouse. Standard operating system keystrokes are used for standard operating system operations.

For more information about using keys or key combinations to perform operations, see Keyboard shortcuts and accelerators: Common GUI help.

### Keyboard navigation

You can navigate the DB2 tools user interface using keys or key combinations.

For more information about using keys or key combinations to navigate the DB2 Tools, see Keyboard shortcuts and accelerators: Common GUI help.

### Keyboard focus

In UNIX<sup>®</sup> operating systems, the area of the active window where your keystrokes will have an effect is highlighted.

## Accessible display

The DB2 tools have features that improve accessibility for users with low vision or other visual impairments. These accessibility enhancements include support for customizable font properties.

### Font settings

You can select the color, size, and font for the text in menus and dialog windows, using the Tools Settings notebook.

For more information about specifying font settings, see *Changing the fonts for menus and text: Common GUI help*.

### Non-dependence on color

You do not need to distinguish between colors in order to use any of the functions in this product.

## Compatibility with assistive technologies

The DB2 tools interfaces support the Java Accessibility API, which enables you to use screen readers and other assistive technologies with DB2 products.

## Accessible documentation

Documentation for DB2 is provided in XHTML 1.0 format, which is viewable in most Web browsers. XHTML allows you to view documentation according to the display preferences set in your browser. It also allows you to use screen readers and other assistive technologies.

Syntax diagrams are provided in dotted decimal format. This format is available only if you are accessing the online documentation using a screen-reader.

### Related concepts:

- “Dotted decimal syntax diagrams” on page 323

---

## Dotted decimal syntax diagrams

Syntax diagrams are provided in dotted decimal format for users accessing the Information Center using a screen reader.

In dotted decimal format, each syntax element is written on a separate line. If two or more syntax elements are always present together (or always absent together), they can appear on the same line, because they can be considered as a single compound syntax element.

Each line starts with a dotted decimal number; for example, 3 or 3.1 or 3.1.1. To hear these numbers correctly, make sure that your screen reader is set to read out punctuation. All the syntax elements that have the same dotted decimal number (for example, all the syntax elements that have the number 3.1) are mutually exclusive alternatives. If you hear the lines 3.1 USERID and 3.1 SYSTEMID, you know that your syntax can include either USERID or SYSTEMID, but not both.

The dotted decimal numbering level denotes the level of nesting. For example, if a syntax element with dotted decimal number 3 is followed by a series of syntax elements with dotted decimal number 3.1, all the syntax elements numbered 3.1 are subordinate to the syntax element numbered 3.

Certain words and symbols are used next to the dotted decimal numbers to add information about the syntax elements. Occasionally, these words and symbols might occur at the beginning of the element itself. For ease of identification, if the word or symbol is a part of the syntax element, it is preceded by the backslash (\) character. The \* symbol can be used next to a dotted decimal number to indicate that the syntax element repeats. For example, syntax element \*FILE with dotted decimal number 3 is given the format 3 \\* FILE. Format 3\* FILE indicates that syntax element FILE repeats. Format 3\* \\* FILE indicates that syntax element \* FILE repeats.

Characters such as commas, which are used to separate a string of syntax elements, are shown in the syntax just before the items they separate. These characters can appear on the same line as each item, or on a separate line with the same dotted decimal number as the relevant items. The line can also show another symbol giving information about the syntax elements. For example, the lines 5.1\*, 5.1 LASTRUN, and 5.1 DELETE mean that if you use more than one of the LASTRUN and DELETE syntax elements, the elements must be separated by a comma. If no separator is given, assume that you use a blank to separate each syntax element.

If a syntax element is preceded by the % symbol, this indicates a reference that is defined elsewhere. The string following the % symbol is the name of a syntax fragment rather than a literal. For example, the line 2.1 %OP1 means that you should refer to separate syntax fragment OP1.

The following words and symbols are used next to the dotted decimal numbers:

- ? means an optional syntax element. A dotted decimal number followed by the ? symbol indicates that all the syntax elements with a corresponding dotted decimal number, and any subordinate syntax elements, are optional. If there is only one syntax element with a dotted decimal number, the ? symbol is displayed on the same line as the syntax element, (for example 5? NOTIFY). If there is more than one syntax element with a dotted decimal number, the ? symbol is displayed on a line by itself, followed by the syntax elements that are optional. For example, if you hear the lines 5 ?, 5 NOTIFY, and 5 UPDATE, you know that syntax elements NOTIFY and UPDATE are optional; that is, you can choose one or none of them. The ? symbol is equivalent to a bypass line in a railroad diagram.
- ! means a default syntax element. A dotted decimal number followed by the ! symbol and a syntax element indicates that the syntax element is the default option for all syntax elements that share the same dotted decimal number. Only one of the syntax elements that share the same dotted decimal number can specify a ! symbol. For example, if you hear the lines 2? FILE, 2.1! (KEEP), and 2.1 (DELETE), you know that (KEEP) is the default option for the FILE keyword. In this example, if you include the FILE keyword but do not specify an option, default option KEEP will be applied. A default option also applies to the next higher dotted decimal number. In this example, if the FILE keyword is omitted, default FILE(KEEP) is used. However, if you hear the lines 2? FILE, 2.1, 2.1.1! (KEEP), and 2.1.1 (DELETE), the default option KEEP only applies to the next higher dotted decimal number, 2.1 (which does not have an associated keyword), and does not apply to 2? FILE. Nothing is used if the keyword FILE is omitted.
- \* means a syntax element that can be repeated 0 or more times. A dotted decimal number followed by the \* symbol indicates that this syntax element can be used zero or more times; that is, it is optional and can be repeated. For example, if you hear the line 5.1\* data area, you know that you can include one

| data area, more than one data area, or no data area. If you hear the lines 3\*, 3  
| HOST, and 3 STATE, you know that you can include HOST, STATE, both  
| together, or nothing.

| **Notes:**

- | 1. If a dotted decimal number has an asterisk (\*) next to it and there is only one  
| item with that dotted decimal number, you can repeat that same item more  
| than once.
  - | 2. If a dotted decimal number has an asterisk next to it and several items have  
| that dotted decimal number, you can use more than one item from the list,  
| but you cannot use the items more than once each. In the previous example,  
| you could write HOST STATE, but you could not write HOST HOST.
  - | 3. The \* symbol is equivalent to a loop-back line in a railroad syntax diagram.
- | • + means a syntax element that must be included one or more times. A dotted  
| decimal number followed by the + symbol indicates that this syntax element  
| must be included one or more times; that is, it must be included at least once  
| and can be repeated. For example, if you hear the line 6.1+ data area, you must  
| include at least one data area. If you hear the lines 2+, 2 HOST, and 2 STATE,  
| you know that you must include HOST, STATE, or both. Similar to the \* symbol,  
| the + symbol can only repeat a particular item if it is the only item with that  
| dotted decimal number. The + symbol, like the \* symbol, is equivalent to a  
| loop-back line in a railroad syntax diagram.

| **Related reference:**

- | • "How to read the syntax diagrams" in the *SQL Reference, Volume 2*

---

## | **Common Criteria certification of DB2 Universal Database products**

| DB2 Universal Database is being evaluated for certification under the Common  
| Criteria at evaluation assurance level 4 (EAL4). For more information about  
| Common Criteria, see the Common Criteria web site at: [http://niap.nist.gov/cc-  
| scheme/](http://niap.nist.gov/cc-scheme/).



---

## Appendix I. Notices

IBM may not offer the products, services, or features discussed in this document in all countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, NY 10504-1785  
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country/region or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106, Japan

**The following paragraph does not apply to the United Kingdom or any other country/region where such provisions are inconsistent with local law:**  
INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions; therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product, and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information that has been exchanged, should contact:

IBM Canada Limited  
Office of the Lab Director  
8200 Warden Avenue  
Markham, Ontario  
L6G 1C7  
CANADA

Such information may be available, subject to appropriate terms and conditions, including in some cases payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems, and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements, or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility, or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information may contain examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious, and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### COPYRIGHT LICENSE:

This information may contain sample application programs, in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as follows:

© (your company name) (year). Portions of this code are derived from IBM Corp. Sample Programs. © Copyright IBM Corp. *\_enter the year or years\_*. All rights reserved.

---

## Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States, other countries, or both, and have been used in at least one of the documents in the DB2 UDB documentation library.

ACF/VTAM	iSeries
AISPO	LAN Distance
AIX	MVS
AIXwindows	MVS/ESA
AnyNet	MVS/XA
APPN	Net.Data
AS/400	NetView
BookManager	OS/390
C Set++	OS/400
C/370	PowerPC
CICS	pSeries
Database 2	QBIC
DataHub	QMF
DataJoiner	RACF
DataPropagator	RISC System/6000
DataRefresher	RS/6000
DB2	S/370
DB2 Connect	SP
DB2 Extenders	SQL/400
DB2 OLAP Server	SQL/DS
DB2 Information Integrator	System/370
DB2 Query Patroller	System/390
DB2 Universal Database	SystemView
Distributed Relational Database Architecture	Tivoli
DRDA	VisualAge
eServer	VM/ESA
Extended Services	VSE/ESA
FFST	VTAM
First Failure Support Technology	WebExplorer
IBM	WebSphere
IMS	WIN-OS/2
IMS/ESA	z/OS
	zSeries

The following terms are trademarks or registered trademarks of other companies and have been used in at least one of the documents in the DB2 UDB documentation library:

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

Intel and Pentium are trademarks of Intel Corporation in the United States, other countries, or both.

Java and all Java-based trademarks are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, or service names may be trademarks or service marks of others.

---

# Index

## A

- accessibility
  - dotted decimal syntax diagrams 323
  - features 322
- anyorder file type modifier 100, 123
- APIs
  - db2Load 123
  - db2LoadQuery 145
  - sqluexpr 12
  - sqluimpr 48
- application record, PC/IXF 254
- ASC data type descriptions 250
- ASC file
  - format 249
  - sample 249
- ASC import file type 35

## B

- binarynumerics file type modifier 100, 123
- bind files
  - used by export, import, load 297
- buffered inserts
  - import utility 29
- building indexes 86

## C

- character strings
  - delimiter 245
- chardel file type modifier
  - export 8, 12
  - import 35, 48
  - load 100, 123
- code page file type modifier 100, 123
- code pages
  - conversion
    - files 279
    - when importing or loading PC/IXF data 279
  - Export API 12
  - EXPORT command 8
  - Import API 48
  - IMPORT command 35
  - import utility considerations 68
  - load utility considerations 165
- codeldel file type modifier
  - export 8, 12
  - import 35, 48
  - load 100, 123
- column descriptor record, PC/IXF 254
- columns
  - incompatible 279
  - specifying for import 48
  - values, invalid 279
- command help
  - invoking 320
- command syntax
  - interpreting 227

- commands
  - db2move 209
  - db2relocatedb 213
    - EXPORT 8
    - IMPORT 35
    - LOAD 100
    - LOAD QUERY 121
- completion messages 299
- compound file type modifier 35, 48
- constraints
  - checking
    - after load operations 91
- continuation record type, PC/IXF 254
- CURSOR file type
  - data movement 226

## D

- data
  - moving across platforms 205
- Data Links Manager
  - moving data 201
- data record, PC/IXF 254
- data transfer
  - across platforms 205
  - between host and workstation 206
- data type descriptions
  - ASC 250
  - DEL file formats 246
  - PC/IXF 275
- data types
  - PC/IXF 270
- Data Warehouse Center
  - moving data 224
  - overview 224
- database movement tool command 209
- databases
  - exporting table to a file 8, 12
  - importing file to table 35, 48
  - loading file to table 100
  - nonrecoverable load options 74
  - recoverable load options 74
  - warehouse 224
- dateformat file type modifier 35, 48, 100, 123
- datesiso file type modifier 8, 12, 35, 48, 100, 123
- DB2 books
  - printing PDF files 317
- DB2 Data Links Manager
  - export utility 199
  - exporting between instances 199
  - import utility 202
  - load utility 203
- DB2 Information Center 302
  - invoking 310
- DB2 tutorials 321
- db2Load API 123
- db2LoadQuery API 145
- DB2LOADREC registry variable 98
- db2move command 209

- db2relocatedb command 213
- decplusblank file type modifier 8, 12, 35, 48, 100, 123
- decpt file type modifier 8, 12, 35, 48, 100, 123
- DEL data type descriptions 246
- DEL file
  - format 244
  - sample 245
- delimited ASCII (DEL) file format 244
  - moving data across platforms 205
- delimiter character string 245
- delprioritychar file type modifier 35, 48, 100, 123
- disability 322
- dldel file type modifier 8, 12, 35, 48, 100, 123
- documentation
  - displaying 310
- dotted decimal syntax diagrams 323
- dump files
  - load utility 160
- dumpfile file type modifier 100, 123

## E

- error messages
  - overview 299
- exception tables
  - load utility 160
- Export API 12
- EXPORT command 8
- export message files 1, 25, 74
- export operations, Data Warehouse Center 224
- EXPORT utility
  - authorities and privileges required to use 2
  - DB2 Data Links Manager 199
  - file formats 243
  - identity columns 4
  - large objects (LOBs) 4
  - overview 1
  - parallel export using db2batch 5
  - recreating an exported table 4
  - restrictions 3
  - transferring data between host and workstation 206
- exported tables
  - recreating using EXPORT utility 4
  - recreating using import utility 32
  - recreating when table attributes not stored in an IXF file 32
  - recreating when table attributes stored in an IXF file 32
- exporting
  - database tables files 8, 12
  - DB2 Data Links Manager considerations 8
  - file type modifiers for 8, 12
  - specifying column names 12

## F

- fastparse file type modifier 100, 123
- file formats
  - delimited ASCII (DEL) 244
  - exporting table to file 8
  - importing file to table 35
  - nondelimited ASCII (ASC) 249
  - PC version of IXF (PC/IXF) 252
  - worksheet (WSF) 290
- file type modifiers
  - Export API 12
  - EXPORT utility 8
  - Import API 48
  - IMPORT command 35
  - Load API 123
  - LOAD command 100
- forcein file type modifier 35, 48, 100, 123, 283

## G

- generated columns
  - using import utility 31
  - using load utility 89
- generatedignore file type modifier 35, 48, 100, 123
- generatedmissing file type modifier 35, 48, 100, 123
- generatedoverride file type modifier 100, 123

## H

- header record, PC/IXF 254
- help
  - displaying 310, 311
  - for commands
    - invoking 320
  - for messages
    - invoking 319
  - for SQL statements
    - invoking 320
- hierarchy record, PC/IXF 254
- HTML documentation
  - updating 311

## I

- IBM Relational Data Replication Tools
  - components 224
  - overview 222
- identity columns 4
  - using import utility 29
  - using load utility 87
- identity record, PC/IXF 254
- identityignore 35
- identityignore file type modifier 48, 100, 123
- identitymissing file type modifier 35, 48, 100, 123
- identityoverride file type modifier 100, 123
- implieddecimal file type modifier 35, 48, 100, 123
- Import API 48

- IMPORT command 35
- import message files 1, 25, 74
- IMPORT utility
  - authorities 26
  - buffered inserts 29
  - client/server 28
  - code page considerations 68
  - compared to load utility 231
  - DB2 Data Links Manager 202
  - file formats 243
  - generated columns 31
  - identity columns 29
  - large objects (LOBs) 33
  - limitations 27
  - optimizing performance 25
  - overview 25
  - performance 25
  - privileges 26
  - recreating an exported table 32
  - remote database 28
  - restrictions 27
  - table locking 34
  - transferring data between host and workstation 206
  - user-defined distinct types (UDTs) 34
- importing
  - code page considerations 48
  - data 35
  - database access through DB2 Connect 48
  - DB2 Data Links Manager considerations 48
  - file to database table 48
  - file type modifiers for 48
  - of PC/IXF files, with forcein 283
  - PC/IXF files, data type-specific rules 281
  - PC/IXF files, general rules 279
  - PC/IXF, multiple-part files 48
  - restrictions 48
  - to a remote database 48
  - to a table or hierarchy that does not exist 48
  - to typed tables 48
- incompatible columns 279
- index record, PC/IXF 254
- indexes
  - building 86
- indexfreespace file type modifier 100, 123
- indexixf file type modifier 35, 48
- indexschema file type modifier 35, 48
- indicator, record length 252
- Information Center
  - installing 303, 305, 308
- installing
  - Information Center 303, 305, 308
- Integration Exchange Format (IXF) 252
- integrity checking 91
- invoking
  - command help 320
  - message help 319
  - SQL statement help 320

## K

- keepblanks file type modifier 35, 48, 100, 123
- keyboard shortcuts
  - support for 322
- keywords
  - syntax 227

## L

- large object (LOB) data types
  - exporting 4
  - importing 33
- Load API 123
- LOAD command 100
  - in a partitioned database environment 179, 195
- load copy location file, using rollforward 98
- load delete start compensation log record 162
- load message files 1, 25, 74
- load operations, Data Warehouse Center 224
- load pending list log record 162
- Load Query API 145
- LOAD QUERY command 121
  - in a partitioned database environment 184
- load start log record 162
- load utility
  - authorities and privileges required to use 81
  - build phase 74
  - changed syntax and behavior 74
  - code page considerations 165
  - compared to import utility 231
  - database recovery 74
  - DB2 Data Links Manager 203
  - delete phase 74
  - dump file 160
  - exception table 160
  - file formats 243
  - file type modifiers for 123
  - generated columns 89
  - identity columns 87
  - index copy phase 74
  - limitations 81
  - load phase 74
  - log records 162
  - optimizing performance 166
  - overview 74
  - parallelism 80
  - process overview 74
  - recovery from failure 97
  - restrictions 81
  - table locking 162
  - table states 162
  - temporary files 100, 161
- loading
  - data
    - partitions 177
    - file to database table 100
    - file type modifiers for 100
  - loading data
    - partitions 197

- LOB (large object) data types
  - exporting 4
  - importing 33
- LOB Location Specifier (LLS) 252
- lobsinfile
  - Export API 12
- lobsinfile file type modifier 8, 35, 48, 100, 123
- locking
  - import utility 34
  - table level 162
- log records
  - load utility 162

## M

- materialized query tables (MQT)
  - check pending state 94
  - dependent immediate 94
  - refreshing 94
- message files
  - export, import, and load 1, 25, 74
- message help
  - invoking 319
- messages
  - overview 299
- modifiers
  - file type
    - EXPORT command 8
    - IMPORT command 35
    - LOAD command 100
- modifiers file type
  - export utility 12
  - for import utility 48
  - Load API 123
- moving data
  - between databases 35, 48
- multidimensional clustering (MDC)
  - considerations 96

## N

- nochecklengths file type modifier 35, 48, 100, 123
- nodefaults file type modifier 35, 48
- nodoubleledel file type modifier 8, 12, 35, 48, 100, 123
- noeofchar file type modifier 35, 48, 100, 123
- noheader file type modifier 100, 123
- non-delimited ASCII (ASC) file
  - format 249
- non-identity generated columns 31, 89
- non-recoverable database
  - load options 74
- norowwarnings file type modifier 100, 123
- notypeid file type modifier 35, 48
- nullindchar file type modifier 35, 48, 100, 123

## O

- online
  - help, accessing 318

- options
  - forcein 283
- ordering DB2 books 318

## P

- packeddecimal file type modifier 100, 123
- pagefreespace file type modifier 100, 123
- parallel export using db2batch 5
- parallelism
  - load utility 80
- parameters
  - syntax 227
- partitioned database environments
  - loading data 195, 197
  - monitoring load operations 184
- partitioned databases
  - load restrictions 179
- partitioning data
  - loading data 177
- partitioning keys
  - loading data 177
- PC version of IXF (PC/IXF) file
  - format 252
- PC/IXF
  - code page conversion files 279
  - column values, invalid 279
  - contrasted with System370 IXF 290
  - data types 275
    - valid 270
  - invalid
    - column values 279
    - data types 270, 279
    - record types 254
- PC/IXF file format
  - description 252
  - moving data across platforms 205
- PC/IXF file import
  - data type-specific rules 281
  - rules 279, 281
  - with forcein 283
- pending states 165
- performance
  - importing 25
  - load utility 166
- printed books, ordering 318
- printing
  - PDF files 317
- privileges
  - export 2
  - import 26
  - LOAD 81
- problem determination
  - online information 321
  - tutorials 321

## R

- reclen file type modifier 35
  - importing 48
  - Load API 123
  - loading 100
- record length indicator 252

- record type, PC/IXF
  - application 254
  - column descriptor 254
  - continuation 254
  - data 254
  - header 254
  - hierarchy 254
  - identity 254
  - index 254
  - list 252
  - subtable 254
  - table 254
  - terminate 254
- recoverable databases
  - load options 74
- registry variables
  - DB2LOADREC 98
- Relocate Database command 213
- replication
  - Data Warehouse Center
    - types supported 224
- Restarting a load operation
  - allow read access mode 97
  - partitioned database load
    - operations 186
- rollforward utility
  - load copy location file, using 98

## S

- samples
  - files
    - ASC 249
    - DEL 245
- SELECT statement
  - in EXPORT command 8
- semantics
  - forcein, code page 283
  - forcein, data type 283
  - forcein, general 283
- SQL messages 299
- SQL statement help
  - invoking 320
- SQLCODE
  - overview 299
- SQLSTATE
  - overview 299
- sqluxpr API 12
- sqlimpr API 48
- staging tables
  - dependent immediate 95
  - propagating 95
- states
  - backup pending 165
  - check pending 165
  - delete pending 165
  - load pending 165
- stored procedures
  - transformer 224
- striptblanks file type modifier 35, 48, 100, 123
- striptnulls file type modifier 35, 48, 100, 123
- structure
  - delimited ASCII (DEL) files 244
  - non-delimited ASCII (ASC) files 249

- subtable record, PC/IXF
  - overview 254
- subtableconvert file type modifier 100
- summary tables
  - import restriction 27
- syntax
  - changes, LOAD utility 74
- syntax diagrams
  - reading 227
- System370 IXF
  - contrasted with PC/IXF 290
  - contrasted with System370 290

## T

- table load delete start log record 162
- table record, PC/IXF 254
- table spaces
  - states 162
- tables
  - exported, recreating 32
  - exporting to files 8, 12
  - importing files 35, 48
  - loading files to 100
  - locking 162
  - states 162
- temporary files
  - LOAD command 100
  - load utility 161
- terminate record, PC/IXF 254
- termination
  - load operations
    - allow read access mode 97
    - in partitioned databases 186
- timeformat file type modifier 35, 48, 100, 123
- timestampformat file type modifier 35, 48, 100, 123
- totalfreespace file type modifier 100, 123
- transformers
  - stored procedures 224
- traverse order
  - default 219
  - typed tables 25, 219
  - user-specified 219
- troubleshooting
  - online information 321
  - tutorials 321
- tutorials 321
  - troubleshooting and problem determination 321
- typed tables
  - data movement examples 221
  - exporting 218
  - importing 218
  - moving data between 218
  - selecting during data movement 220
  - traverse order 25, 219

## U

- Unicode (UCS-2)
  - data movement considerations 293
- Updating
  - HMTL documentation 311

- usedefaults file type modifier 35, 48, 100, 123
- user-defined types (UDTs)
  - distinct types
    - importing 34
- utilities
  - file formats 243

## V

- valid PC/IXF data type 270
- variables
  - syntax 227

## W

- warning messages
  - overview 299
- worksheets
  - file format (WSF) 290
- WSF (worksheet) file format
  - description 290
  - moving data across platforms 205

## Z

- zoned decimal file type modifier 100, 123

---

## Contacting IBM

In the United States, call one of the following numbers to contact IBM:

- 1-800-IBM-SERV (1-800-426-7378) for customer service
- 1-888-426-4343 to learn about available service options
- 1-800-IBM-4YOU (426-4968) for DB2 marketing and sales

In Canada, call one of the following numbers to contact IBM:

- 1-800-IBM-SERV (1-800-426-7378) for customer service
- 1-800-465-9600 to learn about available service options
- 1-800-IBM-4YOU (1-800-426-4968) for DB2 marketing and sales

To locate an IBM office in your country or region, check IBM's Directory of Worldwide Contacts on the web at <http://www.ibm.com/planetwide>

---

## Product information

Information regarding DB2 Universal Database products is available by telephone or by the World Wide Web at <http://www.ibm.com/software/data/db2/udb>

This site contains the latest information on the technical library, ordering books, product downloads, newsgroups, FixPaks, news, and links to web resources.

If you live in the U.S.A., then you can call one of the following numbers:

- 1-800-IBM-CALL (1-800-426-2255) to order products or to obtain general information.
- 1-800-879-2755 to order publications.

For information on how to contact IBM outside of the United States, go to the IBM Worldwide page at [www.ibm.com/planetwide](http://www.ibm.com/planetwide)







Printed in USA

SC09-4830-01



Spine information:



IBM® DB2 Universal Database™

Data Movement Utilities

Version 8.2